



# Scientific Data Formats

RSI

IDL Version 6.3  
April 2006 Edition  
Copyright © RSI  
All Rights Reserved

## Restricted Rights Notice

The IDL<sup>®</sup>, ION Script<sup>™</sup>, and ION Java<sup>™</sup> software programs and the accompanying procedures, functions, and documentation described herein are sold under license agreement. Their use, duplication, and disclosure are subject to the restrictions stated in the license agreement. RSI reserves the right to make changes to this document at any time and without notice.

## Limitation of Warranty

RSI makes no warranties, either express or implied, as to any matter not expressly set forth in the license agreement, including without limitation the condition of the software, merchantability, or fitness for any particular purpose.

RSI shall not be liable for any direct, consequential, or other damages suffered by the Licensee or any others resulting from use of the IDL or ION software packages or their documentation.

## Permission to Reproduce this Manual

If you are a licensed user of this product, RSI grants you a limited, nontransferable license to reproduce this particular document provided such copies are for your use only and are not sold or distributed to third parties. All such copies must contain the title page and this notice page in their entirety.

## Acknowledgments

IDL<sup>®</sup> is a registered trademark and ION<sup>™</sup>, ION Script<sup>™</sup>, ION Java<sup>™</sup>, are trademarks of ITT Industries, registered in the United States Patent and Trademark Office, for the computer program described herein.

Numerical Recipes<sup>™</sup> is a trademark of Numerical Recipes Software. Numerical Recipes routines are used by permission.

GRG2<sup>™</sup> is a trademark of Windward Technologies, Inc. The GRG2 software for nonlinear optimization is used by permission.

NCSA Hierarchical Data Format (HDF) Software Library and Utilities  
Copyright 1988-2001 The Board of Trustees of the University of Illinois  
All rights reserved.

NCSA HDF5 (Hierarchical Data Format 5) Software Library and Utilities  
Copyright 1998-2002 by the Board of Trustees of the University of Illinois. All rights reserved.

CDF Library  
Copyright © 2002 National Space Science Data Center  
NASA/Goddard Space Flight Center

NetCDF Library  
Copyright © 1993-1999 University Corporation for Atmospheric Research/Unidata

HDF EOS Library  
Copyright © 1996 Hughes and Applied Research Corporation

This software is based in part on the work of the Independent JPEG Group.

Portions of this software are copyrighted by DataDirect Technologies, 1991-2003.

Portions of this software were developed using Unisearch's Kakadu software, for which Kodak has a commercial license. Kakadu Software. Copyright © 2001. The University of New South Wales, UNSW, Sydney NSW 2052, Australia, and Unisearch Ltd, Australia.

Portions of this computer program are copyright © 1995-1999 LizardTech, Inc. All rights reserved. MrSID is protected by U.S. Patent No. 5,710,835. Foreign Patents Pending.

Portions of this software are copyrighted by Merge Technologies Incorporated.

IDL Wavelet Toolkit Copyright © 2002 Christopher Torrence.

Other trademarks and registered trademarks are the property of the respective trademark holders.



# Contents

<b>Chapter 1</b>	
<b>Scientific Data Formats Overview .....</b>	<b>19</b>
CDF—Common Data Format .....	19
HDF—Hierarchical Data Format .....	20
HDF-EOS—Hierarchical Data Format - Earth Observing System .....	20
NetCDF—Network Common Data Format .....	21
<b>Chapter 2</b>	
<b>Common Data Format .....</b>	<b>23</b>
Overview of the Common Data Format .....	24
Variables and Attributes .....	25
Variables .....	25
rVariables .....	25
zVariables .....	25
Attributes .....	26
Specifying Attributes and Variables .....	26

CDF File Options .....	27
File Type .....	27
Data Encodings/Decodings .....	27
Creating CDF Files .....	28
Reading CDF Files .....	28
Type Conversion .....	29
Example: Creating a CDF File .....	29
Alphabetical Listing of CDF Routines .....	30
CDF_ATTCREATE .....	32
CDF_ATTDELETE .....	34
CDF_ATT EXISTS .....	36
CDF_ATTGET .....	38
CDF_ATTINQ .....	40
CDF_ATTNUM .....	42
CDF_ATTPUT .....	43
CDF_ATTRENAME .....	46
CDF_CLOSE .....	47
CDF_COMPRESSION .....	48
CDF_CONTROL .....	53
CDF_CREATE .....	60
CDF_DELETE .....	67
CDF_DOC .....	68
CDF_ENCODE_EPOCH .....	70
CDF_ENCODE_EPOCH16 .....	73
CDF_EPOCH .....	75
CDF_EPOCH16 .....	78
CDF_ERROR .....	82
CDF_EXISTS .....	83
CDF_INQUIRE .....	84
CDF_LIB_INFO .....	87
CDF_OPEN .....	89
CDF_PARSE_EPOCH .....	90
CDF_PARSE_EPOCH16 .....	92
CDF_SET_CDF27_BACKWARD_COMPATIBLE .....	94
CDF_VARCREATE .....	96
CDF_VARDELETE .....	100

CDF_VARGET .....	103
CDF_VARGET1 .....	107
CDF_VARINQ .....	109
CDF_VARNUM .....	111
CDF_VARPUT .....	113
CDF_VARRENAME .....	115

### Chapter 3

## **Hierarchical Data Format - HDF5 ..... 117**

Overview of the HDF Version 5 Format .....	118
The HDF5 Format .....	119
HDF4 versus HDF5 .....	119
The IDL HDF5 Library .....	120
Routine Names .....	120
Functions Versus Procedures .....	120
Error Handling .....	121
Dimension Order .....	121
IDL HDF5 Limitations .....	122
HDF5 Datatypes .....	123
Compound Datatypes .....	124
Opaque Datatypes .....	125
Enumeration Datatypes .....	127
Variable Length Array Datatypes .....	129
Example: Reading an Image .....	133
Example: Reading a Subselection .....	134
Example: Creating a Data File .....	136
Example: Reading Partial Datasets .....	137
Alphabetical Listing of HDF5 Routines .....	138
H5_CLOSE .....	143
H5_CREATE .....	144
H5_GET_LIBVERSION .....	149
H5_OPEN .....	150
H5_PARSE .....	151
H5A_CLOSE .....	157
H5A_CREATE .....	158
H5A_DELETE .....	160

H5A_GET_NAME .....	161
H5A_GET_NUM_ATTRS .....	162
H5A_GET_SPACE .....	163
H5A_GET_TYPE .....	164
H5A_OPEN_IDX .....	165
H5A_OPEN_NAME .....	166
H5A_READ .....	167
H5A_WRITE .....	168
H5D_CLOSE .....	170
H5D_CREATE .....	171
H5D_EXTEND .....	174
H5D_GET_SPACE .....	176
H5D_GET_STORAGE_SIZE .....	177
H5D_GET_TYPE .....	178
H5D_OPEN .....	179
H5D_READ .....	180
H5D_WRITE .....	184
H5F_CLOSE .....	186
H5F_CREATE .....	187
H5F_IS_HDF5 .....	191
H5F_OPEN .....	192
H5G_CLOSE .....	193
H5G_CREATE .....	194
H5G_GET_COMMENT .....	195
H5G_GET_LINKVAL .....	196
H5G_GET_MEMBER_NAME .....	197
H5G_GET_NMEMBERS .....	199
H5G_GET_NUM_OBJS .....	200
H5G_GET_OBJ_NAME_BY_IDX .....	201
H5G_GET_OBJINFO .....	202
H5G_LINK .....	204
H5G_MOVE .....	206
H5G_OPEN .....	207
H5G_SET_COMMENT .....	208
H5G_UNLINK .....	209
H5I_GET_FILE_ID .....	210

H5I_GET_TYPE .....	211
H5R_CREATE .....	212
H5R_DEREFERENCE .....	214
H5R_GET_OBJECT_TYPE .....	215
H5R_GET_REGION .....	217
H5S_CLOSE .....	219
H5S_COPY .....	220
H5S_CREATE_SCALAR .....	221
H5S_CREATE_SIMPLE .....	222
H5S_GET_SELECT_BOUNDS .....	224
H5S_GET_SELECT_ELEM_NPOINTS .....	225
H5S_GET_SELECT_ELEM_POINTLIST .....	226
H5S_GET_SELECT_HYPER_BLOCKLIST .....	228
H5S_GET_SELECT_HYPER_NBLOCKS .....	230
H5S_GET_SELECT_NPOINTS .....	231
H5S_GET_SIMPLE_EXTENT_DIMS .....	232
H5S_GET_SIMPLE_EXTENT_NDIMS .....	233
H5S_GET_SIMPLE_EXTENT_NPOINTS .....	234
H5S_GET_SIMPLE_EXTENT_TYPE .....	235
H5S_IS_SIMPLE .....	236
H5S_OFFSET_SIMPLE .....	237
H5S_SELECT_ALL .....	238
H5S_SELECT_ELEMENTS .....	239
H5S_SELECT_HYPERSLAB .....	241
H5S_SELECT_NONE .....	243
H5S_SELECT_VALID .....	244
H5S_SET_EXTENT_NONE .....	245
H5S_SET_EXTENT_SIMPLE .....	246
H5T_ARRAY_CREATE .....	248
H5T_CLOSE .....	250
H5T_COMMIT .....	251
H5T_COMMITTED .....	253
H5T_COMPOUND_CREATE .....	254
H5T_COPY .....	256
H5T_ENUM_CREATE .....	257
H5T_ENUM_GET_DATA .....	259

H5T_ENUM_INSERT .....	260
H5T_ENUM_NAMEOF .....	261
H5T_ENUM_SET_DATA .....	262
H5T_ENUM_VALUEOF .....	264
H5T_ENUM_VALUES_TO_NAMES .....	265
H5T_EQUAL .....	267
H5T_GET_ARRAY_DIMS .....	268
H5T_GET_ARRAY_NDIMS .....	269
H5T_GET_CLASS .....	270
H5T_GET_CSET .....	272
H5T_GET_EBIAS .....	273
H5T_GET_FIELDS .....	274
H5T_GET_INPAD .....	276
H5T_GET_MEMBER_CLASS .....	277
H5T_GET_MEMBER_INDEX .....	279
H5T_GET_MEMBER_NAME .....	280
H5T_GET_MEMBER_OFFSET .....	281
H5T_GET_MEMBER_TYPE .....	282
H5T_GET_MEMBER_VALUE .....	283
H5T_GET_NMEMBERS .....	284
H5T_GET_NORM .....	285
H5T_GET_OFFSET .....	286
H5T_GET_ORDER .....	287
H5T_GET_PAD .....	288
H5T_GET_PRECISION .....	289
H5T_GET_SIGN .....	290
H5T_GET_SIZE .....	291
H5T_GET_STRPAD .....	292
H5T_GET_SUPER .....	293
H5T_GET_TAG .....	294
H5T_IDL_CREATE .....	295
H5T_IDLTYPE .....	298
H5T_INSERT .....	300
H5T_MEMTYPE .....	301
H5T_OPEN .....	303
H5T_REFERENCE_CREATE .....	304



H5T_SET_TAG .....	305
H5T_STR_TO_VLEN .....	306
H5T_VLEN_CREATE .....	307
H5T_VLEN_TO_STR .....	309
<b>Chapter 4</b>	
<b>Hierarchical Data Format .....</b>	<b>311</b>
Overview of the HDF Format .....	312
HDF Interfaces .....	313
Single File Application Interfaces .....	313
Multi-File Application Interface .....	314
Creating HDF Files .....	315
Adding Data to an HDF File .....	315
HDF Examples .....	316
HDF Scientific Dataset ID Numbers .....	317
IDL and HDF Data Types .....	317
Common HDF Tag Numbers .....	319
Alphabetical Listing of HDF Routines .....	322
HDF_AN_ANNLEN .....	328
HDF_AN_ANNLIST .....	329
HDF_AN_ATYPE2TAG .....	331
HDF_AN_CREATE .....	333
HDF_AN_CREATEF .....	335
HDF_AN_END .....	336
HDF_AN_ENDACCESS .....	337
HDF_AN_FILEINFO .....	338
HDF_AN_GET_TAGREF .....	340
HDF_AN_ID2TAGREF .....	342
HDF_AN_NUMANN .....	344
HDF_AN_READANN .....	346
HDF_AN_SELECT .....	347
HDF_AN_START .....	349
HDF_AN_TAG2ATYPE .....	350
HDF_AN_TAGREF2ID .....	352
HDF_AN_WRITEANN .....	354
HDF_BROWSER .....	355

HDF_CLOSE .....	356
HDF_DELDD .....	357
HDF_DF24_ADDIMAGE .....	358
HDF_DF24_GETIMAGE .....	360
HDF_DF24_GETINFO .....	361
HDF_DF24_LASTREF .....	363
HDF_DF24_NIMAGES .....	365
HDF_DF24_READREF .....	367
HDF_DF24_RESTART .....	368
HDF_DFAN_ADDFDS .....	369
HDF_DFAN_ADDFID .....	370
HDF_DFAN_GETDESC .....	372
HDF_DFAN_GETFDS .....	374
HDF_DFAN_GETFID .....	376
HDF_DFAN_GETLABEL .....	377
HDF_DFAN_LABLIST .....	379
HDF_DFAN_LASTREF .....	382
HDF_DFAN_PUTDESC .....	383
HDF_DFAN_PUTLABEL .....	385
HDF_DFP_ADDPAL .....	386
HDF_DFP_GETPAL .....	387
HDF_DFP_LASTREF .....	388
HDF_DFP_NPALS .....	389
HDF_DFP_PUTPAL .....	390
HDF_DFP_READREF .....	392
HDF_DFP_RESTART .....	393
HDF_DFP_WRITEREF .....	394
HDF_DFR8_ADDIMAGE .....	395
HDF_DFR8_GETIMAGE .....	398
HDF_DFR8_GETINFO .....	399
HDF_DFR8_LASTREF .....	401
HDF_DFR8_NIMAGES .....	403
HDF_DFR8_PUTIMAGE .....	405
HDF_DFR8_READREF .....	408
HDF_DFR8_RESTART .....	409
HDF_DFR8_SETPALETTE .....	410

HDF_DUPDD .....	411
HDF_EXISTS .....	412
HDF_GR_ATTRINFO .....	413
HDF_GR_CREATE .....	415
HDF_GR_END .....	417
HDF_GR_ENDACCESS .....	418
HDF_GR_FILEINFO .....	419
HDF_GR_FINDATTR .....	421
HDF_GR_GETATTR .....	422
HDF_GR_GETCHUNKINFO .....	424
HDF_GR_GETIMINFO .....	426
HDF_GR_GETLUTID .....	428
HDF_GR_GETLUTINFO .....	429
HDF_GR_IDTOREF .....	431
HDF_GR_LUTTOREF .....	432
HDF_GR_NAMETOINDEX .....	433
HDF_GR_READIMAGE .....	434
HDF_GR_READLUT .....	436
HDF_GR_REFTOINDEX .....	437
HDF_GR_SELECT .....	438
HDF_GR_SETATTR .....	439
HDF_GR_SETCHUNK .....	441
HDF_GR_SETCHUNKCACHE .....	443
HDF_GR_SETCOMPRESS .....	444
HDF_GR_SETEXTTERNALFILE .....	446
HDF_GR_START .....	448
HDF_GR_WRITEIMAGE .....	449
HDF_GR_WRITELUT .....	451
HDF_HDF2IDLTYPE .....	452
HDF_IDL2HDFTYPE .....	453
HDF_ISHDF .....	454
HDF_LIB_INFO .....	455
HDF_NEWREF .....	457
HDF_NUMBER .....	458
HDF_OPEN .....	459
HDF_PACKDATA .....	461

HDF_READ .....	463
HDF_SD_ADDDATA .....	464
HDF_SD_ATTRFIND .....	467
HDF_SD_ATTRINFO .....	469
HDF_SD_ATTRSET .....	472
HDF_SD_CREATE .....	476
HDF_SD_DIMGET .....	480
HDF_SD_DIMGETID .....	482
HDF_SD_DIMSET .....	484
HDF_SD_END .....	487
HDF_SD_ENDACCESS .....	489
HDF_SD_FILEINFO .....	491
HDF_SD_GETDATA .....	493
HDF_SD_GETINFO .....	495
HDF_SD_IDTOREF .....	498
HDF_SD_ISCOORDVAR .....	500
HDF_SD_NAMETOINDEX .....	501
HDF_SD_REFTOINDEX .....	503
HDF_SD_SELECT .....	505
HDF_SD_SETCOMPRESS .....	507
HDF_SD_SETEXTFILE .....	509
HDF_SD_SETINFO .....	511
HDF_SD_START .....	515
HDF_UNPACKDATA .....	517
HDF_VD_ATTACH .....	519
HDF_VD_ATTRFIND .....	521
HDF_VD_ATTRINFO .....	523
HDF_VD_ATTRSET .....	525
HDF_VD_DETACH .....	531
HDF_VD_FDEFINE .....	532
HDF_VD_FEXIST .....	534
HDF_VD_FIND .....	535
HDF_VD_GET .....	536
HDF_VD_GETID .....	538
HDF_VD_GETINFO .....	539
HDF_VD_INSERT .....	541

HDF_VD_ISATTR .....	542
HDF_VD_ISVD .....	543
HDF_VD_ISVG .....	544
HDF_VD_LONE .....	545
HDF_VD_NATTRS .....	546
HDF_VD_READ .....	548
HDF_VD_SEEK .....	550
HDF_VD_SETINFO .....	551
HDF_VD_WRITE .....	553
HDF_VG_ADDTR .....	556
HDF_VG_ATTACH .....	557
HDF_VG_DETACH .....	559
HDF_VG_GETID .....	560
HDF_VG_GETINFO .....	561
HDF_VG_GETNEXT .....	563
HDF_VG_GETTR .....	564
HDF_VG_GETTRS .....	565
HDF_VG_INQTR .....	566
HDF_VG_INSERT .....	567
HDF_VG_ISVD .....	568
HDF_VG_ISVG .....	569
HDF_VG_LONE .....	570
HDF_VG_NUMBER .....	571
HDF_VG_SETINFO .....	572

## Chapter 5

<b>HDF-EOS .....</b>	<b>575</b>
Overview of the HDF-EOS .....	576
Feature Routines .....	577
HDF-EOS Programming Model .....	578
Writing .....	578
Reading .....	578
Note on Array Ordering .....	579
Alphabetical Listing of EOS Routines .....	580
EOS_EH_CONVANG .....	585
EOS_EH_GETVERSION .....	587

EOS_EH_IDINFO .....	589
EOS_EXISTS .....	590
EOS_GD_ATTACH .....	591
EOS_GD_ATTRINFO .....	593
EOS_GD_BLKSSOMOFFSET .....	595
EOS_GD_CLOSE .....	596
EOS_GD_COMPINFO .....	597
EOS_GD_CREATE .....	599
EOS_GD_DEFBOXREGION .....	602
EOS_GD_DEFCOMP .....	604
EOS_GD_DEFDIM .....	606
EOS_GD_DEFFIELD .....	608
EOS_GD_DEFORIGIN .....	610
EOS_GD_DEFPIXREG .....	612
EOS_GD_DEFPROJ .....	613
EOS_GD_DEFTILE .....	615
EOS_GD_DEFVRTREGION .....	617
EOS_GD_DETACH .....	620
EOS_GD_DIMINFO .....	621
EOS_GD_DUPREGION .....	622
EOS_GD_EXTRACTREGION .....	624
EOS_GD_FIELDINFO .....	626
EOS_GD_GETFILLVALUE .....	628
EOS_GD_GETPIXELS .....	629
EOS_GD_GETPIXVALUES .....	631
EOS_GD_GRIDINFO .....	633
EOS_GD_INQATTRS .....	635
EOS_GD_INQDIMS .....	637
EOS_GD_INQFIELDS .....	639
EOS_GD_INQGRID .....	641
EOS_GD_INTERPOLATE .....	643
EOS_GD_NENTRIES .....	645
EOS_GD_OPEN .....	647
EOS_GD_ORIGININFO .....	649
EOS_GD_PIXREGINFO .....	650
EOS_GD_PROJINFO .....	651

EOS_GD_QUERY .....	653
EOS_GD_READATTR .....	655
EOS_GD_READFIELD .....	656
EOS_GD_READTILE .....	658
EOS_GD_REGIONINFO .....	660
EOS_GD_SETFILLVALUE .....	662
EOS_GD_SETTILECACHE .....	664
EOS_GD_TILEINFO .....	666
EOS_GD_WRITEATTR .....	668
EOS_GD_WRITEFIELD .....	670
EOS_GD_WRITEFIELDMETA .....	672
EOS_GD_WRITETILE .....	674
EOS_PT_ATTACH .....	676
EOS_PT_ATTRINFO .....	678
EOS_PT_BCKLINKINFO .....	680
EOS_PT_CLOSE .....	682
EOS_PT_CREATE .....	683
EOS_PT_DEFBOXREGION .....	684
EOS_PT_DEFLEVEL .....	686
EOS_PT_DEFLINKAGE .....	689
EOS_PT_DEFTIMEPERIOD .....	691
EOS_PT_DEFVRTREGION .....	693
EOS_PT_DETACH .....	695
EOS_PT_EXTRACTPERIOD .....	696
EOS_PT_EXTRACTREGION .....	698
EOS_PT_FWDLINKINFO .....	700
EOS_PT_GETLEVELNAME .....	702
EOS_PT_GETRECNUMS .....	704
EOS_PT_INQATTRS .....	706
EOS_PT_INQPOINT .....	708
EOS_PT_LEVELINDX .....	710
EOS_PT_LEVELINFO .....	711
EOS_PT_NFIELDS .....	713
EOS_PT_NLEVELS .....	714
EOS_PT_NRECS .....	715
EOS_PT_OPEN .....	716

EOS_PT_PERIODINFO .....	718
EOS_PT_PERIODRECS .....	720
EOS_PT_QUERY .....	722
EOS_PT_READATTR .....	724
EOS_PT_READLEVEL .....	725
EOS_PT_REGIONINFO .....	727
EOS_PT_REGIONRECS .....	729
EOS_PT_SIZEOF .....	731
EOS_PT_UPDATELEVEL .....	732
EOS_PT_WRITEATTR .....	734
EOS_PT_WRITELEVEL .....	736
EOS_QUERY .....	738
EOS_SW_ATTACH .....	740
EOS_SW_ATTRINFO .....	742
EOS_SW_CLOSE .....	744
EOS_SW_COMPINFO .....	745
EOS_SW_CREATE .....	747
EOS_SW_DEFBOXREGION .....	748
EOS_SW_DEFCOMP .....	750
EOS_SW_DEFDATAFIELD .....	752
EOS_SW_DEFDIM .....	754
EOS_SW_DEFDIMMAP .....	756
EOS_SW_DEFGEOFIELD .....	758
EOS_SW_DEFIDXMAP .....	760
EOS_SW_DEFTIMEPERIOD .....	762
EOS_SW_DEFVRTREGION .....	764
EOS_SW_DETACH .....	767
EOS_SW_DIMINFO .....	768
EOS_SW_DUPREGION .....	769
EOS_SW_EXTRACTPERIOD .....	771
EOS_SW_EXTRACTREGION .....	773
EOS_SW_FIELDINFO .....	775
EOS_SW_GETFILLVALUE .....	777
EOS_SW_IDXMAPINFO .....	778
EOS_SW_INQATTRS .....	780
EOS_SW_INQDATAFIELDS .....	782



EOS_SW_INQDIMS .....	784
EOS_SW_INQGEOFIELDS .....	786
EOS_SW_INQIDXMAPS .....	788
EOS_SW_INQMAPS .....	790
EOS_SW_INQSWATH .....	792
EOS_SW_MAPINFO .....	794
EOS_SW_NENTRIES .....	796
EOS_SW_OPEN .....	798
EOS_SW_PERIODINFO .....	800
EOS_SW_QUERY .....	802
EOS_SW_READATTR .....	804
EOS_SW_READFIELD .....	805
EOS_SW_REGIONINFO .....	807
EOS_SW_SETFILLVALUE .....	809
EOS_SW_WRITEATTR .....	811
EOS_SW_WRITEDATAMETA .....	813
EOS_SW_WRITEFIELD .....	815
EOS_SW_WRITEGEOMETA .....	817

## Chapter 6

### **Network Common Data Format ..... 819**

Overview of NetCDF .....	820
NetCDF Data Modes .....	821
Attributes, Dimensions, and Variables .....	822
Attributes .....	822
Dimensions .....	822
Variables .....	822
Creating NetCDF Files .....	823
Reading NetCDF Files .....	823
NetCDF Examples .....	824
Type Conversion .....	826
Specifying Attributes and Variables .....	827
String Data in NetCDF Files .....	828
Alphabetical Listing of NetCDF Routines .....	829
NetCDF_ATTCOPY .....	830
NetCDF_ATTDEL .....	832

NCDF_ATTGET .....	834
NCDF_ATTINQ .....	836
NCDF_ATTNAME .....	839
NCDF_ATTPUT .....	841
NCDF_ATTRENAME .....	844
NCDF_CLOSE .....	846
NCDF_CONTROL .....	847
NCDF_CREATE .....	850
NCDF_DIMDEF .....	852
NCDF_DIMID .....	854
NCDF_DIMINQ .....	855
NCDF_DIMRENAME .....	857
NCDF_EXISTS .....	858
NCDF_INQUIRE .....	859
NCDF_OPEN .....	861
NCDF_VARDEF .....	862
NCDF_VARGET .....	865
NCDF_VARGET1 .....	867
NCDF_VARID .....	869
NCDF_VARINQ .....	870
NCDF_VARPUT .....	872
NCDF_VARRENAME .....	875
<b>Index .....</b>	<b>877</b>



## Chapter 1

# Scientific Data Formats Overview

This chapter provides an overview of the four self-describing scientific data formats supported by IDL: CDF (Common Data Format), HDF and HDF5 (Hierarchical Data Format), HDF-EOS (Earth Observing System extensions to HDF), and netCDF (Network Common Data Format). These data formats are supported on all IDL platforms. Detailed documentation for each routine can be found in this volume.

## CDF—Common Data Format

The Common Data Format is a file format that facilitates the storage and retrieval of multi-dimensional scientific data. This version of IDL supports CDF 3.1. IDL's CDF routines all begin with the prefix “CDF\_”.

CDF is a product of the National Space Science Data Center (NSSDC). General information about CDF, including the “frequently-asked-questions” (FAQ) list, software, and CDF's IDL library (an alternative interface between CDF and IDL) are available on the World Wide Web at:

[http://nssdc.gsfc.nasa.gov/cdf/cdf\\_home.html](http://nssdc.gsfc.nasa.gov/cdf/cdf_home.html)

If you do not have access to the WWW you can get CDF information via ftp at:

<ftp://nssdc.gsfc.nasa.gov/pub/cdf/FAQ.doc>

For assistance via e-mail, send a message to the internet address:

[cdfsupport@nssdc.gsfc.nasa.gov](mailto:cdfsupport@nssdc.gsfc.nasa.gov)

## HDF—Hierarchical Data Format

The Hierarchical Data Format (HDF) is a multi-object file format that facilitates the transfer of various types of data between machines and operating systems. HDF is a product of the National Center for Supercomputing Applications (NCSA). HDF is designed to be flexible, portable, self-describing and easily extensible for future enhancements or compatibility with other standard formats. The HDF library contains interfaces for storing and retrieving images and multi-dimensional scientific data.

IDL supports two distinct versions of HDF: version 4 and version 5.

### HDF Version 4 Support

This version of IDL supports HDF 4.1r5. IDL's HDF version 4 routines all begin with the prefix "HDF\_".

### HDF Version 5 Support

This version of IDL supports HDF5 5-1.6.3. IDL's HDF version 5 routines all begin with the prefix "H5\_" or "H5\*\_".

Further information about HDF and HDF5 can be found on the World Wide Web at the HDF Information Server:

<http://hdf.ncsa.uiuc.edu>

Alternately, you can send e-mail to [hdfhelp@ncsa.uiuc.edu](mailto:hdfhelp@ncsa.uiuc.edu).

## HDF-EOS—Hierarchical Data Format - Earth Observing System

HDF-EOS (Hierarchical Data Format-Earth Observing System) is an extension of NCSA (National Center for Supercomputing Applications) HDF and uses HDF calls as an underlying basis. This API contains functionality for creating, accessing and manipulating Grid, Point and Swath structures. IDL's HDF-EOS routines all begin with the prefix "EOS\_". This version of IDL supports HDF-EOS 2.8.

HDF-EOS is a product of NASA, information may be found at:

<http://hdfeos.gsfc.nasa.gov>

## NetCDF—Network Common Data Format

The network Common Data Format (netCDF) is a self-describing scientific data access interface and library developed at the Unidata Program Center in Boulder, Colorado. The netCDF interface and library use XDR (eXternal Data Representation) to make the data format machine-independent. This version of IDL supports netCDF 3.5. IDL's NetCDF routines all begin with the prefix "NCDF\_".

More information about netCDF can be found on Unidata's netCDF World Wide Web home page which can be found at:

<http://www.unidata.ucar.edu/packages/netcdf/>

Further information and the original netCDF documentation can be obtained from Unidata at the following addresses:

UCAR Unidata Program Center  
P.O. Box 3000  
Boulder, Colorado, USA 80307  
(303) 497-8644  
e-mail: [support@unidata.ucar.edu](mailto:support@unidata.ucar.edu)





## Chapter 2

# Common Data Format

The following topics are covered in this appendix:

---

Overview of the Common Data Format . . .	24	Creating CDF Files . . . . .	28
Variables and Attributes . . . . .	25	Alphabetical Listing of CDF Routines . . . .	30
CDF File Options . . . . .	27		

# Overview of the Common Data Format

The Common Data Format is a file format that facilitates the storage and retrieval of multi-dimensional scientific data. This version of IDL supports version 3.1 of the CDF library. IDL's CDF routines all begin with the prefix "CDF\_".

CDF is a product of the National Space Science Data Center (NSSDC). General information about CDF, including the "frequently-asked-questions" (FAQ) list, software, and CDF's IDL library (an alternative interface between CDF and IDL) are available on the World Wide Web at:

<http://cdf.gsfc.nasa.gov/>

CDF documentation, including the *CDF User's Guide*, is available at:

<http://cdf.gsfc.nasa.gov/html/docs.html>

For assistance via e-mail, send a message to the internet address:

[cdfsupport@listserv.gsfc.nasa.gov](mailto:cdfsupport@listserv.gsfc.nasa.gov)



# Variables and Attributes

Information in a CDF file consists of attributes (metadata) and collections of data records (variables).

## Variables

IDL can create CDF files representing any data that can be stored in a zero- to eight-dimensional array. CDF supports two distinct types of variables, *rVariables* and *zVariables*. For reasons of efficiency, CDF uses variances to indicate whether data is unique between records and dimensions. For example, consider a data set of simultaneous surface temperatures at a variety of locations, the IDL code for creating the CDF file is included at the end of this section. A variable representing “GMT time” will vary from record to record, but not dimension to dimension (since all data are taken simultaneously). On the other hand, a variable such as longitude may not vary from record to record, but will vary from dimension to dimension. Record variance is set using the REC\_VARY and REC\_NOVARY keywords to CDF\_VARCREATE, while dimensional variance is set through the *DimVary* argument to CDF\_VARCREATE. In both cases, the default is varying data.

## rVariables

*rVariables* (or regular variables) are multidimensional arrays of values, each having the same dimensions. That is, all *rVariables* in a CDF must have the same number of dimensions and dimension sizes. In IDL, the *rVariable* dimension sizes are declared when the CDF file is first created with CDF\_CREATE. In the example at the end of this section, all variables except time are *rVariables*.

## zVariables

*zVariables* (The *z* doesn’t stand for anything—the CDF people just like the letter *z*) are multidimensional arrays of values of the same data type. *zVariables* can have different dimensionality from other *zVariables* and *rVariables*. In general, *zVariables* are much more flexible, and therefore easier to use, than *rVariables*.

For more discussion on CDF variables, see “Organizing Your Data in CDF” in the *CDF User’s Guide*.

## Attributes

Attributes can contain auxiliary information about an entire CDF file (*global scope* attributes or *gAttributes*), or about particular CDF variables (*variable scope* attributes or *rAttributes/zAttributes* depending on variable type). CDF attributes can be scalar or vector in nature, and of any valid datatype. In the case of vector, or multiple entry, attributes the user must keep track of the entry numbers (in CDF terms these are the *gEntry*, *rEntry*, or *zEntry* numbers depending on attribute type). For example, every *rVariable* in a CDF file might have an *rAttribute* named “Date”. A vector *zVariable* might have a *zAttribute* named “Location” with values such as [“Melbourne Beach”, “Crowley”,...]. A global attribute “MODS” might be used to keep track of the modification history of a CDF file (see “[CDF\\_ATTPUT](#)” on page 43). Note however, that variables cannot have multiple attributes with the same names. In IDL, CDF attributes are created with `CDF_ATTPUT` and retrieved with `CDF_ATTGET`. For more on CDF variables, see “Attributes” in the *CDF User’s Guide*.

## Specifying Attributes and Variables

Variables and attributes can be referred to either by name or by their ID numbers in most CDF routines. For example, in the `CDF_VARCREATE` command shown in the example under “[Type Conversion](#)” on page 29, the following command would have been equivalent:

```
; Reference by variable ID:  
CDF_VARCREATE, fileid, varid, '12'
```

# CDF File Options

## File Type

The `SINGLE_FILE` and `MULTI_FILE` keywords to `CDF_CREATE` allow CDFs to be written as either:

1. all data in a single file, or
2. a separate file for each variable, plus a master file for global information.

The default is `MULTI_FILE`. For more discussion on CDF file format options, see “File Format Options” in the *CDF User’s Guide*.

## Data Encodings/Decodings

Keywords to `CDF_CREATE` allow files to be written in a variety of data encoding and decoding options. (For example, the `/SUN_ENCODING` keyword creates a file in the SUN native encoding scheme). The default encoding/decoding is network (XDR). All CDF encodings and decodings can be written or read on all platforms, but matching the encoding with the architecture used provides the best performance. If you work in a single-platform environment most of the time, select `HOST_ENCODING` for maximum performance. If you know that the CDF file will be transported to a computer using another architecture, specify the encoding for the target architecture or specify `NETWORK_ENCODING` (the default). Specifying the target architecture provides maximum performance on that architecture; specifying `NETWORK_ENCODING` provides maximum flexibility.

For more on CDF encoding/decoding methods and combinations, see “Encoding” and “Decoding” in the *CDF User’s Guide*.

## Creating CDF Files

The following list details the basic IDL commands needed to create a new CDF file:

- **CDF\_CREATE**: Call this procedure to begin creating a new file. **CDF\_CREATE** contains a number of keywords which affect the internal format of the new CDF file.
- **CDF\_VARCREATE**: Define the variables to be used in the file.
- **CDF\_ATTPUT**: Optionally, use attributes to describe the data.
- **CDF\_VARPUT**: Write the appropriate data to the CDF file.
- **CDF\_CLOSE**: Close the file.

---

**Note**

On Windows, CDF routines can save and retrieve data sets greater than 64 KB in size.

---

## Reading CDF Files

The following commands are the basic commands needed to read data from a CDF file:

- **CDF\_OPEN**: Open an existing CDF file.
- **CDF\_INQUIRE**: Call this function to find the general information about the contents of the CDF file.
- **CDF\_CONTROL**: Call this function to obtain further information about the CDF file
- **CDF\_VARINQ**: Retrieve the names, types, sizes, and other information about the variables in the CDF file.
- **CDF\_VARGET**: Retrieve the variable values.
- **CDF\_ATTINQ**: Optionally, retrieve the names, scope and other information about the CDFs attributes.
- **CDF\_ATTGET**: Optionally, retrieve the attributes.
- **CDF\_CLOSE**: Close the file.

- If the structure of the CDF file is already known, the inquiry routines do not need to be called—only CDF\_OPEN, CDF\_ATTGET, CDF\_VARGET, and CDF\_CLOSE would be needed.

## Type Conversion

Values are converted to the appropriate type before being written to a CDF file. For example, in the commands below, IDL converts the string “12” to a floating-point 12.0 before writing it:

```
varid=CDF_VARCREATE(fileid, 'VarName', ['VARY', 'VARY'], $
    DIM=[2,3+5], /CDF_FLOAT)
CDF_VARPUT, fileid, 'VarName', '12' ; Reference by variable ID
```

## Example: Creating a CDF File

The following is a simple example demonstrates the basic procedure used in creating a CDF file. See [“Variables and Attributes”](#) on page 25 for a discussion of the variances used in this example. See the documentation for individual CDF routines for more specific examples.

```
id = CDF_CREATE('Temperature.cdf', [2,3], /Clobber )
att_id = CDF_ATTCREATE(id, 'Title', /GLOBAL)
CDF_ATTPUT, id, att_id, 0, 'My Fancy CDF'
att1_id = CDF_ATTCREATE(id, 'Planet', /GLOBAL)
CDF_ATTPUT, id, 'Planet', 0, 'Mars'
time_id = CDF_VARCREATE(id, 'Time', ['NOVARY', 'NOVARY'], $
    /REC_VARY)
att2_id = CDF_ATTCREATE(id, 'Time Standard', /VARIABLE_SCOPE)
; times are every half hour starting a 8 am GMT.
CDF_ATTPUT, id, att2_id, time_id, 'GMT'
FOR I=0,9 DO CDF_VARPUT, id, time_id, 8.+ 0.5 * I, rec_start=I
temp_id = CDF_VARCREATE(id, 'Temp', ['VARY', 'VARY'], $
    /REC_VARY, /ZVAR, DIMENSIONS=[2,3])
long_id = CDF_VARCREATE(id, 'Longitude', ['VARY', 'VARY'], $
    /REC_NOVARY)
lat_id = CDF_VARCREATE(id, 'Latitude', ['VARY', 'VARY'], $
    /REC_NOVARY)
; write 10 temperature records:
CDF_VARPUT, id, temp_id, FINDGEN(2, 3, 10)
; create longitudes:
CDF_VARPUT, id, long_id, [[10.0, 12.0], [8.0, 6.0], [3.0, 2.0]]
; create latitudes:
CDF_VARPUT, id, lat_id, [[40.0, 42.0], [38.0, 34.0],[30.0, 31.0]]
CDF_CLOSE, id
```

# Alphabetical Listing of CDF Routines

CDF\_ATTCREATE  
CDF\_ATTDELETE  
CDF\_ATT EXISTS  
CDF\_ATTGET  
CDF\_ATTINQ  
CDF\_ATTNUM  
CDF\_ATTPUT  
CDF\_ATTRENAME  
CDF\_CLOSE  
CDF\_COMPRESSION  
CDF\_CONTROL  
CDF\_CREATE  
CDF\_DELETE  
CDF\_DOC  
CDF\_ENCODE\_EPOCH  
CDF\_ENCODE\_EPOCH16  
CDF\_EPOCH  
CDF\_EPOCH16  
CDF\_ERROR  
CDF\_EXISTS  
CDF\_INQUIRE  
CDF\_LIB\_INFO  
CDF\_OPEN  
CDF\_PARSE\_EPOCH  
CDF\_PARSE\_EPOCH16  
CDF\_SET\_CDF27\_BACKWARD\_COMPATIBLE

CDF\_VARCREATE  
CDF\_VARDELETE  
CDF\_VARGET  
CDF\_VARGET1  
CDF\_VARINQ  
CDF\_VARNUM  
CDF\_VARPUT  
CDF\_VARRENAME

# CDF\_ATTCREATE

The CDF\_ATTCREATE function creates a new attribute in the specified Common Data Format file. If successful, the attribute ID is returned.

## Syntax

```
Result = CDF_ATTCREATE( Id, Attribute_Name [, /GLOBAL_SCOPE]
                        [, /VARIABLE_SCOPE] )
```

## Return Value

Returns the attribute ID.

## Arguments

### Id

The CDF ID of the file for which a new attribute is created, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute\_Name

A string containing the name of the attribute to be created.

## Keywords

### GLOBAL\_SCOPE

Set this keyword to make the scope of the attribute global. This is the default.

### VARIABLE\_SCOPE

Set this keyword to indicate that the attribute's scope is per variable.

## Examples

```
id = CDF_OPEN('test') ; Create a CDF file.
xx = CDF_ATTCREATE(id, 'Attribute-1', /GLOBAL_SCOPE)
CDF_ATTRENAME, id, 'Attribute-1', 'My Favorite Attribute'
PRINT, CDF_ATTNUM(id, 'My Favorite Attribute')
CDF_CLOSE, id ; Close the CDF file.
```



## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_ATTDELETE

The CDF\_ATTDELETE procedure deletes an attribute from the specified CDF file. Note that the attribute's entries are also deleted, and that the attributes that numerically follow the deleted attribute within the CDF file are automatically renumbered.

## Syntax

```
CDF_ATTDELETE, Id, Attribute [, EntryNum] [, /ZVARIABLE]
```

## Arguments

### ID

The CDF ID of the file containing the *Attribute* to be deleted, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute

A string containing the name or zero-based attribute number of the attribute to be deleted.

### EntryNum

The entry number to delete. If EntryNum is not specified, the entire attribute is deleted. If the attribute is variable in scope, this is either the name or number of the variable the attribute is to be associated with. If the attribute is global in scope, this is the actual gEntry. It is the user's responsibility to keep track of valid gEntry numbers. Normally, gEntry numbers will begin with 0 or 1 and will increase up to MAXGENTRY (as reported in the GET\_ATTR\_INFO structure returned by CDF\_CONTROL), but this is not required.

## Keywords

### ZVARIABLE

If EntryNum is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that EntryNum is an rVariable ID. Note: the attribute must have a scope of VARIABLE\_SCOPE.

## Examples

```

cid = CDF_CREATE('DEMOattdelete')
attr1_id = CDF_ATTCREATE(cid, 'GLOBAL_ATTR1', /GLOBAL_SCOPE)
attr2_id = CDF_ATTCREATE(cid, 'GLOBAL_ATTR2', /GLOBAL_SCOPE)
attr3_id = CDF_ATTCREATE(cid, 'VAR_ATTR1', /VARIABLE_SCOPE)
attr4_id = CDF_ATTCREATE(cid, 'VAR_ATTR2', /VARIABLE_SCOPE)

; Check the number of attributes:
info = CDF_INQUIRE(cid)
HELP, info.natts

; Delete the first and third attributes:
CDF_ATTDELETE, cid, 'GLOBAL_ATTR1'
; The attribute numbers are zero-based and automatically
; renumbered
CDF_ATTDELETE, cid, 1

; Select the new first attribute:
CDF_ATTINQ, cid, 0, name, scope, MaxEntry, MaxZentry
HELP, name, scope

CDF_DELETE, cid

```

### IDL Output

```

<Expression>      LONG      =          4

NAME              STRING     = 'GLOBAL_ATTR2'
SCOPE            STRING     = 'GLOBAL_SCOPE'

```

## Version History

4.0.1b	Introduced
--------	------------

### See Also

[CDF\\_ATTCREATE](#), [CDF\\_ATTGET](#), [CDF\\_ATT EXISTS](#), [CDF\\_ATTINQ](#),  
[CDF\\_ATTPUT](#), [CDF\\_ATTRENAME](#)

# CDF\_ATTEXISTS

The CDF\_ATTEXISTS function determines whether a given attribute exists in the specified CDF file. Attributes may be specified by name or number.

## Syntax

```
Result = CDF_ATTEXISTS( Id, Attribute [, EntryNum] [, /ZVARIABLE] )
```

## Return Value

Returns TRUE (1) if the specified attribute exists or FALSE (0) if it does not exist

## Arguments

### Id

The CDF ID of the file containing the Attribute to be checked, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute

A string containing the name or zero-based attribute number of the attribute to be checked.

### EntryNum

The entry number to confirm. If EntryNum is not specified, the entire file is searched for the specified attribute. If the attribute is variable in scope, this is either the name or number of the variable the attribute is to be associated with. If the attribute is global in scope, this is the actual gEntry. It is the user's responsibility to keep track of valid gEntry numbers. Normally gEntry numbers will begin with 0 or 1 and will increase up to MAXGENTRY (as reported in the GET\_ATTR\_INFO structure returned by CDF\_CONTROL), but this is not required.

## Keywords

### ZVARIABLE

If EntryNum is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is

to assume that EntryNum is an rVariable ID. Note: the attribute must have a scope of VARIABLE\_SCOPE.

## Examples

Create a function to test an attribute's existence and return a string:

```
FUNCTION exists, cdfid, atname_or_number
IF CDF_ATT EXISTS(cdfid, atname_or_number) THEN $
    RETURN, 'Attribute Exists' ELSE $
    RETURN, 'Attribute Does Not Exist'
END

; Create a CDF with 2 attributes:
cdfid = CDF_CREATE('DEMOattexists')
attr1_id = CDF_ATTCREATE(cdfid, 'GLOBAL_ATT' , /GLOBAL_SCOPE)
attr2_id = CDF_ATTCREATE(cdfid, 'VARIABLE_ATT', /VARIABLE_SCOPE)

; Check the existence of the two attributes, plus a third that
; does not exist:
PRINT, EXISTS(cdfid, attr1_id)
PRINT, EXISTS(cdfid, 1)
PRINT, EXISTS(cdfid, 'BAD ATTR')

CDF_DELETE, cdfid
```

### IDL Output

```
Attribute Exists
Attribute Exists
Attribute Does Not Exist
```

## Version History

4.0.1b	Introduced
--------	------------

## See Also

[CDF\\_ATTCREATE](#), [CDF\\_ATTGET](#), [CDF\\_ATTDELETE](#), [CDF\\_ATTINQ](#),  
[CDF\\_ATTPUT](#), [CDF\\_ATTRENAME](#)

# CDF\_ATTGET

The CDF\_ATTGET procedure reads an attribute entry from a CDF file.

## Syntax

```
CDF_ATTGET, Id, Attribute, EntryNum, Value [, CDF_TYPE= variable]
[, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute

A string containing the name of the attribute or the attribute number to be written.

### EntryNum

The entry number. If the attribute is variable in scope, this is either the name or number of the variable the attribute is to be associated with. If the attribute is global in scope, this is the actual gEntry. It is the user's responsibility to keep track of valid gEntry numbers. Normally, gEntry numbers will begin with 0 or 1 and will increase up to MAXGENTRY (as reported in the GET\_ATTR\_INFO structure returned by [CDF\\_CONTROL](#)), but this is not required.

### Value

A named variable in which the value of the attribute is returned.

## Keywords

### CDF\_TYPE

Set this keyword equal to a named variable that will contain the CDF type of the attribute entry, returned as a scalar string. Possible returned values are: CDF\_CHAR, CDF\_UCHAR, CDF\_INT1, CDF\_BYTE, CDF\_UINT1, CDF\_UINT2, CDF\_INT2, CDF\_UINT4, CDF\_INT4, CDF\_REAL4, CDF\_FLOAT, CDF\_REAL8, CDF\_DOUBLE, CDF\_EPOCH, or CDF\_EPOCH16. If the type cannot be determined, "UNKNOWN" is returned.

## ZVARIABLE

If EntryNum is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that EntryNum is an rVariable ID.

### Note

---

The attribute must have a scope of VARIABLE\_SCOPE.

---

## Examples

```
; Open the CDF file created in the CDF_ATTPUT example:
id = CDF_OPEN('foo')
CDF_ATTGET, id, 'Attribute2', 'Var2', x
PRINT, x, FORMAT='(["',9(X,F3.1,","),X,F3.1,""])'
CDF_CLOSE, id ; Close the CDF file.
```

### IDL Output

```
[ 0.0, 1.0, 2.0, 3.0, 4.0, 5.0, 6.0, 7.0, 8.0, 9.0]
```

This is the expected output, since this attribute was created with a call to FINDGEN.

## Version History

Pre 4.0	Introduced
6.3	Add support for EPOCH_16 type

# CDF\_ATTINQ

The CDF\_ATTINQ procedure obtains information about a specified attribute in a Common Data Format file.

## Syntax

```
CDF_ATTINQ, Id, Attribute, Name, Scope, MaxEntry [, MaxZEntry]
```

## Arguments

### Id

The CDF ID of the file containing the desired attribute, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute

A string containing either the name or number of the attribute to be inquired.

### Name

A named variable in which the name of the attribute is returned.

### Scope

A named variable in which a string, describing the scope of the attribute, is returned. This string will have one of the following values: “GLOBAL\_SCOPE”, “VARIABLE\_SCOPE”, “GLOBAL\_SCOPE\_ASSUMED”, or “VARIABLE\_SCOPE\_ASSUMED”.

### MaxEntry

A named variable in which the maximum rVariable entry number for this attribute is returned.

### MaxZEntry

A named variable in which the maximum zVariable entry number for this attribute is returned.



## Keywords

None

## Examples

```
cdfid= CDF_OPEN('/cdrom/ozone.8.20.92')
CDF_ATTINQ, cdfid, 0, name, scope, maxentry, maxzentry
PRINT, name, scope, maxentry, maxzentry
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_ATTNUM

The CDF\_ATTNUM function returns the attribute number associated with a particular attribute in a Common Data Format file.

## Syntax

*Result* = CDF\_ATTNUM(*Id*, *Attribute\_Name*)

## Return Value

Returns the attribute number.

## Arguments

### Id

The CDF ID for the file that contains the desired attribute, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute\_Name

A string containing the name of the attribute.

## Keywords

None

## Examples

See the example for “[CDF\\_ATTPUT](#)” on page 43.

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_ATTPUT

The CDF\_ATTPUT procedure writes an attribute entry to a Common Data Format file, or attaches an attribute to a CDF variable. If the specified entry already exists, it is overwritten.

## Syntax

```
CDF_ATTPUT, Id, Attribute, EntryNum, Value [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Attribute

A string containing either the name or number of the attribute to be written.

### EntryNum

The entry number. If the attribute is variable in scope, this is either the name or number of the variable the attribute is to be associated with. If the attribute is global in scope, this is the actual gEntry. It is the user's responsibility to keep track of valid gEntry numbers. Normally gEntry numbers will begin with 0 or 1 and will increase up to MAXGENTRY (as reported in the GET\_ATTR\_INFO structure returned by CDF\_CONTROL), but this is not required.

### Value

The value(s) to be written.

## Keywords

### ZVARIABLE

If EntryNum is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that EntryNum is an rVariable ID. Note: the attribute must have a scope of VARIABLE\_SCOPE.

## Examples

### Example 1

```

Id= CDF_CREATE('foo', /SUN_ENCODING, /HOST_DECODING, $
    /ROW_MAJOR) ; no dimensions.
dummy= CDF_VARCREATE(id, 'Var1', /CDF_INT4, /REC_VARY)
v2= CDF_VARCREATE(id, 'Var2', /CDF_FLOAT, /REC_NOVARY)
dummy= CDF_ATTCREATE(id, 'Title', /VARIABLE)
global_dummy = CDF_ATTCREATE(id, 'Date', /GLOBAL)
dummy= CDF_ATTCREATE(id, 'Att2', /VARIABLE)
CDF_ATTPUT, id, 'Title', 'Var1', 'Temperature at surface'
CDF_ATTPUT, id, 'Title', v2, 'Time of recording'
CDF_ATTPUT, id, 'Date', 1, 'July 4, 1996'
CDF_ATTPUT, id, 'Att2', 'Var2', FINDGEN(10)

; Rename the "Att2" attribute to "Attribute2":
CDF_ATTRENAME, Id, 'Att2', 'Attribute2'

; Verify the attribute number (zero-based) of Attribute2
PRINT, CDF_ATTNUM(id, 'Attribute2')

; Close the CDF file. This file is used in the CDF_ATTGET example.
CDF_CLOSE, id

```

### IDL Output

```
1
```

### Example 2

The following example uses the Global attribute “MODS” to keep track of the modification history of a CDF file named `mods.cdf`.

```

id = CDF_CREATE('mods.cdf', /CLOBBER)
cid = CDF_ATTCREATE(id, 'MODS', /GLOBAL_SCOPE)
CDF_ATTPUT, id, cid, 0, 'Original Version'
CDF_CLOSE, id

; Next, reopen the CDF file and make modifications:
id = CDF_OPEN('mods.cdf')
CDF_CONTROL, id, ATTRIBUTE='MODS', GET_ATTR_INFO=ginfo

; Use CDF_CONTROL to get the MAXGENTRY used.
CDF_ATTPUT, id, cid, ginfo.maxgentry+1, 'Second Version'

; Insert the new gEntry at MAXGENTRY+1.
CDF_CLOSE, id

```

```

; Reopen the CDF file again and make more modifications:
id = CDF_OPEN('mods.cdf')
CDF_CONTROL, id, ATTRIBUTE='MODS', GET_ATTR_INFO=ginfo
CDF_ATTPUT, id, cid, ginfo.maxgentry+1, 'Third Version'
CDF_CLOSE, id

; Reopen the CDF file again and make a modification in the
; MAXGENTRY + 2 spot (skipping an entry number).
id = CDF_OPEN('mods.cdf')
CDF_CONTROL, id, ATTRIBUTE='MODS', GET_ATTR_INFO=ginfo
CDF_ATTPUT, id, cid, ginfo.maxgentry+2, 'Fourth Version'

; Now, examine the CDF file to review its modification history.
; Since the gENTRY numbers have a gap in them, we can check each
; attribute with the CDF_ATTEXTISTS function. This is a good idea
; if you do not know for certain that the attribute entries are
; serially numbered.

CDF_CONTROL, id, ATTRIBUTE='MODS', GET_ATTR_INFO=ginfo
FOR I=0, ginfo.maxgentry DO BEGIN
  IF CDF_ATTEXTISTS(id, cid, I) THEN BEGIN
    CDF_ATTGET, id, cid, I, gatt
    PRINT, I, gatt, FORMAT='("Attribute: MODS (gENTRY #",i1,") = ",A)'
  ENDIF ELSE BEGIN
    PRINT, I, FORMAT='("Attribute: MODS (gENTRY #",i1,") $
    Does not exist")'
  ENDELSE
ENDFOR
CDF_CLOSE, id

```

## IDL Output

```

Attribute: MODS (gENTRY #0) = Original Version
Attribute: MODS (gENTRY #1) = Second Version
Attribute: MODS (gENTRY #2) = Third Version
Attribute: MODS (gENTRY #3) Does not exist
Attribute: MODS (gENTRY #4) = Fourth Version

```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_ATTRENAME

The CDF\_ATTRENAME procedure is used to rename an existing attribute in a Common Data Format file.

## Syntax

CDF\_ATTRENAME, *Id*, *OldAttr*, *NewName*

## Arguments

### Id

The CDF ID of the file containing the desired attribute, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### OldAttr

A string containing the current name of the attribute *or* the attribute number to be renamed.

### NewName

A string containing the new name for the attribute.

## Keywords

None

## Examples

See the example for “[CDF\\_ATTPUT](#)” on page 43.

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_CLOSE

The CDF\_CLOSE procedure closes the specified Common Data Format file. The CDF's data buffers are flushed, all of the CDF's open files are closed, and the CDF identifier is freed. You *must* use CDF\_CLOSE to close a CDF file to guarantee that all modifications you have made are actually written to disk.

## Syntax

CDF\_CLOSE, *Id*

## Arguments

### Id

The CDF ID of the file to be closed, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

## Keywords

None

## Examples

```
; Open a file:
id = CDF_OPEN('open_close.cdf'
; ... Other CDF_ commands go here.
; Close the cdf file.
CDF_CLOSE, id
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_COMPRESSION

The CDF\_COMPRESSION procedure sets or returns the compression mode for a CDF file and/or variables. Compression parameters should be set before values are written to the CDF file.

## Special Note About Temporary File Location

CDF creates temporary files whenever files/variables are compressed or uncompressed. By default, these files are created in the current directory. UNIX users can set the environment variable CDF\_TMP to set the temporary directory explicitly.

## Syntax

```
CDF_COMPRESSION, Id [, GET_COMPRESSION=variable]
  [, GET_GZIP_LEVEL=variable] [, GET_VAR_COMPRESSION=variable]
  [, GET_VAR_GZIP_LEVEL=variable] [, SET_COMPRESSION={0 | 1 | 2 | 3 |
  5}] [, SET_GZIP_LEVEL=integer{1 to 9}]
  [, SET_VAR_COMPRESSION={0 | 1 | 2 | 3 | 5}]
  [, SET_VAR_GZIP_LEVEL=integer{1 to 9}]
  [, VARIABLE=variable name or index] [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID of the file being compressed or queried, as returned from a previous call to CDF\_OPEN or CDF\_CREATE. Note that CDF compression only works for single-file CDF files (see [CDF\\_CREATE](#)).

## Keywords

### GET\_COMPRESSION

Set this keyword to a named variable to retrieve the compression type used for the single-file CDF file. Note that individual CDF variables may compression types different that the one for the rest of the CDF file.



## GET\_GZIP\_LEVEL

Set this keyword to a named variable in which the current GZIP effort level (1-9) for the CDF file is returned. If the compression type for the file is not GZIP (5), then a value of zero is returned.

## GET\_VAR\_COMPRESSION

Set this keyword to a named variable to retrieve the compression type for the variable identified by the VARIABLE keyword.

## GET\_VAR\_GZIP\_LEVEL

Set this keyword to a named variable in which the GZIP effort level (1-9) for variable specified by the VARIABLE keyword is returned. If the compression type for the variable is not GZIP (5), then a value of zero is returned.

## SET\_COMPRESSION

Set this keyword to the compression type to be used for the single-file CDF file. Note that individual CDF variables may use compression types different than the one for the rest of the CDF file. Valid compression types are:

- 0 = No Compression
- 1 = Run-Length Encoding
- 2 = Huffman
- 3 = Adaptive Huffman
- 5 = GZIP (see the optional GZIP\_LEVEL keyword)

## SET\_GZIP\_LEVEL

This keyword is used to indicate the desired effort for the GZIP compression. This effort must be expressed as a scalar in the range (1-9). If GZIP\_LEVEL is not specified upon entry then the default effort level is taken to be 5. If the SET\_GZIP\_LEVEL keyword is set to a valid value, and the keyword SET\_COMPRESSION is not specified, the SET\_COMPRESSION is set to GZIP (5).

## SET\_VAR\_COMPRESSION

Set this keyword to the compression type for the variable identified by the VARIABLE keyword. If the variable is a zVariable, and is referred to by index in the VARIABLE keyword, then the keyword ZVARIABLE must be set. The desired

variable compression should be set before variable data is added with CDF\_VARPUT. Valid compression types are:

- 0 = No Compression
- 1 = Run-Length Encoding
- 2 = Huffman
- 3 = Adaptive Huffman
- 5 = GZIP (see the optional GZIP\_LEVEL keyword)

## SET\_VAR\_GZIP\_LEVEL

Set this keyword to the GZIP effort level (1-9). If the compression type for the variable is not GZIP (5), no action is performed.

## VARIABLE

Set this keyword to the name of a variable or a variable index to set the current variable. This keyword is mandatory when queering/setting the compression parameters of a rVariable or zVariable. Note that if VARIABLE is set to the index of a zVARIABLE, the ZVARIABLE keyword must also be set. If ZVARIABLE is not set, the variable is assumed to be an rVariable.

## ZVARIABLE

Set this keyword if the current variable is a zVARIABLE and is referred to by index in the VARIABLE keyword. For example:

```
CDF_COMPRESSION, id, VARIABLE=0, /ZVARIABLE,$
  GET_VAR_COMPRESSION=vComp
```

## Examples

```
; Create a CDF file and define the compression.
; Compression only works on Single-File CDFs:
id=CDF_CREATE('demo.cdf',[10,20],/Clobber,/SINGLE_FILE)
CDF_COMPRESSION,id,SET_COMPRESSION=1 ; (Run-length encoding)
att_id=CDF_ATTCREATE(id, 'Date',/GLOBAL)
CDF_ATTPUT,id,'Date',att_id,system()

; Change the compression type for the file to GZIP by using
; SET_GZIP_LEVEL:
CDF_COMPRESSION,id,SET_GZIP_LEVEL=7

; Retrieve compression information:
```

```

CDF_COMPRESSION,id,GET_GZIP_LEVEL=glevel,GET_COMPRESSION=gcomp
HELP,glevel,gcomp

; Create and compress an rVariable:
rid=CDF_VARCREATE(id,'rvar0',[1,1],/CDF_FLOAT)
CDF_COMPRESSION,id,SET_VAR_COMPRESSION=2,VARIABLE='rvar0'
CDF_VARPUT,id,'rvar0',findgen(10,20,5)
CDF_COMPRESSION,id,GET_VAR_COMPRESSION=v_comp,VARIABLE=rid,GET_VAR
_GZIP_LEVEL=v_glevel
HELP,v_comp,v_glevel

; Create and compress a zVariable:
zid=CDF_varcreate(id,'zvar0',[1,1,1],DIM=[10,20,30],/ZVARIABLE,$
/CDF_DOUBLE)

; You can set a compression and check it in the same call:
CDF_COMPRESSION,id,SET_VAR_GZIP_LEVEL=9,VARIABLE=zid,/ZVARIABLE,$
GET_VAR_GZIP_LEVEL=v_gzip
HELP,v_gzip

CDF_VARPUT,id,zid,dindgen(10,20,30),/ZVARIABLE

; File and variable keywords can be combined in the same call
; (Set calls are processed before Get calls)
CDF_COMPRESSION,id,GET_VAR_COMPRESSION=v_comp,VARIABLE='zvar0',$
/ZVARIABLE,SET_COMPRESSION=2,GET_COMPRESSION=file_comp
HELP,file_comp,v_comp

CDF_DELETE,id

```

## IDL Output

GLEVEL	LONG	=	7
GCOMP	LONG	=	5
V_COMP	LONG	=	2
V_GLEVEL	LONG	=	0

(Note that V\_GLEVEL is 0, since the variable compression is not GZIP.)

V_GZIP	LONG	=	9
FILE_COMP	LONG	=	2
V_COMP	LONG	=	5

## Version History

5.3	Introduced
-----	------------

## See Also

[CDF\\_CONTROL](#), [CDF\\_CREATE](#), [CDF\\_OPEN](#), [CDF\\_VARNUM](#)

# CDF\_CONTROL

The CDF\_CONTROL procedure allows you to obtain or set information for a Common Data Format file, its variables, and its attributes.

## Syntax

```
CDF_CONTROL, Id [, ATTRIBUTE=name or number]
  [, GET_ATTR_INFO=variable] [, GET_CACHESIZE=variable]
  [, GET_COPYRIGHT=variable] [, GET_FILENAME=variable]
  [, GET_FORMAT=variable] [, GET_NEGTOPOFP0_MODE=variable]
  [, GET_NUMATTRS=variable] [, GET_READONLY_MODE=variable]
  [, GET_RVAR_CACHESIZE=variable] [, GET_VAR_INFO=variable]
  [, GET_ZMODE=variable] [, GET_ZVAR_CACHESIZE=variable]
  [, SET_CACHESIZE=value] [, SET_EXTENDRECS=records]
  [, SET_INITIALRECS=records] [, /SET_NEGTOPOFP0_MODE]
  [, SET_PADVALUE=value] [, /SET_READONLY_MODE]
  [, SET_RVAR_CACHESIZE=value{See Note}]
  [, SET_RVARS_CACHESIZE=value{See Note}] [, SET_ZMODE={0 | 1 | 2}]
  [, SET_ZVAR_CACHESIZE=value{See Note}]
  [, SET_ZVARS_CACHESIZE=value{See Note}] [, VARIABLE=name or index]
  [, /ZVARIABLE]
```

**Note:** Use only with MULTI\_FILE CDF files

## Arguments

### Id

The CDF ID of the file being changed or queried, as returned from a previous call to CDF\_OPEN or CDF\_CREATE.

## Keywords

### ATTRIBUTE

Makes the attribute specified the current attribute. Either an attribute name or an attribute number may be specified.

## GET\_ATTR\_INFO

Set this keyword to a named variable that will contain information about the current attribute. Information is returned in the form of a structure with the following tags:

```
{ NUMGENTRIES:0L, NUMRENTRIES:0L, NUMZENTRIES:0L,
  MAXGENTRY:0L, MAXRENTY:0L, MAXZENTRY:0L }
```

The first three tags contain the number of globals, rVariables, and zVariables associated with the attribute. MAXGENTRY contains the highest index used, and the last two tags contain the highest variable ids that were used when setting the attribute's value.

Note that an attribute must be set before GET\_ATTR\_INFO can be used. For example:

```
CDF_CONTROL, id, ATTRIBUTE='ATT1', GET_ATTR_INFO=X
```

## GET\_CACHESIZE

Set this keyword to a named variable that will be set equal to the number of 512-byte cache buffers being used for the current .cdf file. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User's Guide*.

## GET\_COPYRIGHT

Set this keyword to a named variable that will contain the copyright notice of the CDF library now being used by IDL (as opposed to the library that was used to write the current CDF).

## GET\_FILENAME

Set this keyword to a named variable that will contain the pathname of the current .cdf file.

## GET\_FORMAT

Set this keyword to a named variable that will contain a string describing the CDF Format of the current CDF file. Possible formats are SINGLE\_FILE and MULTI\_FILE, and can only be set with the CDF\_CREATE procedure. For example:

```
id = CDF_CREATE('single', /SINGLE_FILE)
CDF_CONTROL, id, GET_FORMAT = cdfformat
HELP, cdfformat
```

IDL prints:

```
CDFFORMAT          STRING          = 'SINGLE_FILE'
```

## GET\_NEGTOPOSFP0\_MODE

Set this keyword to a named variable that will be set equal to the CDF negative to positive floating point 0.0 (NEGtoPOSfp0) mode. In NEGtoPOSfp0 mode, values equal to -0.0 will be converted to 0.0 whenever encountered. By CDF convention, a returned value of -1 indicates that this feature is enabled, and a returned value of zero indicates that this feature is disabled.

## GET\_NUMATTRS

Set this keyword to a named variable that will contain a two-element array of longs. The first value will contain the number of attributes with global scope; the second value will contain the number of attributes with variable scope. NOTE: attributes with GLOBAL\_SCOPE\_ASSUMED scope will be included in the global scope count and attributes with VARIABLE\_SCOPE\_ASSUMED will be included in the count of attributes with variable scope.

Note that you can obtain the total number of attributes using the [CDF\\_INQUIRE](#) routine.

## GET\_READONLY\_MODE

Set this keyword to a named variable that will be set equal to the CDF read-only mode. By CDF convention, a returned value of -1 indicates that the file is in read-only mode, and a returned value of zero indicates that the file is not in read-only mode.

## GET\_RVAR\_CACHESIZE

Set this keyword to a named variable that will be set equal to the number of 512-byte cache buffers being used for the current MULTI\_FILE format CDF and the rVariable indicated by the VARIABLE keyword. This keyword should only be used for MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## GET\_VAR\_INFO

Set this keyword to a named variable that will contain information about the current variable. For detailed information about the returned values, see “Records” in the *CDF User’s Guide*. Information is returned in the form of a structure with the following tags:

```
{ EXTENDRECS:0L, MAXALLOCRECS:0L, MAXREC:0L,
  MAXRECS:0L, NINDEXENTRIES:0L, NINDEXRECORDS:0L,
  PADVALUE:<as appropriate> }
```

The EXTENDRECS field will contain the number of records by which the current variable will be extended whenever a new record needs to be added.

The MAXALLOCREC field will contain the maximum record number (zero-based) allocated for the current variable. Records can only be allocated for NOVARY zVariables in SINGLE\_FILE format CDFs. When these conditions are not met, the value is set to -1.

The MAXREC field will contain the maximum record number for the current variable. For variables with a record variance of NOVARY, this will be at most zero. A value of -1 indicates that no records have been written.

The MAXRECS field will contain the maximum record number (zero-based) of all variables of this type (rVariable or zVariable) in the current CDF. A value of -1 indicates that no records have been written.

The NINDEXENTRIES field will contain the number of index entries for the current variable in the current CDF. This value is -1 unless the current CDF is of SINGLE\_FILE format, and the variable is a zVariable.

The NINDEXRECORDS field will contain the number of index records for the current variable in the current CDF. This value is -1 unless the current CDF is of SINGLE\_FILE format, and the variable is a zVariable.

The PADVALUE field will contain the value being used to fill locations that are not explicitly filled by the user. If a PADVALUE is not specified, CDF\_CONTROL returns an error.

For example:

```
fid = CDF_CREATE('test.cdf')
varid = CDF_VARCREATE(fid, 'test')
CDF_CONTROL, fid, GET_VAR_INFO=info, VARIABLE='test'
```

IDL Prints:

```
% CDF_CONTROL: Function completed but
NO_PADVALUE_SPECIFIED: A pad value has not been specified.
```

## GET\_ZMODE

Set this keyword to a named variable that will be set equal the zMode of the current CDF. In a non-zero zMode, CDF rVariables are temporarily replaced with zVariables. The possible return values are:

- 0 = zMode is off.
- 1 = zMode is on in zMode/1, indicating that the dimensionality and variances of the variables will stay the same.



- $2 = zMode$  is on in  $zMode/2$ , indicating that those dimensions with false variances (NOVARY) will be eliminated.

For Information about zModes, see “CDF Modes” in the *CDF User’s Guide*.

## GET\_ZVAR\_CACHESIZE

Set this keyword to a named variable that will be set equal to the number of 512-byte cache buffers being used in the current MULTI\_FILE format CDF and the zVariable indicated by the VARIABLE keyword. This keyword should only be used with MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## SET\_CACHESIZE

Set this keyword equal to the desired number of 512-byte cache buffers to used for the current .cdf file. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## SET\_EXTENDRECS

Set this keyword equal to the number of additional physical records that should be added to the current variable whenever it needs to be extended.

## SET\_INITIALRECS

Set this keyword equal to the number of records that should be initially written to the current variable. Note that this keyword should be set *before* writing any data to the variable.

## SET\_NEGTOPOSFP0\_MODE

Set this keyword to a non-zero value to put the current CDF file into negative to positive floating point 0.0 (NEGtoPOSfp0) mode. In this mode, values equal to -0.0 will be converted to 0.0 whenever encountered. Setting this keyword equal to zero takes the current CDF file out of NEGtoPOSfp0 mode.

## SET\_PADVALUE

Set this keyword equal to the pad value for the current variable.

## SET\_READONLY\_MODE

Set this keyword to a non-zero value to put the current CDF file into read-only mode. Set this keyword equal to zero to take the current CDF file out of read-only mode.

## SET\_RVAR\_CACHESIZE

Set this keyword equal to the desired number of 512-byte cache buffers to used for the rVariable file specified by the VARIABLE keyword. This keyword should only be used with MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## SET\_RVARS\_CACHESIZE

Set this keyword equal to the desired number of 512-byte cache buffers to used for all rVariable files in the current CDF file or files. This keyword should only be used with MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## SET\_ZMODE

Set this keyword to change the zMode of the current CDF. In a non-zero zMode, CDF rVariables are temporarily replaced with zVariables. Set this keyword to one (1) to change to zMode/1, in which the dimensionality and variances of the variables stay the same. Set this keyword to two (2) to change to zMode/2, in which those dimensions with false variances (NOVARY) are eliminated. For Information about zModes, see “CDF Modes” in the *CDF User’s Guide*.

## SET\_ZVAR\_CACHESIZE

Set this keyword equal to the desired number of 512-byte cache buffers to used for the zVariable’s file specified by the VARIABLE keyword. This keyword should only be used with MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## SET\_ZVARS\_CACHESIZE

Set this keyword equal to the desired number of 512-byte cache buffers to used for all zVariable files in the current CDF. This keyword should only be used with MULTI\_FILE CDF files. For discussion about using caches with CDF files, see “Caching Scheme” in the *CDF User’s Guide*.

## VARIABLE

Set this keyword to a name or index to set the current variable. The following example specifies that the variable MyData should have 20 records written to it initially:

```
CDF_CONTROL, id, VAR='MyData', SET_INITIALRECS=20
```

Note that if `VARIABLE` is set to the index of a `zVariable`, the `ZVARIABLE` keyword *must* also be set. If `ZVARIABLE` is not set, the variable is assumed to be an `rVariable`.

## ZVARIABLE

Set this keyword to `TRUE` if the current variable is a `zVariable` and is referred to by index. For example:

```
CDF_CONTROL, id, VARIABLE=0, /ZVARIABLE, GET_VAR_INFO=V
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[CDF\\_CREATE](#), [CDF\\_INQUIRE](#)

# CDF\_CREATE

The CDF\_CREATE function creates a new Common Data Format file with the given filename and dimensions.

Note that when you create a CDF file, you may specify both encoding and decoding methods. Encoding specifies the method used to write data to the CDF file. Decoding specifies the method used to retrieve data from the CDF file and pass it to an application (IDL, for example). Encoding and decoding methods are specified by setting the XXX\_ENCODING and XXX\_DECODING keywords to CDF\_CREATE. If no decoding method is specified, the decoding method is set to be the same as the encoding method.

All CDF encodings and decodings can be written or read on all platforms, but matching the encoding with the architecture used provides the best performance. Since most people work in a single-platform environment most of the time, the HOST\_ENCODING method is used as the default encoding scheme. This provides maximum performance. If you know that the CDF file will be transported to a computer using another architecture, specify the encoding for the target architecture or specify NETWORK\_ENCODING. Specifying the target architecture provides maximum performance on that architecture; specifying NETWORK\_ENCODING provides maximum flexibility.

For more discussion on CDF encoding/decoding methods and combinations, see “Encoding” and “Decoding” in the *CDF User’s Guide*.

---

## Note

Versions of IDL beginning with 6.3 support the CDF 3.1 library. If you need to create CDF files that can be read by earlier versions of IDL, or by CDF libraries earlier than version 3.0, use the

[CDF\\_SET\\_CDF27\\_BACKWARD\\_COMPATIBLE](#) routine.

---

## Syntax

```
Result = CDF_CREATE( Filename, [Dimensions] [, /CLOBBER] [, /MULTI_FILE |
    , /SINGLE_FILE] [, /COL_MAJOR | , /ROW_MAJOR] )
```

### Encoding Keywords (pick one):

```
[, /ALPHAOSF1_ENCODING]
[, /ALPHAVMSD_ENCODING]
[, /ALPHAVMSG_ENCODING]
[, /DECSTATION_ENCODING]
```

```
[, /HOST_ENCODING]  
[, /HP_ENCODING]  
[, /IBMPC_ENCODING]  
[, /IBMRS_ENCODING]  
[, /MAC_ENCODING]  
[, /NETWORK_ENCODING]  
[, /NEXT_ENCODING]  
[, /SGI_ENCODING]  
[, /SUN_ENCODING]
```

**Decoding Keywords (pick one):**

```
[, /ALPHAOSF1_DECODING]  
[, /ALPHAVMSD_DECODING]  
[, /ALPHAVMSG_DECODING]  
[, /DECSTATION_DECODING]  
[, /HOST_DECODING]  
[, /HP_DECODING]  
[, /IBMPC_DECODING]  
[, /IBMRS_DECODING]  
[, /MAC_DECODING]  
[, /NETWORK_DECODING]  
[, /NEXT_DECODING]  
[, /SGI_DECODING]  
[, /SUN_DECODING]
```

## Return Value

Returns the CDF ID for the new file.

## Arguments

### Filename

A scalar string containing the name of the file to be created. Note that if the desired filename has a `.cdf` ending, you can omit the extension and specify just the first part of the filename. For example, specifying `"mydata"` would open the file `mydata.cdf`.

## Dimensions

A vector of values specifying size of each rVariable dimension. If no dimensions are specified, the file will contain a single scalar per record (*i.e.*, a 0-dimensional CDF). This argument has no effect on zVariables.

## Keywords

### CLOBBER

Set this keyword to erase the existing file (if the file already exists) before creating the new version.

Note that if the existing file has been corrupted, the CLOBBER operation may fail, causing IDL to display an error message. In this case you must manually delete the existing file from outside IDL.

### COL\_MAJOR

Set this keyword to use column major (IDL-like) array ordering for variable storage.

### MULTI\_FILE

Set this keyword to cause all CDF control information and attribute entry data to be placed in one `.cdf` file, with a separate file created for each defined variable. If the variable is an rVariable, then the variable files will have extensions of `.v0`, `.v1`, *etc.*; zVariables will be stored in files with extensions of `.z0`, `.z1`, *etc.* See “Format” in the *CDF User’s Guide* for more information. If both `SINGLE_FILE` and `MULTI_FILE` are set the file will be created in the `SINGLE_FILE` format.

#### Note

---

In versions of IDL prior to 6.3, `MULTI_FILE` was the default.

---

#### MULTI\_FILE Example:

```
id=CDF_CREATE('multi', /MULTI_FILE)
CDF_CONTROL, id, GET_FORMAT=cdf_format
HELP, cdf_format
```

#### IDL prints:

```
CDF_FORMAT      STRING      = 'MULTI_FILE'
```

## ROW\_MAJOR

Set this keyword to specify row major (C-like) array ordering for variable storage. This is the default.

## SINGLE\_FILE

Set this keyword to cause all CDF information (control information, attribute entry data, variable data, etc.) to be written to a single `.cdf` file. This is the default. See “Format” in the *CDF User’s Guide* for more information. If both `SINGLE_FILE` and `MULTI_FILE` are set the file will be created in the `SINGLE_FILE` format.

### Note

---

In versions of IDL prior to 6.3, `MULTI_FILE` was the default.

---

## Encoding Keywords

Select one of the following keywords to specify the type of encoding:

### ALPHAOSF1\_ENCODING

Set this keyword to indicate DEC ALPHA/OSF1 data encoding.

### ALPHAVMSD\_ENCODING

Set this keyword to indicate DEC ALPHA/VMS data encoding using Digital’s `D_FLOAT` representation.

### ALPHAVMSG\_ENCODING

Set this keyword to indicate DEC ALPHA/VMS data encoding using Digital’s `G_FLOAT` representation.

### DECSTATION\_ENCODING

Set this keyword to select Decstation (MIPSEL) data encoding.

### HOST\_ENCODING

Set this keyword to select that the file will use native data encoding. This is the default method.

### HP\_ENCODING

Set this keyword to select HP 9000 data encoding.

## **IBMPC\_ENCODING**

Set this keyword to select IBM PC data encoding.

## **IBMRS\_ENCODING**

Set this keyword to select IBM RS/6000 series data encoding.

## **MAC\_ENCODING**

Set this keyword to select Macintosh data encoding.

## **NETWORK\_ENCODING**

Set this keyword to select network-transportable data encoding (XDR).

## **NEXT\_ENCODING**

Set this keyword to select NeXT data encoding.

## **SGI\_ENCODING**

Set this keyword to select SGI (MIPSEB) data encoding (Silicon Graphics Iris and Power series).

## **SUN\_ENCODING**

Set this keyword to select SUN data encoding.

## **Decoding Keywords**

Select one of the following keywords to specify the type of decoding:

### **ALPHAOSF1\_DECODING**

Set this keyword to indicate DEC ALPHA/OSF1 data decoding.

### **ALPHAVMSD\_DECODING**

Set this keyword to indicate DEC ALPHA/VMS data decoding using Digital's D\_FLOAT representation.

### **ALPHAVMSG\_DECODING**

Set this keyword to indicate DEC ALPHA/VMS data decoding using Digital's G\_FLOAT representation.



## **DECSTATION\_DECODING**

Set this keyword to select Decstation (MIPSEL) data decoding.

## **HOST\_DECODING**

Set this keyword to select that the file will use native data decoding. This is the default method.

## **HP\_DECODING**

Set this keyword to select HP 9000 data decoding.

## **IBMPC\_DECODING**

Set this keyword to select IBM PC data decoding.

## **IBMRS\_DECODING**

Set this keyword to select IBM RS/6000 series data decoding.

## **MAC\_DECODING**

Set this keyword to select Macintosh data decoding.

## **NETWORK\_DECODING**

Set this keyword to select network-transportable data decoding (XDR).

## **NEXT\_DECODING**

Set this keyword to select NeXT data decoding.

## **SGI\_DECODING**

Set this keyword to select SGI (MIPSEB) data decoding (Silicon Graphics Iris and Power series).

## **SUN\_DECODING**

Set this keyword to select SUN data decoding.

## **Examples**

Use the following command to create a 10-element by 20-element CDF using network encoding and Sun decoding:

```

id = CDF_CREATE('cdf_create.cdf', [10,20], /NETWORK_ENCODING, $
/SUN_DECODING)
; ... other cdf commands ...
CDF_CLOSE, id ; close the file.

```

Now suppose that we decide to use HP\_DECODING instead. We can use the CLOBBER keyword to delete the existing file when creating the new file:

```

id = CDF_CREATE('cdf_create.cdf', [10,20], /NETWORK_ENCODING, $
/HP_DECODING, /CLOBBER)
; ... other cdf commands ...
CDF_CLOSE, id ; close the file.

```

The new file is written over the existing file. Use the following command to delete the file:

```

CDF_DELETE, id

```

## Version History

Pre 4.0	Introduced
6.3	<p>Changed default behavior to create a single file rather than multiple files (see <a href="#">SINGLE_FILE</a> and <a href="#">MULTI_FILE</a>)</p> <p>Changed default behavior to use HOST_ENCODING rather than NETWORK_ENCODING</p> <p>Changed default behavior to use HOST_DECODING rather than NETWORK_DECODING</p>

# CDF\_DELETE

The CDF\_DELETE procedure deletes the specified Common Data Format file. Files deleted include the original .cdf file and the .v0, .v1, etc. files if they exist.

## Syntax

```
CDF_DELETE, Id
```

## Arguments

### Id

The CDF ID of the file to be deleted, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

## Keywords

None

## Examples

```
id = CDF_OPEN('open_close.cdf'); Open a file.  
; ... other CDF_ commands ...  
CDF_DELETE, id ; Close and Delete the cdf file.
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_DOC

The CDF\_DOC procedure retrieves general documentation information about a Common Data Format file.

## Syntax

```
CDF_DOC, Id, Version, Release, Copyright [, INCREMENT=variable]
```

## Arguments

### Id

A CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Version

A named variable in which the version number of the CDF library that created the CDF is returned.

### Release

A named variable in which the release number of the CDF library that created the CDF is returned.

### Copyright

A named variable in which the copyright notice of the CDF library that created the CDF is returned.

## Keywords

### INCREMENT

Set this keyword to a named variable that will contain the increment of the CDF library that created the specified CDF file.

## Examples

```
id=CDF_CREATE('VersionCheck')    ; Create a CDF file.
CDF_DOC, id, vers, rel, copy, INCREMENT=incr
PRINT, 'File Written Using CDF', vers, rel, incr, $
      FORMAT='(A,I1, ". ", I1, "r", I2)'
```

```
CDF_CLOSE, id ; Close the CDF file.
```

### IDL Output

```
File Written Using CDF2.6
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_ENCODE\_EPOCH

The CDF\_ENCODE\_EPOCH function encodes a CDF\_EPOCH variable into a string. Four different string formats are available. The default (EPOCH=0) is the standard CDF format, which may be parsed by the CDF\_PARSED\_EPOCH function or broken down with the CDF\_EPOCH procedure.

## Syntax

*Result* = CDF\_ENCODE\_EPOCH(*Epoch* [, EPOCH={0 | 1 | 2 | 3}])

## Return Value

Returns a string containing the encoded CDF\_EPOCH variable.

## Arguments

### Epoch

The double-precision CDF\_EPOCH value to be encoded. For more information about CDF\_EPOCH values, see “Data Types” in the *CDF User’s Guide*.

## Keywords

### EPOCH

Set this keyword equal to one of the following integer values, specifying the epoch mode to use for output of the epoch date string:

Value	Date Format
0	DD-Mon-YYYY hh:mm:ss.ccc (This is the default)
1	YYYYMMDD.tttttttt
2	YYYYMMDDhhmmss
3	YYYY-MM-DDThh:mm:ss.cccZ (The characters T and Z are the CDF_EPOCH type 3 place holders)

where:

Date Element	Represents
DD	the day of the month (1-31)
Mon	the abbreviated month name: (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec)
MM	the month number (1-12)
YYYY	the year (A.D.)
hh	the hour (0-23)
mm	the minute (0-59)
ss	the second (0-59)
ccc	the millisecond (0-999)
ttttttt	the fraction of the day ( <i>e.g.</i> 2500000 is 6 am).

## Examples

```
epoch_string = '04-Dec-1995 20:19:18.176'
epoch = CDF_PARSE_EPOCH(epoch_string)
HELP, epoch_string, epoch
```

```
; Create encode strings:
encode0 = CDF_ENCODE_EPOCH(epoch, EPOCH=0)
encode1 = CDF_ENCODE_EPOCH(epoch, EPOCH=1)
encode2 = CDF_ENCODE_EPOCH(epoch, EPOCH=2)
encode3 = CDF_ENCODE_EPOCH(epoch, EPOCH=3)
```

```
; Compare encoding formats:
HELP, encode0, encode1, encode2, encode3
```

### IDL Output

```
EPOCH_STRING    STRING    = '04-Dec-1995 20:19:18.176'
EPOCH           DOUBLE   =      6.2985328e+13

ENCODE0         STRING   = '04-Dec-1995 20:19:18.176'
ENCODE1         STRING   = '19951204.8467381'
ENCODE2         STRING   = '19951204201918'
ENCODE3         STRING   = '1995-12-04T20:19:18.176Z'
```

## Version History

---

4.0.1b	Introduced
--------	------------

---

## See Also

[CDF\\_EPOCH](#), [CDF\\_PARSE\\_EPOCH](#)



# CDF\_ENCODE\_EPOCH16

The CDF\_ENCODE\_EPOCH16 function encodes a CDF\_EPOCH16 value into the standard date and time character string.

## Syntax

```
Result = CDF_ENCODE_EPOCH16(Epoch16 [, EPOCH={0 | 1 | 2 | 3}])
```

## Return Value

Returns the string representation of the given CDF\_EPOCH16 value.

## Arguments

### Epoch16

The double-precision CDF\_EPOCH16 value to be encoded.

### Note

The CDF\_EPOCH16 value can be obtained by calling [CDF\\_EPOCH16](#) with the COMPUTE keyword, or by calling [CDF\\_PARSE\\_EPOCH16](#).

## Keywords

### EPOCH

Set this keyword equal to one of the following integer values, specifying the epoch mode to use for output of the epoch date string:

Value	Date Format
0	DD-Mon-YYYY hh:mm:ss.ccc.uuu.nnn.ppp (This is the default)
1	YYYYMMDD.tttttttttttttttt
2	YYYYMMDDss
3	YYYY-MM-DDThh:mm:ss.ccc.uuu.nnn.pppZ (The characters T and Z are the CDF_EPOCH16 type 3 place holders)

where:

Date Element	Represents
DD	the day of the month (1-31)
Mon	the abbreviated month name: (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec)
MM	the month number (1-12)
YYYY	the year (A.D.)
hh	the hour (0-23)
mm	the minute (0-59)
ss	the second (0-59)
ccc	the millisecond (0-999)
uuu	the microsecond (0-999)
nnn	the nanosecond (0-999)
ppp	the picosecond (0-999)
tttttttttttttttt	the fraction of the day ( <i>e.g.</i> 500000000000000 is noon).

## Examples

```
test_string = '04-Dec-2005 20:19:18.176.214.648.000'
test_epoch = CDF_PARSE_EPOCH16(test_string)
PRINT, CDF_ENCODE_EPOCH16(test_epoch)
```

IDL Output

```
04-Dec-2005 20:19:18.176.214.648.000
```

## Version History

6.3	Introduced
-----	------------

## See Also

[CDF\\_EPOCH16](#), [CDF\\_PARSE\\_EPOCH16](#)

# CDF\_EPOCH

The CDF\_EPOCH procedure computes or breaks down CDF\_EPOCH values in a CDF file. When computing an epoch, any missing value is considered to be zero.

If you supply a value for the Epoch argument and set the BREAKDOWN\_EPOCH keyword, CDF\_EPOCH will compute the values of the Year, Month, Day, etc. and insert the values into the named variables you supply. If you specify the Year (and optionally, the Month, Day, etc.) and set the COMPUTE\_EPOCH keyword, CDF\_EPOCH will compute the epoch and place the value in the named variable supplied as the Epoch parameter.

---

## Note

You must set either the BREAKDOWN\_EPOCH or COMPUTE\_EPOCH keyword.

---

## Syntax

```
CDF_EPOCH, Epoch, Year [, Month, Day, Hour, Minute, Second, Milli]
    [, /BREAKDOWN_EPOCH] [, /COMPUTE_EPOCH]
```

## Arguments

### Epoch

The Epoch value to be broken down, or a named variable that will contain the computed epoch will be placed. The Epoch value is the number of milliseconds since 01-Jan-0000 00:00:00.000

---

## Note

“Year zero” is a convention chosen by NSSDC to measure epoch values. This date is more commonly referred to as 1 BC. Remember that 1 BC was a leap year. The Epoch is defined as the number of milliseconds since 01-Jan-0000 00:00:00.000, as computed using the CDF library’s internal date routines. The CDF date/time calculations do not take into account the changes to the Gregorian calendar, and cannot be directly converted into Julian date/times. To convert between CDF epochs and date/times, use the CDF\_EPOCH routine with either the BREAKDOWN\_EPOCH or CONVERT\_EPOCH keywords.

---

### Year

If COMPUTE\_EPOCH is set, a four-digit integer representing the year.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the year.

## Month

If `COMPUTE_EPOCH` is set, an integer between 1 and 12 representing the month. Alternately, you can set *Month* equal to zero, in which case the *Day* argument can take on any value between 1-366.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the numeric month value.

## Day

If `COMPUTE_EPOCH` is set, an integer between 1 and 31 representing the day of the month. Alternately, if the *Month* argument is set equal to zero, *Day* can be an integer between 1-366 representing the day of the year.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the numeric day of the month value.

## Hour

If `COMPUTE_EPOCH` is set, an integer between 0 and 23 representing the hour of the day.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the numeric hour of the day value.

## Minute

If `COMPUTE_EPOCH` is set, an integer between 0 and 59 representing the minute of the hour.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the numeric minute of the hour value.

## Second

If `COMPUTE_EPOCH` is set, an integer between 0 and 59 representing the second of the minute.

If `BREAKDOWN_EPOCH` is set, a named variable that will contain the numeric second of the minute value.

## Milli

If COMPUTE\_EPOCH is set, an integer between 0 and 999 representing the millisecond. Alternately, if the *Hour*, *Minute*, and *Second* arguments are set all equal to zero, *Milli* can be an integer between 0-86400000 representing the millisecond of the day.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric millisecond value.

## Keywords

### BREAKDOWN\_EPOCH

Set this keyword to break down the value of the *Epoch* argument into its component parts, storing the resulting year, month, day, *etc.* values in the variables specified by the corresponding arguments.

### COMPUTE\_EPOCH

Set this keyword to compute the value of *Epoch* from the values specified by the *Year*, *Month*, *Day*, *etc.* arguments.

## Examples

To compute the epoch value of September 20, 1992 at 3:00 am:

```
CDF_EPOCH, MergeDate, 1992, 9, 20, 3, /COMPUTE_EPOCH
```

To break down the given epoch value into standard date components:

```
CDF_EPOCH, 4.7107656e13, yr, mo, dy, hr, mn, sc, milli, /BREAK
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_EPOCH16

The CDF\_EPOCH16 procedure computes or breaks down a CDF\_EPOCH16 value in a CDF file. When computing an epoch, any missing value is considered to be zero.

If you supply a value for the *Epoch* argument and set the BREAKDOWN\_EPOCH keyword, CDF\_EPOCH16 will compute the values of the *Year*, *Month*, *Day*, *etc.* and insert the values into the named variables you supply.

If you specify the *Year* (and optionally, the *Month*, *Day*, *etc.*) and set the COMPUTE\_EPOCH keyword, CDF\_EPOCH16 will compute the epoch and place the value in the named variable supplied as the *Epoch* parameter.

---

## Note

You *must* set either the BREAKDOWN\_EPOCH or COMPUTE\_EPOCH keyword.

---

## Syntax

CDF\_EPOCH16, *Epoch*, *Year* [, *Month*, *Day*, *Hour*, *Minute*, *Second*, *Milli*, *Micro*, *Nano*, *Pico*] [, /BREAKDOWN\_EPOCH] [, /COMPUTE\_EPOCH]

## Arguments

### Epoch

The Epoch value to be broken down, or a named variable that will contain the computed epoch will be placed. The Epoch value is the number of picoseconds since 01-Jan-0000 00:00:00.000.000.000.000.

---

## Note

“Year zero” is a convention chosen by CDF to measure epoch values. This date is more commonly referred to as 1 BC. Remember that 1 BC was a leap year. The Epoch is defined as the number of picoseconds since 01-Jan-0000 00:00:00.000.000.000.000, as computed using the CDF library’s internal date routines. The CDF date/time calculations do not take into account the changes to the Gregorian calendar, and cannot be directly converted into Julian date/times. To convert between CDF epochs and date/times, use the CDF\_EPOCH16 routine with either the BREAKDOWN\_EPOCH or CONVERT\_EPOCH keywords.

---

## Year

If COMPUTE\_EPOCH is set, a four-digit integer representing the year.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the year.

## Month

If COMPUTE\_EPOCH is set, an integer between 1 and 12 representing the month. Alternately, you can set *Month* equal to zero, in which case the *Day* argument can take on any value between 1-366.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric month value.

## Day

If COMPUTE\_EPOCH is set, an integer between 1 and 31 representing the day of the month. Alternately, if the *Month* argument is set equal to zero, *Day* can be an integer between 1-366 representing the day of the year.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric day of the month value.

## Hour

If COMPUTE\_EPOCH is set, an integer between 0 and 23 representing the hour of the day.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric hour of the day value.

## Minute

If COMPUTE\_EPOCH is set, an integer between 0 and 59 representing the minute of the hour.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric minute of the hour value.

## Second

If COMPUTE\_EPOCH is set, an integer between 0 and 59 representing the second of the minute.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric second of the minute value.

## Milli

If COMPUTE\_EPOCH is set, an integer between 0 and 999 representing the millisecond.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric millisecond value.

## Micro

If COMPUTE\_EPOCH is set, an integer between 0 and 999 representing the microsecond.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric microsecond value.

## Nano

If COMPUTE\_EPOCH is set, an integer between 0 and 999 representing the nanosecond.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric nanosecond value.

## Pico

If COMPUTE\_EPOCH is set, an integer between 0 and 999 representing the picosecond.

If BREAKDOWN\_EPOCH is set, a named variable that will contain the numeric picosecond value.

## Keywords

### BREAKDOWN\_EPOCH

Set this keyword to break down the value of the *Epoch* argument into its component parts, storing the resulting year, month, day, *etc.* values in the variables specified by the corresponding arguments.

### COMPUTE\_EPOCH

Set this keyword to compute the value of *Epoch* from the values specified by the *Year, Month, Day, etc.* arguments.



## Examples

To compute the epoch value of September 20, 2005 at 3:05:46:02:156 am:

```
CDF_EPOCH16, epoch, 2005, 9, 20, 3, 5, 46, 27, 2, 156, $  
/COMPUTE_EPOCH
```

To break down the given epoch value into standard date components:

```
CDF_EPOCH16, epoch, yr, mo, dy, hr, min, sec, milli, micro, pico, $  
/BREAKDOWN_EPOCH
```

## Version History

6.3	Introduced
-----	------------

# CDF\_ERROR

The CDF\_ERROR function returns a short explanation of a given status code returned from a Common Data Format file.

## Syntax

*Result* = CDF\_ERROR(*Status*)

## Return Value

Returns a string containing a status code explanation.

## Arguments

### Status

The status code to be explained.

## Keywords

None

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_EXISTS

The CDF\_EXISTS function returns true if the Common Data Format (CDF) scientific data format library is supported on the current IDL platform.

This routine is written in the IDL language. Its source code can be found in the file `cdf_exists.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

*Result* = CDF\_EXISTS()

## Return Value

Returns a 1 (True) if the library is supported or a 0 (False) if the library is not supported.

## Arguments

None

## Keywords

None

## Examples

The following IDL command prints an error message if the CDF library is not available:

```
IF CDF_EXISTS() EQ 0 THEN PRINT, 'CDF not supported.'
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_INQUIRE

The CDF\_INQUIRE function returns global information about the Common Data Format file. The tags of this structure are described below.

## Syntax

*Result* = CDF\_INQUIRE(*Id*)

## Return Value

This information is returned in a structure of the form:

```
{ NDIMS:0L, DECODING:"", ENCODING:"", MAJORITY:"", MAXREC:0L, $
  NVAR:0L, NZVAR:0L, NATTS:0L, DIM:LONARR(NDIMS) }
```

## Explanation of the Structure Tags

The structure returned by this function consists of the following tags:

Tag	Description
NDIMS	The longword integer specifying the number of dimensions in the rVariables in the current CDF.
DECODING	A string describing the decoding type set in the CDF file, such as 'MAC_DECODING' or 'ALPHAVMSD_ENCODING'.
ENCODING	A string describing the type of encoding used in the CDF file, such as 'NETWORK_ENCODING' or 'SUN_ENCODING'.
MAJORITY	A string describing the majority used in the CDF file. The majority will be either row ('ROW_MAJOR') or column ('COL_MAJOR').
MAXREC	A longword integer specifying the highest record number written in the rVariables in the current CDF. The MAXREC field will contain the value -1 if no rVariables have yet been written to the CDF.
NVAR	A longword integer specifying the number of rVariables (regular variables) in the CDF.

Table 2-1: CDF\_INQUIRE Structure Tags

Tag	Description
NZVARS	A longword integer specifying the number of zVariables in the CDF.
NATTS	A longword integer specifying the number of attributes in the CDF. Note that the number returned in this field includes both global and variable attributes. You can use the GET_NUMATTR keyword to the <a href="#">CDF_CONTROL</a> routine to determine the number of each.
DIM	A vector where each element contains the corresponding dimension size for the rVariables in the current CDF. For 0-dimensional CDF's, this argument contains a single element (a zero).

Table 2-1: *CDF\_INQUIRE Structure Tags (Continued)*

## Arguments

### Id

A CDF ID, returned from a previous call to `CDF_OPEN` or `CDF_CREATE`.

## Keywords

None

## Examples

```

cdfid = CDF_CREATE('CDFinquire', /HP_ENCODING, /MAC_DECODING)
attr1_id = CDF_ATTCREATE(cdfid, 'GLOBAL_ATT', /GLOBAL_SCOPE)
attr2_id = CDF_ATTCREATE(cdfid, 'VARIABLE_ATT', /VARIABLE_SCOPE)
CDF_CONTROL, cdfid, GET_NUMATTRS = num_attrs
PRINT, 'This CDF has ', num_attrs(0), $
      'Global attribute(s) and ', num_attrs(1), $
      'Variable attribute(s).', $
      FORMAT='(A,I2,A,I2,A)'

inquire = CDF_INQUIRE(cdfid)
HELP, inquire, /STRUCT
CDF_DELETE, cdfid ; Delete the CDF file.

```

## IDL Output

This CDF has 1 Global attribute(s) and 1 Variable attribute(s).

```
** Structure <4003e0c0>, 9 tags, length=48, refs=1:
NDIMS          LONG          0
DECODING       STRING        'MAC_DECODING'
ENCODING       STRING        'HP_ENCODING'
MAJORITY       STRING        'ROW_MAJOR'
MAXREC         LONG          -1
NVAR           LONG          0
NZVAR          LONG          0
NATTS          LONG          2
DIM            LONG          Array(1)
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[CDF\\_CONTROL](#), [CDF\\_DOC](#), [CDF\\_LIB\\_INFO](#)

# CDF\_LIB\_INFO

The CDF\_LIB\_INFO procedure returns information about the CDF Library being used by this version of IDL. Information about the version of CDF used to create a particular CDF file can be obtained through CDF\_DOC.

## Syntax

```
CDF_LIB_INFO [, COPYRIGHT=variable] [, INCREMENT=variable]  
            [, RELEASE=variable] [, SUBINCREMENT=variable] [, VERSION=variable]
```

## Arguments

None

## Keywords

### COPYRIGHT

A named variable in which the copyright notice of the CDF library that this version of IDL is using will be returned.

### INCREMENT

A named variable in which the incremental number of the CDF library that this version of IDL is using will be returned.

### RELEASE

A named variable in which the release number of the CDF library that this version of IDL is using will be returned.

### SUBINCREMENT

A named variable in which the sub incremental character of the CDF library that this version of IDL is using will be returned.

### VERSION

A named variable in which the version number of the CDF library that this version of IDL is using will be returned.

## Examples

```
CDF_LIB_INFO, VERSION=V, RELEASE=R, COPYRIGHT=C, $
  INCREMENT=I
PRINT, 'IDL ', !version.release, 'uses CDF Library ', $
  V, R, I, FORMAT='(A,A,A,I0,".",I0,".",I0,A)'
PRINT, C
```

### IDL Output

```
IDL 6.3 uses CDF Library 3.1.1
Common Data Format (CDF)
(C) Copyright 1990-2005 NASA/GSFC
Space Physics Data Facility
NASA/Goddard Space Flight Center
Greenbelt, Maryland 20771 USA
(Internet -- CDFSUPPORT@LISTSERV.GSFC.NASA.GOV)
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[CDF\\_DOC](#)



# CDF\_OPEN

The CDF\_OPEN function opens an existing Common Data Format file.

## Syntax

```
Result = CDF_OPEN(Filename)
```

## Return Value

If successful, the CDF ID for the file is returned.

## Arguments

### Filename

A scalar string containing the name of the file to be created. Note that if the desired filename has a .cdf ending, you can omit the extension and specify just the first part of the filename. For example, specifying “mydata” would open the file `mydata.cdf`.

## Keywords

None

## Examples

```
id = CDF_OPEN('open_close.cdf')    ; Open a file.  
; ... other CDF_ commands ...  
CDF_CLOSE, id ; Close the cdf file.
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_PARSE\_EPOCH

The CDF\_PARSE\_EPOCH function parses a properly-formatted input string into a double-precision value properly formatted for use as a CDF\_EPOCH variable.

---

## Note

CDF\_EPOCH variables may be unparsed into a variety of formats using the CDF\_ENCODE\_EPOCH function.

---

## Syntax

$$Result = CDF\_PARSE\_EPOCH(Epoch\_string)$$

## Return Value

Returns the double-precision value of the input string properly formatted for use as a CDF\_EPOCH variable.

## Arguments

### Epoch\_string

A formatted string that will be parsed into a double precision value suitable to be used as a CDF\_EPOCH value. The format of the date string is:

DD-Mon-YYYY hh:mm:ss.ccc

where:

Date Element	Represents
DD	the day of the month (1-31)
Mon	the abbreviated month name: (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec)
YYYY	the year (A.D.)
hh	the hour (0-23)
mm	the minute (0-59)

Date Element	Represents
ss	the second (0-59)
ccc	the millisecond (0-999)

For more information about CDF\_EPOCH values, see “Data Types” in the *CDF User’s Guide*.

## Keywords

None

## Examples

```
test_string = '04-Dec-1995 20:19:18.176'
test_epoch = CDF_PARSE_EPOCH(test_string)
HELP, test_string, test_epoch
PRINT, CDF_ENCODE_EPOCH(test_epoch, EPOCH=0)
```

### IDL Output

```
TEST_STRING      STRING      = '04-Dec-1995 20:19:18.176'
TEST_EPOCH       DOUBLE      =      6.2985328e+13
```

```
04-Dec-1995 20:19:18.176
```

## Version History

4.0.1b	Introduced
--------	------------

## See Also

[CDF\\_ENCODE\\_EPOCH](#), [CDF\\_EPOCH](#)

# CDF\_PARSE\_EPOCH16

The CDF\_PARSE\_EPOCH16 function parses a properly-formatted input string into a double-complex value properly formatted for use as a CDF\_EPOCH16 variable.

## Note

CDF\_EPOCH16 variables may be unparsed into a variety of formats using the CDF\_ENCODE\_EPOCH16 or CDF\_EPOCH16 functions.

## Syntax

Result = CDF\_PARSE\_EPOCH16(*Epoch\_string*)

## Return Value

Returns the double-precision complex value of the input string properly formatted for use as a CDF\_EPOCH16 variable.

## Arguments

### Epoch\_string

A formatted string that will be parsed into a double precision complex value suitable to be used as a CDF\_EPOCH value. The format of the date string is:

DD-Mon-YYYY hh:mm:ss.ccc.uuu.nnn.ppp

where:

Date Element	Represents
DD	the day of the month (1-31)
Mon	the abbreviated month name: (Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, or Dec)
YYYY	the year (A.D.)
hh	the hour (0-23)
mm	the minute (0-59)
ss	the second (0-59)

Date Element	Represents
ccc	the millisecond (0-999)
uuu	the microsecond (0-999)
nnn	the nanosecond (0-999)
ppp	the picosecond (0-999)

## Keywords

None

## Example

```
test_string = '04-Dec-2005 20:19:18.176.214.648.000'
test_epoch = CDF_PARSE_EPOCH16(test_string)
CDF_EPOCH16, test_epoch, year, month, day, hour, min, sec, $
    milli, micro, nano, pico, /BREAKDOWN_EPOCH
HELP, test_string, test_epoch
PRINT, CDF_ENCODE_EPOCH16(test_epoch)
PRINT, year, month, day, hour, min, sec, milli, micro, nano, pico
```

IDL Prints:

```
TEST_STRING      STRING      = '04-Dec-2005 20:19:18.176.214.648.000'
TEST_EPOCH      DCOMPLEX   = ( 6.3300947e+10, 1.7621465e+11)

04-Dec-2005 20:19:18.176.214.648.000
2005 12 4 20 19 18 176 214 648 0
```

## Version History

6.3	Introduced
-----	------------

## See Also

[CDF\\_ENCODE\\_EPOCH16](#), [CDF\\_EPOCH16](#)

# CDF\_SET\_CDF27\_BACKWARD\_COMPATIBLE

The CDF\_SET\_CDF27\_BACKWARD\_COMPATIBLE procedure allows users of IDL version 6.3 and later to create a CDF file that can be read by IDL 6.2 or earlier, or by CDF version 2.7.2 or earlier. By default, a CDF file created by IDL 6.3 or later cannot be read by earlier versions.

This procedure must be called prior to calling the CDF\_CREATE function. It is useful if you need to create and share CDF files with colleagues who access CDF files using IDL version 6.2 or earlier, or using the CDF library version 2.7.2 or earlier.

In CDF version 2.7.2 and earlier, the maximum CDF file size was 2 Gbytes. This limitation was lifted in CDF version 3.0 with the use of a 64-bit file offset. As a result, users who use a CDF library older than CDF version 3.0 cannot read CDF files that were produced by CDF version 3.0 or a later release. CDF versions 3.0 and later *can* read files that were generated with any of the previous CDF releases.

---

**Note**

After calling this routine, the “backward compatible” setting specified persists either until this routine is called again or until the end of the IDL session.

---

## Syntax

```
CDF_SET_CDF27_BACKWARD_COMPATIBLE [, /YES | /NO]
```

## Arguments

None

## Keywords

### YES

Set this keyword to create a CDF file that can be read by IDL version 6.2 or earlier, or by CDF version 2.7.2 or earlier. If this keyword is set, the maximum file size is 2 Gbytes.

### NO

Set this keyword to create a file that can only be read using IDL version 6.3 or later or CDF version 3.0 or later. This is the default when a CDF file is created.

## Examples

Use the following command to create a CDF file that can be read by IDL 6.2 or earlier IDL versions.

```
CDF_SET_CDF27_BACKWARD_COMPATIBLE, /YES
id = CDF_CREATE('myfile.cdf')
CDF_CLOSE, id
```

## Version History

6.3	Introduced
-----	------------

# CDF\_VARCREATE

The CDF\_VARCREATE function creates a new variable in a Common Data Format file.

In CDF, *variable* is a generic name for an object that represents data. Data can be scalar (0-dimensional) or multi-dimensional (up to 10-dimensional). Data does not have any associated scientific context; it could represent an independent variable, a dependent variable, a time and date value, an image, the name of an XML file, *etc.* You can describe a variable's relationship to other variables via CDF's *attributes*.

CDF supports two types of variables: zVariables and rVariables. Different zVariables in a CDF data set can have different numbers of dimensions and different dimension sizes. All rVariables in a CDF data set must have the same number of dimensions and the same dimension sizes; this is much less efficient than the zVariable storage mechanism. (rVariables were included in the original version of CDF, and zVariables were added in a later version to address the rVariables' inefficient use of disk space.)

If you are working with a data set created using an early version of CDF, you may need to use rVariables. If you are creating a new CDF data set, you should use zVariables.

## Syntax

```
Result = CDF_VARCREATE( Id, Name [, DimVary] [, /VariableType]
    [, ALLOCATERECS=records] [, DIMENSIONS=array]
    [, NUMELEM=characters] [, /REC_NOVARY | , /REC_VARY]
    [, /ZVARIABLE] )
```

## Return Value

Returns the variable of the type specified by the chosen keyword.

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Name

A string containing the name of the variable to be created.



## DimVary

A one-dimensional array containing one element per CDF dimension. If the element is non-zero or the string 'VARY', the variable will have variance in that dimension. If the element is zero or the string 'NOVARY' then the variable will have no variance with that dimension. If the variable is zero-dimensional, this argument may be omitted.

## Keywords

### VariableType

You must specify the type variable being created. This is done by setting one of the following keywords:

**CDF\_BYTE**

**CDF\_CHAR**

**CDF\_DOUBLE**

**CDF\_EPOCH**

**CDF\_EPOCH16**

**CDF\_FLOAT**

**CDF\_INT1**

**CDF\_INT2**

**CDF\_INT4**

**CDF\_REAL4**

**CDF\_REAL8**

**CDF\_UCHAR**

**CDF\_UINT1**

**CDF\_UINT2**

**CDF\_UINT4**

If no type is specified, CDF\_FLOAT is assumed.

## ALLOCATERECS

Set this keyword equal to the desired number of pre-allocated records for this variable in a SINGLE\_FILE CDF file. Pre-allocating records ensures that variable data is stored contiguously in the CDF file. For discussion about allocating records, see “Records” in the *CDF User’s Guide*.

## DIMENSIONS

Set this keyword to create a new zVariable with the specified dimensions. If this keyword is not set, the variable is assumed to be a scalar. For example:

```
id = CDF_CREATE("cdffile.cdf", [100] )
zid = CDF_VARCREATE(id, "Zvar", [1,1,1], DIM=[10,20,30])
```

---

### Note

Variables created with the DIMENSIONS keyword set are always zVariables.

---

## NUMELEM

The number of elements of the data type at each variable value. This keyword only has meaning for string data types (CDF\_CHAR, CDF\_UCHAR). This is the number of characters in the string. The default is 1.

## REC\_NOVARY

If this keyword is set, all records will contain the same information.

## REC\_VARY

If this keyword is set, all records will contain unique data. This is the default.

## ZVARIABLE

Set this keyword to create a zVariable. For example:

```
id = CDF_CREATE("cdffile.cdf", [100] )
zid = CDF_VARCREATE(id, "Zvar", /ZVARIABLE)
```

---

### Note

zVariables are much more efficient than rVariables in their use of disk space. Unless the recipient of your data set is using a very early version of CDF, you should always create zVariables.

---

**Note**


---

Variables created with the DIMENSIONS keyword set are always zVariables.

---

## Examples

In this example, we create a variable, setting the data type from a string variable, which could have been returned by the DATATYPE keyword to a CDF\_VARINQ call:

```

; create a file in IDL's current directory
id = CDF_CREATE('temp.cdf')

VARTYPE = 'CDF_FLOAT'

; Use the _EXTRA keyword and the CREATE_STRUCT function to
; make the appropriate keyword.

VarId = CDF_VARCREATE(Id, 'Pressure', [1,1], $
    NUMELEM=2, _EXTRA=CREATE_STRUCT(VARTYPE,1))
CDF_CLOSE, id ; Close the CDF file.

```

## Version History

Pre 4.0	Introduced
6.3	Add support for the CDF_EPOCH16 variable type

# CDF\_VARDELETE

The CDF\_VARDELETE procedure deletes a variable from a SINGLE\_FILE CDF file. Note that the variable's entries are also deleted, and that the variables that numerically follow the deleted variable within the CDF file are automatically renumbered. CDF rVariables and zVariables are counted separately within CDF files. Attempting to delete a variable from a MULTI\_FILE format CDF file will result in a warning message.

## Syntax

```
CDF_VARDELETE, Id, Variable [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID of the file containing the Variable to be deleted, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Variable

A string containing the name of the variable to be deleted OR the variable number to be deleted. Variable numbers are 0-based in IDL. zVariables and rVariables are counted separately in CDF files.

## Keywords

### ZVARIABLE

Set this keyword if the Variable is a zVariable and was passed by number. The default is to assume that Variable is an rVariable.

## Examples

```
cid = CDF_CREATE('DEMOvardelete',/SINGLE_FILE)

; Create 3 zVariables and 1 rVariable:
var1_id = CDF_VARCREATE(cid, 'rVAR1', /CDF_FLOAT)
var2_id = CDF_VARCREATE(cid, 'zVAR1', /CDF_INT4, /REC_NOVARY, $
    /ZVARIABLE)
var3_id = CDF_VARCREATE(cid, 'zVAR2', /CDF_CHAR, [2,10], $
    NUMELEM=10, DIM=[5,5])
```

```

var4_id = CDF_VARCREATE(cid, 'zVAR3' ,/CDF_REAL8, /ZVARIABLE)

; Check the number of variables:
info = CDF_INQUIRE(cid)
HELP, info.nzvars, info.nvars

; Delete the first and third zvariables:
CDF_VARDELETE, cid, 'zVAR1', /ZVARIABLE
CDF_VARDELETE, cid, 1, /ZVARIABLE

; CAUTION: Remember the variable numbers are zero-based
; and are automatically renumbered.

info = CDF_INQUIRE(cid)
HELP, info.nzvars, info.nvars
varinfo = CDF_VARINFO(cid, 0, /ZVARIABLE)
; check on zVAR2
HELP, varinfo, /STRUCTURE

CDF_DELETE, cid

```

## IDL Output

```

<Expression>    LONG      =          3
<Expression>    LONG      =          1

<Expression>    LONG      =          1
<Expression>    LONG      =          1

** Structure <400a3b40>, 8 tags, length=48, refs=1:
  IS_ZVAR        INT          1
  NAME           STRING      'zVAR2'
  DATATYPE       STRING      'CDF_CHAR'
  NUMELEM        LONG         10
  RECVAR         STRING      'VARY'
  DIMVAR         BYTE        Array(2)
  ALLOCATERECS   LONG        Array(2)
  DIM            LONG        Array(1)

```

## Version History

4.0.1b	Introduced
--------	------------

## See Also

[CDF\\_ATTDELETE](#), [CDF\\_CONTROL](#), [CDF\\_VARCREATE](#), [CDF\\_VARINQ](#)

# CDF\_VARGET

The CDF\_VARGET procedure reads multiple values from a Common Data Format file variable. By default, all elements of a record are read. If INTERVAL and/or OFFSET are specified but no COUNT is specified, CDF\_VARGET attempts to get as many elements of each record as possible.

## Syntax

```
CDF_VARGET, Id, Variable, Value [, COUNT=vector] [, INTERVAL=vector]  
  [, OFFSET=vector] [, REC_COUNT=records] [, REC_INTERVAL=value]  
  [, REC_START=record] [, /STRING{data in CDF file must be type CDF_CHAR  
  or CDF_UCHAR}] [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE

### Variable

A string containing the name of the variable *or* the variable number being read.

### Value

A named variable in which the values of the variable are returned.

## Keywords

### COUNT

An optional vector containing the counts to be used in reading Value. The default is to read all elements in each record, taking into account INTERVAL and OFFSET.

### INTERVAL

A vector specifying the interval between values in each dimension. The default value is 1 for each dimension.

## OFFSET

A vector specifying the array indices within the specified record(s) at which to begin writing. OFFSET is a 1-dimensional array containing one element per CDF dimension. The default value is zero for each dimension.

## REC\_COUNT

The number of records to read. The default is 1.

## REC\_INTERVAL

The interval between records when reading multiple records. The default value is 1.

## REC\_START

The record number at which to start reading. The default is 0.

## STRING

Set this keyword to return CDF\_CHAR and CDF\_UCHAR data from the CDF file into *Value* as string data rather than byte data. This keyword is ignored if the data in the CDF file is not of type CDF\_CHAR or CDF\_UCHAR.

## ZVARIABLE

If *Variable* is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that *Variable* is an rVariable ID.

## Examples

```

; Create a CDF file, and make a few variables:
id = CDF_CREATE('DEMOfargets')
vid1 = CDF_VARCREATE(id, 'VAR1', /CDF_CHAR, NUMELEM=15)
vid2=CDF_VARCREATE(id, 'VAR2', /CDF_UCHAR, NUMELEM=10)
CDF_VARPUT, id, vid1, BINDGEN(15, 2)+55, COUNT=2
CDF_VARPUT, id, vid2, ['IDLandCDF ', 'AreWayCool']

; Retrieve the CDF_CHAR array as byte data:
CDF_VARGET, id, 'VAR1', var1_byte, REC_COUNT=2
HELP, var1_byte

;Retrieve the CDF_CHAR array as string data:
CDF_VARGET, id, 'VAR1', var1_string, REC_COUNT=2, /STRING
HELP, var1_string

```



```

; For demonstration purposes, use the 'VAR2' variable number to
; access 'VAR2' for the duration of this example:

var2num = CDF_VARNUM(id, 'VAR2')
HELP, var2num

; Rename 'VAR2' to 'VAR_STRING_2':
CDF_VARRENAME, id, var2num, 'VAR_STRING_2'

; Examine VAR_STRING_2 with CDF_VARINQ:
VAR2_INQ = CDF_VARINQ(id, var2num)
HELP, VAR2_INQ, /STRUCTURE

; Read in and print out VAR_STRING_2:
CDF_VARGET, id, var2num, var2_string, /STRING, REC_COUNT=2
PRINT, var2_string

CDF_DELETE, id ; Delete the CDF file

```

## IDL Output

```
% CDF_VARGET: Warning: converting data to unsigned bytes
```

This warning message indicates that the data was stored in the CDF file with type CDF\_CHAR (signed 1-byte characters), but was retrieved by IDL with type BYTE (unsigned byte). To turn this warning message off, set !QUIET=1.

```

VAR1_BYTE      BYTE      = Array(15,  2)

VAR1_STRING    STRING    = Array(2)

VAR2NUM        LONG      =          1

** Structure <400b1600>, 6 tags, length=33, refs=1:
  IS_ZVAR      INT        0
  NAME         STRING     'VAR_STRING_2'
  DATATYPE     STRING     'CDF_UCHAR'
  NUMELEM      LONG       10
  RECVAR       STRING     'VARY'
  DIMVAR       BYTE       0

IDLandCDF  AreWayCool

```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_VARGET1

The CDF\_VARGET1 procedure reads one value from a CDF file variable.

## Syntax

```
CDF_VARGET1, Id, Variable, Value [, OFFSET=vector] [, REC_START=record]  
  [, /STRING{data in CDF file must be type CDF_CHAR or CDF_UCHAR}]  
  [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Variable

A string containing the name or an integer containing the index of the variable being inquired.

### Value

A named variable in which the value of the variable is returned.

## Keywords

### OFFSET

A vector specifying the array indices within the specified record(s) at which to begin reading. OFFSET is a 1-dimensional array containing one element per CDF dimension. The default value is 0 for each dimension.

### REC\_START

The record number at which to start reading. The default is 0.

### STRING

Set this keyword to return CDF\_CHAR and CDF\_UCHAR data from the CDF file into Value as string data rather than byte data. This keyword is ignored if the data in the CDF file is not of type CDF\_CHAR or CDF\_UCHAR.

## ZVARIABLE

If Variable is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that Variable is an rVariable ID.

## Examples

See the example for “[CDF\\_VARCREATE](#)” on page 96.

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_VARINQ

The CDF\_VARINQ function returns a structure containing information about the specified variable in a Common Data Format file.

## Syntax

*Result* = CDF\_VARINQ(*Id*, *Variable* [, /ZVARIABLE] )

## Return Value

The returned structure has the form:

```
{ IS_ZVAR:0, NAME:"", DATATYPE:"", NUMELEM:0L, $
  RECVAR:"", DIMVAR:BYTARR(...) [, DIM:LONARR(...)] }
```

### Note

The DIM field is included in the structure only if IS\_ZVAR is one.

## Explanation of the Structure Tags

The following table provides structure tag information.

Tag	Description
IS_ZVAR	This field will contain a 1 if the variable is a zVariable or a 0 if it is an rVariable.
NAME	The name of the variable.
DATATYPE	A string describing the data type of the variable. The string has the form 'CDF_XXX' where XXX is FLOAT, DOUBLE, EPOCH, UCHAR, etc.
NUMELEM	The number of elements of the data type at each variable value. This is always 1 except in the case of string type variables (CDF_CHAR, CDF_UCHAR).
RECVAR	A string describing the record variance of the variable. This is either the string 'VARY' or 'NOVARY'.

Table 2-2: CDF\_VARINQ Structure Tags

Tag	Description
DIMVAR	An array of bytes. The value of each element is zero if there is no variance with that dimension and one if there is variance. For zero-dimensional CDFs, DIMVAR will have one element whose value is zero.
DIM	An array of longs. The value of each element corresponds to the dimension of the variable. This field is only included in the structure if the variable is a zVariable.

Table 2-2: CDF\_VARINQ Structure Tags (Continued)

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Variable

A string containing the name or an integer containing the index of the variable being inquired.

## Keywords

### ZVARIABLE

If Variable is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that Variable is an rVariable ID.

## Examples

See the example for “CDF\_VARGET” on page 103.

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_VARNUM

The CDF\_VARNUM function returns the variable number associated with a given variable name in a Common Data Format file.

## Syntax

$$Result = CDF\_VARNUM( Id, VarName [, IsZVar] )$$

## Return Value

Returns the variable number of a specified variable name. If the specified variable cannot be found in the CDF file, CDF\_VARNUM returns the scalar -1.

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### VarName

A string containing the name of the variable.

### IsZVar

A named variable into which CDF\_VARNUM will place a 1 to indicate that the referenced variable is a zVariable or a 0 to indicate that it is an rVariable.

## Keywords

None

## Examples

See the example for “CDF\_VARGET” on page 103.

## Version History

Pre 4.0	Introduced
---------	------------



# CDF\_VARPUT

The CDF\_VARPUT procedure writes a value to a variable in a Common Data Format file. This function provides equivalent functionality to the C routines CDFvarPut and CDFvarHyperPut.

## Syntax

```
CDF_VARPUT, Id, Variable, Value [, COUNT=vector] [, INTERVAL=vector]  
  [, OFFSET=vector] [, REC_INTERVAL=value] [, REC_START=record]  
  [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### Variable

A string containing the name or number of the variable being written.

### Value

The value to write. If the value has 1 more dimension than the CDF, multiple records will be written.

## Keywords

### COUNT

An optional vector containing the counts to be used in writing *Value*. Note that counts do not have to match the dimensions of *Value*. The default count is to use the dimensions of *Value*.

### INTERVAL

A vector specifying the interval between values in each dimension. The default value is 1 in each dimension.

## OFFSET

A vector specifying the array indices within the specified record(s) at which to begin writing. OFFSET is a 1-dimensional array containing one element per CDF dimension. The default value is zero in each dimension.

## REC\_INTERVAL

The interval between records being written when writing multiple records. The default value is 1.

## REC\_START

The record number at which to start writing. The default is 0.

## ZVARIABLE

If *Variable* is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that *Variable* is an rVariable ID.

## Examples

```
id= CDF_CREATE('mycdf', [5,10], /NETWORK_ENCODING, /ROW_MAJOR)
varid= CDF_VARCREATE(id, 'v1', [1,1], /CDF_FLOAT, /REC_VARY)
```

To write the value 42.0 into record 12, third row, fourth column:

```
CDF_VARPUT, id, varid, 42, REC_START=12, OFFSET=[2,3]
```

To write 3 records, skipping every other record, starting at record 2, writing every other entry of each record. Note that in this example we write 25 values into each record written:

```
CDF_VARPUT, id, varid, FINDGEN(5,5,3), INTERVAL=[2,1], $
    REC_INTERVAL=2, REC_START=2
CDF_DELETE, id
```

## Version History

Pre 4.0	Introduced
---------	------------

# CDF\_VARRENAME

The CDF\_VARRENAME procedure renames an existing variable in a Common Data Format file.

## Syntax

```
CDF_VARRENAME, Id, OldVariable, NewName [, /ZVARIABLE]
```

## Arguments

### Id

The CDF ID, returned from a previous call to CDF\_OPEN or CDF\_CREATE.

### OldVariable

A string containing the current name of the variable *or* the variable number to be renamed.

### NewName

A string containing the new name for the variable.

## Keywords

### ZVARIABLE

If OldVariable is a variable ID (as opposed to a variable name) and the variable is a zVariable, set this flag to indicate that the variable ID is a zVariable ID. The default is to assume that OldVariable is an rVariable ID.

## Examples

See the example for “CDF\_VARGET” on page 103.

## Version History

Pre 4.0	Introduced
---------	------------





## Chapter 3

# Hierarchical Data Format - HDF5

This chapter details the interface routines for the Hierarchical Data Format version 5. The following topics are covered in this chapter:

---

<a href="#">Overview of the HDF Version 5 Format</a> ..	118	<a href="#">Example: Reading an Image</a> .....	133
<a href="#">The HDF5 Format</a> .....	119	<a href="#">Example: Reading a Subselection</a> .....	134
<a href="#">The IDL HDF5 Library</a> .....	120	<a href="#">Example: Creating a Data File</a> .....	136
<a href="#">IDL HDF5 Limitations</a> .....	122	<a href="#">Example: Reading Partial Datasets</a> .....	137
<a href="#">HDF5 Datatypes</a> .....	123	<a href="#">Alphabetical Listing of HDF5 Routines</a> ..	138

# Overview of the HDF Version 5 Format

The Hierarchical Data Format version 5 file format is designed for scientific data consisting of a hierarchy of datasets and attributes (or metadata). HDF is a product of the National Center for Supercomputing Applications (NCSA), which supplies the underlying C-language library; IDL provides access to this library via a set of procedures and functions contained in a dynamically loadable module (DLM).

This version of IDL supports HDF5 5-1.6.3. IDL's HDF5 routines all begin with the prefix "H5\_" or "H5\*\_".

For more information on HDF5 see:

<http://hdf.ncsa.uiuc.edu/HDF5/>

# The HDF5 Format

Hierarchical Data Format files are organized in a hierarchical structure. The two primary structures are:

- The HDF5 group — a grouping structure containing instances of zero or more groups or datasets, together with supporting metadata.
- The HDF5 dataset — a multidimensional array of data elements, together with supporting metadata.

HDF attributes are small named datasets that are attached to primary datasets, groups, or named datatypes.

## HDF4 versus HDF5

HDF5 was designed to address some of the limitations of the HDF4 format, in addition to providing new functionality.

The limitations of the HDF4 format included:

- A file cannot store more than 20,000 complex objects and cannot be larger than 2 gigabytes;
- The data models are inconsistent, there are too many object types, and datatypes are too restrictive;
- The C library source was old and complex, did not support parallel I/O effectively, and was not threadsafe.

The new HDF5 includes the following improvements:

- Larger files may be stored and more objects per file may be included.
- A more comprehensive data model with two basic structures: multidimensional datasets and groups.
- Simpler, better-engineered library and API, with support for parallel I/O and threads.

---

### Note

The HDF5 format is not compatible with HDF4, although a conversion routine (h4toh5) is available from NCSA (<http://hdf.ncsa.uiuc.edu/h4toh5/>).

---

# The IDL HDF5 Library

The IDL HDF5 library consists of an almost direct mapping between the HDF5 library functions and the IDL functions and procedures. The relationship between the IDL routines and the HDF5 library is described in the following subsections.

## Routine Names

The IDL routine names are typically identical to the HDF5 function names, with the exception that an underscore is added between the prefix and the actual function. For example, the C function `H5get_libversion()` is implemented by the IDL function `H5_GET_LIBVERSION`.

The IDL HDF5 library contains the following function categories:

Prefix	Category	Purpose
H5	Library	General library tasks
H5A	Attribute	Manipulate attribute datasets
H5D	Dataset	Manipulate general datasets
H5F	File	Create, open, and close files
H5G	Group	Handle groups of other groups or datasets
H5I	Identifier	Query object identifiers
H5R	Reference	Reference identifiers
H5S	Dataspace	Handle dataspace dimensions and selection
H5T	Datatype	Handle dataset element information

*Table 3-1: HDF Function Categories*

## Functions Versus Procedures

HDF5 functions that only return an error code are typically implemented as IDL procedures. An example is `H5F_CLOSE`, which takes a single file identifier number as the argument and closes the file. HDF5 functions that return values are implemented as IDL functions. An example is `H5F_OPEN`, which takes a filename as the argument and returns a file identifier number.



## Error Handling

All HDF5 functions that return an error or status code are checked for failure. If an error occurs, the HDF5 error handling code is called to retrieve the internal HDF5 error message. This error message is printed to the output window, and program execution stops.

## Dimension Order

HDF5 uses C row-major ordering instead of IDL column-major ordering. For row major, the first listed dimension varies slowest, while for column major the first listed dimension varies fastest. The IDL HDF5 library handles this difference by automatically reversing the dimensions for all functions that accept lists of dimensions.

---

**Note**

Only the order in which the dimensions are listed is affected; in both the HDF5 file and in IDL memory, the layout of the data is identical.

---

For example, an HDF5 file may be known to contain a dataset with dimensions [5][10][50], either as declared in the C code, or from the output from the `h5dump` utility. When this dataset is read into IDL, the array will have the dimensions listed as [50, 10, 5], using the output from the IDL help function.

---

**Note**

In both the C program used to create the file and in IDL memory after reading the dataset, the values with dimension 50 will be contiguous.

---

# IDL HDF5 Limitations

The IDL HDF5 library currently has the following limitations:

- Conversion cannot be forced from the HDF5 datatype to a different IDL type (such as single-precision instead of double), although data can be converted after reading from the file.
- Only the first (or top) error message from the HDF5 error stack is printed.
- Variable-length and opaque datatypes are currently ignored.
- The low-level property interface (H5P) is not exposed.

# HDF5 Datatypes

In HDF5, a *datatype* is an object that describes the storage format of the individual data points of a data set. There are two categories of datatypes; *atomic* and *compound* datatypes:

- *Atomic datatypes* cannot be decomposed into smaller units at the API level.
- *Compound datatypes* are a collection of one or more atomic types or small arrays of such types. Compound datatypes are similar to a struct in C or a common block in Fortran. See “[Compound Datatypes](#)” on page 124 for additional details.

In addition, HDF5 uses the following terms for different datatype concepts:

- A *named datatype* is a datatype that is named and stored in a file. Naming is permanent; a datatype cannot be changed after being named. Named datatypes are created from in-memory datatypes using the `H5T_COMMIT` routine.
- An *opaque datatype* is a mechanism for describing data which cannot be otherwise described by HDF5. The only properties associated with opaque types are the size in bytes and an ASCII tag string. See “[Opaque Datatypes](#)” on page 125 for additional details.
- An *enumeration datatype* is a one-to-one mapping between a set of symbols and an ordered set of integer values. The symbols are passed between IDL and the underlying HDF5 library as character strings. All the values for a particular enumeration datatype are of the same integer type. See “[Enumeration Datatypes](#)” on page 127 for additional details.
- A *variable length array* datatype is a sequence of existing datatypes (atomic, variable length, or compound) which are not fixed in length from one dataset location to another. See “[Variable Length Array Datatypes](#)” on page 129 for additional details.

## Compound Datatypes

HDF5 compound datatypes can be compared to C structures, Fortran structures, or SQL records. Compound datatypes can be nested; there is no limitation to the complexity of a compound datatype. Each member of a compound datatype must have a descriptive name, which is the key used to uniquely identify the member within the compound datatype.

Use one of the [H5T\\_COMPOUND\\_CREATE](#) or [H5T\\_IDL\\_CREATE](#) routines to create compound datatypes. Use the following routines to work with compound datatypes:

- [H5T\\_GET\\_MEMBER\\_CLASS](#)
- [H5T\\_GET\\_MEMBER\\_INDEX](#)
- [H5T\\_GET\\_MEMBER\\_NAME](#)
- [H5T\\_GET\\_MEMBER\\_OFFSET](#)
- [H5T\\_GET\\_MEMBER\\_TYPE](#)
- [H5T\\_GET\\_MEMBER\\_VALUE](#)
- [H5T\\_GET\\_NMEMBERS](#)

### Example

See [H5F\\_CREATE](#) for an extensive example using compound datatypes.

## Opaque Datatypes

An opaque datatype contains a series of bytes. It always contains a single element, regardless of the length of the series of bytes it contains.

When an IDL variable is written to a dataset or attribute defined as an opaque datatype, it is written as a string of bytes with no demarcation. When data in a opaque datatype is read into an IDL variable, it is returned as byte array. Use the `FIX` routine to convert the returned byte array to the appropriate IDL data type.

Use the `H5T_IDL_CREATE` routine with the `OPAQUE` keyword to create opaque datatypes. To create an opaque array, use an opaque datatype with the `H5T_ARRAY_CREATE` routine. A single string tag can be assigned to an opaque datatype to provide auxiliary information about what is contained therein. Create tags using the `H5T_SET_TAG` routine; retrieve tags using the `H5T_GET_TAG` routine. HDF5 limits the length of the tag to 255 characters.

### Example

The following example creates an opaque datatype and stores within it a 20-element integer array.

```

; Create a file to hold the data
file = 'h5_test.h5'
fid = H5F_CREATE(file)

; Create some data
data = INDGEN(20)

; Create an opaque datatype
dt = H5T_IDL_CREATE(data, /OPAQUE)

; Create a single element dataspace
ds = H5S_CREATE_SIMPLE(1)

; Create and write the dataset
d = H5D_CREATE(fid, 'dataset', dt, ds)
H5D_WRITE, d, data

; Close the file
H5F_CLOSE, fid

; Reopen file for reading
fid = H5F_OPEN(file)

; Read in the data
d = H5D_OPEN(fid, 'dataset')
```

```
result = H5D_READ(d)

; Close the file
H5F_CLOSE, fid

HELP, result
```

IDL prints:

```
RESULT          BYTE          = Array[40]
```

Note that the result is a 40-element byte array, since each integer requires two bytes.

## Enumeration Datatypes

An enumeration datatype consists of a set of (*Name*, *Value*) pairs, where:

- *Name* is a scalar string that is unique within the datatype (a given name string can only be associated with a single value)
- *Value* is a scalar integer that is unique within the datatype

---

### Note

Name/value pairs must be assigned to the datatype *before* it is used to create a dataset. The dataset stores the state of the datatype at the time the dataset is created; additional changes to the datatype will not be reflected in the dataset.

---

Create the enumeration datatype using the [H5T\\_ENUM\\_CREATE](#) function. Once you have created an enumeration datatype:

- use the [H5T\\_ENUM\\_INSERT](#) procedure to associate a single name/value pair with the datatype
- use the [H5T\\_ENUM\\_VALUEOF](#) function to retrieve the value associated with a single name
- use the [H5T\\_ENUM\\_NAMEOF](#) function to retrieve the name associated with a single value

These routines replicate the facilities provided by the underlying HDF5 library, which deals only with single name/value pairs. To make it easier to read and write entire enumerated lists, IDL provides two helper routines at package the name/value pairs in arrays of IDL `IDL_H5_ENUM` structures, which have the following definition:

```
{IDL_H5_ENUM, NAME:'', VALUE:0}
```

The routines are:

- [H5T\\_ENUM\\_SET\\_DATA](#) associates multiple name/value pairs with an enumeration datatype in a single operation. Data can be provided either as a string array of names and an integer array of values or as a single array of `IDL_H5_ENUM` structures.
- [H5T\\_ENUM\\_GET\\_DATA](#) retrieves multiple name/value pairs from an enumeration datatype in a single operation. Data are returned in an array of `IDL_H5_ENUM` structures.

The [H5T\\_ENUM\\_VALUES\\_TO\\_NAMES](#) function is a helper routine that lets you retrieve the names associated with an array of values in a single operation.

The following routines may also be useful when working with enumeration datatypes:

[H5T\\_GET\\_MEMBER\\_INDEX](#), [H5T\\_GET\\_MEMBER\\_NAME](#),  
[H5T\\_GET\\_MEMBER\\_VALUE](#)

## Example

The following example creates an enumeration datatype and saves it to a file. The example then reopens the file and reads the data, printing the names.

```

; Create a file to hold the data
file = 'h5_test.h5'
fid = H5F_CREATE(file)

; Create arrays to serve as name/value pairs
names = ['dog', 'pony', 'turtle', 'emu', 'wildebeest']
values = INDGEN(5)+1

; Create the enumeration datatype
dt = H5T_ENUM_CREATE()

; Associate the name/value pairs with the datatype
H5T_ENUM_SET_DATA, dt, names, values

; Create a dataspace, then create and write the dataset
ds = H5S_CREATE_SIMPLE(N_ELEMENTS(values))
d = H5D_CREATE(fid, 'dataset', dt, ds)
H5D_WRITE, d, values

; Close the file
H5F_CLOSE, fid

; Reopen file for reading
fid = H5F_OPEN(file)

; Read in the data
d = H5D_OPEN(fid, 'dataset')
dt = H5D_GET_TYPE(d)
result = H5D_READ(d)

; Close the file
H5F_CLOSE, fid

; Print the value associated with the name "pony"
PRINT, H5T_ENUM_VALUEOF(dt, 'pony')

; Print all the name strings
PRINT, H5T_ENUM_VALUES_TO_NAMES(dt, result)

```



## Variable Length Array Datatypes

HDF5 provides support for variable length arrays, but IDL itself does not. As a result, in order to store data in an HDF5 variable length array you must:

1. Create a series of vectors of data in IDL, each with a potentially different length. All vectors must be of the same data type.
2. Store a pointer to each data vector in the PDATA field of an IDL\_H5\_VLEN structure. The IDL\_H5\_VLEN structure is defined as follows:

```
{ IDL_H5_VLEN, pdata:PTR_NEW() }
```

3. Create an array of IDL\_H5\_VLEN structures that will be stored as an HDF5 variable length array.
4. The IDL\_H5\_VLEN structure is defined as follows:

```
{ IDL_H5_VLEN, pdata:PTR_NEW() }
```

5. Create a base HDF5 datatype from one of the data vectors.
6. Create an HDF5 variable length datatype from the base datatype.
7. Create an HDF5 dataspace of the appropriate size.
8. Create an HDF5 dataset.
9. Write the array of IDL\_H5\_VLEN structures to the HDF5 dataset.

---

### Note

IDL string arrays are a special case: see [“Variable Length String Arrays”](#) on page 131 for details.

---

Creating a variable length array datatype is a two-step process. First, you must create a base datatype using the H5T\_IDL\_CREATE function; all data in the variable length array must be of this datatype. Second, you create a variable length array datatype using the base datatype as an input to the [H5T\\_VLEN\\_CREATE](#) function.

---

### Note

No explicit size is provided to the H5T\_VLEN\_CREATE function; sizes are determined as needed by the data being written.

---

### Example: Writing a Variable Length Array

```
; Create a file to hold the data
file = 'h5_test.h5'
fid = H5F_CREATE(file)
```

```

; Create three vectors containing integer data
a = INDGEN(2)
b = INDGEN(3)
c = 3

; Create an array of three IDL_H5_VLEN structures
sArray = REPLICATE({IDL_H5_VLEN}, 3)

; Populate the IDL_H5_VLEN structures with pointers to
; the three data vectors
sArray[0].pdata = PTR_NEW(a)
sArray[1].pdata = PTR_NEW(b)
sArray[2].pdata = PTR_NEW(c)

; Create a datatype based on one of the data vectors
dt1 = H5T_IDL_CREATE(a)

; Create a variable length datatype based on the previously-
; created datatype
dt = H5T_VLEN_CREATE(dt1)

; Create a dataspace
ds = H5S_CREATE_SIMPLE(N_ELEMENTS(sArray))

; Create the dataset
d = H5D_CREATE(fid, 'dataset', dt, ds)

; Write the array of structures to the dataset
H5D_WRITE, d, sArray

```

## Examples: Reading a Variable Length Array

Using the `H5D_READ` function to read data written as a variable length array creates an array of `IDL_H5_VLEN` structures. The following examples show how to refer to individual data elements of various HDF5 datatypes

### Atomic HDF5 Datatypes

To read and access data stored in variable length arrays of atomic HDF5 datatypes, simply dereference the pointer stored in the `PDATA` field of the appropriate `IDL_H5_VLEN` structure. For example, to retrieve the variable `b` from the data written in the above example:

```

data = H5D_READ(d)
b = *data[1].pdata

```

## Compound HDF5 Datatypes

If you have a variable length array of compound datatypes, the tag `tag` of the  $j^{\text{th}}$  structure of the  $i^{\text{th}}$  element of the variable length array would be accessed as follows:

```
data = H5D_READ(d)
a = (*data[i].pdata)[j].tag
```

## Variable Length Arrays of Variable Length Arrays

If you have a variable length array of variable length arrays of integers, the  $k^{\text{th}}$  integer of the  $j^{\text{th}}$  element of a variable length array stored in the  $i^{\text{th}}$  element of a variable length array would be accessed as follows:

```
data = H5D_READ(d)
a = (*( *data[i].pdata)[j].pdata)[k]
```

## Compound Datatypes Containing Variable Length Arrays

If you have a compound datatype containing a variable length array, the  $k^{\text{th}}$  data element of the  $j^{\text{th}}$  variable length array in the  $i^{\text{th}}$  compound datatype would be accessed as follows:

```
data = H5D_READ(d)
a = (*data[i].vl_array[j].pdata)[k]
```

## Variable Length String Arrays

Because the data vectors referenced by the pointers stored in the `PDATA` field of the `IDL_H5_VLEN` structure must all have the same type and dimension, strings are handled as vectors of individual characters rather than as atomic units. This means that each element in a string array must be assigned to an individual `IDL_H5_VLEN` structure:

```
str = ['dog', 'dragon', 'duck']
sArray = REPLICATE({IDL_H5_VLEN}, 3)
sArray[0].pdata = ptr_new(str[0])
sArray[1].pdata = ptr_new(str[1])
sArray[2].pdata = ptr_new(str[2])
```

Use the [H5T\\_STR\\_TO\\_VLEN](#) function to assist in converting between an IDL string array and an HDF5 variable length string array. The following achieves the same result as the above five lines:

```
str = ['dog', 'dragon', 'duck']
sArray = H5T_STR_TO_VLEN(str)
```

Similarly, if you have an HDF5 variable length array containing string data, use the [H5T\\_VLEN\\_TO\\_STR](#) function to access the string data:

```
data = H5D_READ(d)
str = H5T_VLEN_TO_STR(data)
```

## Example: Reading an Image

The following example opens up the `hdf5_test.h5` file and reads in a sample image. It is assumed that the user already knows the dataset name, either from using `h5dump`, or the `H5G_GET_MEMBER_NAME` function.

```

PRO ex_read_hdf5

; Open the HDF5 file.
file = FILEPATH('hdf5_test.h5', $
    SUBDIRECTORY=['examples', 'data'])
file_id = H5F_OPEN(file)

; Open the image dataset within the file.
; This is located within the /images group.
; We could also have used H5G_OPEN to open up the group first.
dataset_id1 = H5D_OPEN(file_id, '/images/Eskimo')

; Read in the actual image data.
image = H5D_READ(dataset_id1)

; Open up the dataspace associated with the Eskimo image.
dataspace_id = H5D_GET_SPACE(dataset_id1)

; Retrieve the dimensions so we can set the window size.
dimensions = H5S_GET_SIMPLE_EXTENT_DIMS(dataspace_id)

; Now open and read the color palette associated with
; this image.
dataset_id2 = H5D_OPEN(file_id, '/images/Eskimo_palette')
palette = H5D_READ(dataset_id2)

; Close all our identifiers so we don't leak resources.
H5S_CLOSE, dataspace_id
H5D_CLOSE, dataset_id1
H5D_CLOSE, dataset_id2
H5F_CLOSE, file_id

; Display the data.
DEVICE, DECOMPOSED=0
WINDOW, XSIZE=dimensions[0], YSIZE=dimensions[1]
TVLCT, palette[0,*], palette[1,*], palette[2,*]

; Use /ORDER since the image is stored top-to-bottom.
TV, image, /ORDER

END

```

## Example: Reading a Subselection

The following example reads only a portion of the previous image, using the dataspace keywords to H5D\_READ.

```

PRO ex_read_hdf5_select

; Open the HDF5 file.
file = FILEPATH('hdf5_test.h5', $
  SUBDIRECTORY=['examples', 'data'])
file_id = H5F_OPEN(file)

; Open the image dataset within the file.
dataset_id1 = H5D_OPEN(file_id, '/images/Eskimo')

; Open up the dataspace associated with the Eskimo image.
dataspace_id = H5D_GET_SPACE(dataset_id1)

; Now choose our hyperslab. We will pick out only the central
; portion of the image.
start = [100, 100]
count = [200, 200]
; Be sure to use /RESET to turn off all other
; selected elements.
H5S_SELECT_HYPERSLAB, dataspace_id, start, count, $
  STRIDE=[2, 2], /RESET

; Create a simple dataspace to hold the result. If we
; didn't supply
; the memory dataspace, then the result would be the same size
; as the image dataspace, with zeroes everywhere except our
; hyperslab selection.
memory_space_id = H5S_CREATE_SIMPLE(count)

; Read in the actual image data.
image = H5D_READ(dataset_id1, FILE_SPACE=dataspace_id, $
  MEMORY_SPACE=memory_space_id)

; Now open and read the color palette associated with
; this image.
dataset_id2 = H5D_OPEN(file_id, '/images/Eskimo_palette')
palette = H5D_READ(dataset_id2)

; Close all our identifiers so we don't leak resources.
H5S_CLOSE, memory_space_id
H5S_CLOSE, dataspace_id
H5D_CLOSE, dataset_id1

```

```
H5D_CLOSE, dataset_id2
H5F_CLOSE, file_id

; Display the data.
DEVICE, DECOMPOSED=0
WINDOW, XSIZE=count[0], YSIZE=count[1]
TVLCT, palette[0,*], palette[1,*], palette[2,*]

; We need to use /ORDER since the image is stored
; top-to-bottom.
TV, image, /ORDER

END
```

## Example: Creating a Data File

The following example creates a simple HDF5 data file with a single sample data set. The file is created in the current working directory.

```
PRO ex_create_hdf5

    file = filepath('hdf5_out.h5')
    fid = H5F_CREATE(file)

    ;; create data
    data = hanning(100,150)

    ;; get data type and space, needed to create the dataset
    datatype_id = H5T_IDL_CREATE(data)
    dataspace_id = H5S_CREATE_SIMPLE(size(data, /DIMENSIONS))

    ;; create dataset in the output file
    dataset_id = H5D_CREATE(fid,$
        'Sample data',datatype_id,dataspace_id)
    ;; write data to dataset
    H5D_WRITE,dataset_id,data

    ;; close all open identifiers
    H5D_CLOSE,dataset_id
    H5S_CLOSE,dataspace_id
    H5T_CLOSE,datatype_id
    H5F_CLOSE,fid

END
```



## Example: Reading Partial Datasets

To read a portion of a compound dataset or attribute, create a datatype that matches only the elements you wish to retrieve, and specify that datatype as the second argument to the `H5D_READ` function. The following example creates a simple HDF5 data file in the current directory, then opens the file and reads a portion of the data.

```
; Create sample data in an array of structures with two fields
struct = {time:0.0, data:intarr(40)}
r = REPLICATE(struct,20)
r.time = RANDOMU(seed,20)*1000
r.data = INDGEN(40,20)

; Create a file
file = 'h5_test.h5'
fid = H5F_CREATE(file)
; Create a datatype based on a single element of the array
dt = H5T_IDL_CREATE(struct)
; Create a 20 element dataspace
ds = H5S_CREATE_SIMPLE(N_ELEMENTS(r))
; Create and write the dataset
d = H5D_CREATE(fid, 'dataset', dt, ds)
H5D_WRITE, d, r
; Close the file
H5F_CLOSE, fid

; Open the file for reading
fid = H5F_OPEN(file)
; Open the dataset
d = H5D_OPEN(fid, 'dataset')
; Define the data we want to read from the dataset
struct = {data:intarr(40)}
; Create datatype denoting the portion to be read
dt = H5T_IDL_CREATE(struct)
; Read only the data that matches our datatype. The
; returned value will be a 20 element structure with only
; one tag, 'DATA'. Each element of which will be a [40]
; element integer array
result = H5D_READ(d, dt)
H5F_CLOSE, fid
```

# Alphabetical Listing of HDF5 Routines

H5\_CLOSE  
H5\_CREATE  
H5\_GET\_LIBVERSION  
H5\_OPEN  
H5\_PARSE  
H5A\_CLOSE  
H5A\_CREATE  
H5A\_DELETE  
H5A\_GET\_NAME  
H5A\_GET\_NUM\_ATTRS  
H5A\_GET\_SPACE  
H5A\_GET\_TYPE  
H5A\_OPEN\_IDX  
H5A\_OPEN\_NAME  
H5A\_READ  
H5A\_WRITE  
H5D\_CLOSE  
H5D\_CREATE  
H5D\_EXTEND  
H5D\_GET\_SPACE  
H5D\_GET\_STORAGE\_SIZE  
H5D\_GET\_TYPE  
H5D\_OPEN  
H5D\_READ  
H5D\_WRITE  
H5F\_CLOSE

H5F\_CREATE  
H5F\_IS\_HDF5  
H5F\_OPEN  
H5G\_CLOSE  
H5G\_CREATE  
H5G\_GET\_COMMENT  
H5G\_GET\_LINKVAL  
H5G\_GET\_MEMBER\_NAME  
H5G\_GET\_NMEMBERS  
H5G\_GET\_NUM\_OBJS  
H5G\_GET\_OBJ\_NAME\_BY\_IDX  
H5G\_GET\_OBJINFO  
H5G\_LINK  
H5G\_MOVE  
H5G\_OPEN  
H5G\_SET\_COMMENT  
H5G\_UNLINK  
H5I\_GET\_FILE\_ID  
H5I\_GET\_TYPE  
H5R\_CREATE  
H5R\_DEREFERENCE  
H5R\_GET\_OBJECT\_TYPE  
H5R\_GET\_REGION  
H5S\_CLOSE  
H5S\_COPY  
H5S\_CREATE\_SCALAR  
H5S\_CREATE\_SIMPLE  
H5S\_GET\_SELECT\_BOUNDS

H5S\_GET\_SELECT\_ELEM\_NPOINTS  
H5S\_GET\_SELECT\_ELEM\_POINTLIST  
H5S\_GET\_SELECT\_HYPER\_BLOCKLIST  
H5S\_GET\_SELECT\_HYPER\_NBLOCKS  
H5S\_GET\_SELECT\_NPOINTS  
H5S\_GET\_SIMPLE\_EXTENT\_DIMS  
H5S\_GET\_SIMPLE\_EXTENT\_NDIMS  
H5S\_GET\_SIMPLE\_EXTENT\_NPOINTS  
H5S\_GET\_SIMPLE\_EXTENT\_TYPE  
H5S\_IS\_SIMPLE  
H5S\_OFFSET\_SIMPLE  
H5S\_SELECT\_ALL  
H5S\_SELECT\_ELEMENTS  
H5S\_SELECT\_HYPERSLAB  
H5S\_SELECT\_NONE  
H5S\_SELECT\_VALID  
H5S\_SET\_EXTENT\_NONE  
H5S\_SET\_EXTENT\_SIMPLE  
H5T\_ARRAY\_CREATE  
H5T\_CLOSE  
H5T\_COMMIT  
H5T\_COMMITTED  
H5T\_COMPOUND\_CREATE  
H5T\_COPY  
H5T\_ENUM\_CREATE  
H5T\_ENUM\_GET\_DATA  
H5T\_ENUM\_INSERT  
H5T\_ENUM\_NAMEOF

H5T\_ENUM\_SET\_DATA  
H5T\_ENUM\_VALUEOF  
H5T\_ENUM\_VALUES\_TO\_NAMES  
H5T\_EQUAL  
H5T\_GET\_ARRAY\_DIMS  
H5T\_GET\_ARRAY\_NDIMS  
H5T\_GET\_CLASS  
H5T\_GET\_CSET  
H5T\_GET\_EBIAS  
H5T\_GET\_FIELDS  
H5T\_GET\_INPAD  
H5T\_GET\_MEMBER\_CLASS  
H5T\_GET\_MEMBER\_INDEX  
H5T\_GET\_MEMBER\_NAME  
H5T\_GET\_MEMBER\_OFFSET  
H5T\_GET\_MEMBER\_TYPE  
H5T\_GET\_MEMBER\_VALUE  
H5T\_GET\_NMEMBERS  
H5T\_GET\_NORM  
H5T\_GET\_OFFSET  
H5T\_GET\_ORDER  
H5T\_GET\_PAD  
H5T\_GET\_PRECISION  
H5T\_GET\_SIGN  
H5T\_GET\_SIZE  
H5T\_GET\_STRPAD  
H5T\_GET\_SUPER  
H5T\_GET\_TAG

H5T\_IDL\_CREATE  
H5T\_IDLTYPE  
H5T\_INSERT  
H5T\_MEMTYPE  
H5T\_OPEN  
H5T\_REFERENCE\_CREATE  
H5T\_SET\_TAG  
H5T\_STR\_TO\_VLEN  
H5T\_VLEN\_CREATE  
H5T\_VLEN\_TO\_STR

# H5\_CLOSE

The H5\_CLOSE procedure flushes all data to disk, closes file identifiers, and cleans up memory. This routine closes IDL's link to its HDF5 libraries. This procedure is used automatically by IDL when RESET\_SESSION is issued, but it may also be called if the user desires to free all HDF5 resources.

## Syntax

H5\_CLOSE

## Arguments

None

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5\\_OPEN](#)

# H5\_CREATE

The H5\_CREATE function creates and closes a new HDF5 file. This is a simplified routine that encapsulates some of the routines listed in the following sections. Dataspaces are all defined as the full extent of the data, and datatypes are created automatically based on the type of the data.

There are two primary scenarios for the use of H5\_CREATE. The first is a new HDF5 file being created from structures created in IDL. The second is an HDF5 file being read using H5\_PARSE modifications that are made to the structure with the resulting structure being written to a new file.

---

**Note**

Passing the output structure of H5\_PARSE to H5\_CREATE may not always completely reproduce the original file. Types of things that are not handled by these routines include: references, user-defined datatypes, and the order of items in the file. Additionally, dataset chunking is not supported and thus operations that require chunking are also not supported, for example: dataset extensibility and compression.

---

## Syntax

H5\_CREATE, *Filename*, *Structure*

## Arguments

### Filename

The full path name of the file to create. If the file exists it will be overwritten.

### Structure

An IDL structure variable (such as one that could be from H5\_PARSE) that conforms to the following:



To create an HDF5 Group the following tags can be used:

Field	Description
_NAME	String: Object name
_TYPE (required)	String: "GROUP" (case insensitive)
_COMMENT	String: Any user defined string
STRUCTURES	Any number of additional structures describing datasets, attributes, groups, or links contained with this group

*Table 3-2: H5\_CREATE Group Structure Tags*

---

**Note**

To create a top level group in the file the \_NAME field must be defined as the single character /, a null string, or left undefined, otherwise a group underneath the top level group will be created.

---

To create an HDF5 Dataset the following tags can be used:

Field	Description
_NAME	String: Object name
_TYPE (required)	String: "DATASET" (case insensitive)
_DATA (required)	Any IDL variable (except HDF5 references) accepted by H5D_WRITE
STRUCTURES	Any number of additional structures describing attributes contained with this dataset

*Table 3-3: H5\_CREATE Dataset Structure Tags*

To create an HDF5 Datatype the following tags can be used:

Field	Description
_NAME	String: Object name
_TYPE (required)	String: "DATATYPE" (case insensitive)
_DATA (required)	Any IDL variable (except HDF5 references)
STRUCTURE	Any number of additional structures describing attributes contained within this datatype or describing the individual elements of a compound datatype.

*Table 3-4: H5\_CREATE Datatype Structure Tags*

---

**Note**

When creating a DATATYPE structure the \_DATA tag is required. However, the structure returned from H5\_PARSE can also be used and a proper datatype will be created without the \_DATA tag as long as the \_DATATYPE, \_STORAGESIZE, and \_SIGN tags returned are intact. If a compound datatype is being created, and the \_DATA tag is not present, the additional structures define the fields of the datatype and the \_STORAGESIZE and \_SIGN tags are ignored.

---

To create an HDF5 Attribute the following tags can be used:

Field	Description
_NAME	String: Object name
_TYPE (required)	String: "ATTRIBUTE" (case insensitive)
_DATA (required)	Any IDL variable (except HDF5 references) accepted by H5A_WRITE

*Table 3-5: H5\_CREATE Attribute Structure Tags*

---

**Note**

Note: The ATTRIBUTE structure must be contained within a GROUP or DATASET structure, it cannot be a top level structure.

---

To create an HDF5 Link the following tags can be used:

Field	Description
<code>_NAME</code>	String: Object name
<code>_TYPE</code> (required)	String: "LINK" (case insensitive)
<code>_DATA</code> (required)	(required)String: The name (with path information) of the object to which the link will point
<code>_LINK_TYPE</code>	String: "SOFT" or "HARD" (case insensitive). If not supplied a soft link is created by default

Table 3-6: *H5\_CREATE Link Structure Tags*

#### Note

The `_DATA` field must contain the full path information, from the top level group, to the object to which the link will point while `_NAME` contains the name that will appear in the group in which the link structure exists. For example:

```
{_NAME : "Link1", _TYPE : "LINK", _DATA : "/Group1/MyDataset" }
```

#### Note

If the `_NAME` field is not supplied then the name of the structure tag will be used. Additional tags may exist in the structure(s) but will be ignored.

## Keywords

None

## Examples

As mentioned, there are two primary use cases for `H5_CREATE`. These are shown in the following example cases.

In the first case, a new HDF5 file is created from structures created in IDL. For example: to create an HDF5 file containing a single data set with a palette attached as an attribute the following code could be used:

```
grey_scale = byte(bindgen(256)##(bytarr(3)+1b))
```

```
palette = {_TYPE:'Attribute', _DATA:grey_scale}
dataset = {_NAME:'Hanning', _TYPE:'Dataset', $
           _DATA:hanning(100,200), PALETTE:palette}
H5_CREATE, 'myfile.h5', dataset
```

In the second case an HDF5 file is read using `H5_PARSE`, modifications are made to the structure and the resulting structure is written to a new file. For example, to change the palette in the example file created above so that the colors are reversed:

```
result = H5_PARSE('myfile.h5', /READ_DATA)
newpalette = reverse(result.hanning.palette._data, 2)
result.hanning.palette._data = newpalette
H5_CREATE, 'myNEWfile.h5', result
```

## Version History

6.2	Introduced
-----	------------

## See Also

[H5\\_PARSE](#), [H5A\\_WRITE](#), [H5D\\_WRITE](#)

# H5\_GET\_LIBVERSION

The H5\_GET\_LIBVERSION function returns the current version of the HDF5 library used by IDL.

## Syntax

```
Result = H5_GET_LIBVERSION()
```

## Return Value

Returns a string in the form of '*maj.min.rel*', where *maj* is the major number, *min* is the minor number, and *rel* is the release number. An example would be '1.4.3', representing HDF5 version 1.4.3.

## Arguments

None

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5\\_OPEN](#)

# H5\_OPEN

The H5\_OPEN procedure initializes IDL's HDF5 library. This procedure is issued automatically by IDL when one of IDL's HDF5 routines is used.

---

**Note**

This routine is provided for diagnostic purposes only. You do not need to use this routine while working with IDL's HDF5 routines.

---

## Syntax

H5\_OPEN

## Arguments

None

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5\\_CLOSE](#), [H5\\_GET\\_LIBVERSION](#)

## H5\_PARSE

The `H5_PARSE` function recursively descends through an HDF5 file or group and creates an IDL structure containing object information and data.

---

**Note**

This function is not part of the standard HDF5 interface, but is provided as a programming convenience.

Two structure fields were added in IDL 6.1. If an `H5_PARSE` structure from IDL 6.0 is restored the `/RELAXED_STRUCTURE_ASSIGNMENT` keyword should be used to prevent backward incompatibility.

---

### Syntax

*Result* = `H5_PARSE (File [, /READ_DATA])`

or

*Result* = `H5_PARSE (Loc_id, Name [, FILE=string] [, PATH=string]  
[, /READ_DATA] [, /SHOW_HARDLINKS])`

### Return Value

The *Result* is an IDL structure containing the parsed file or group. The fields within each structure in *Result* depend upon the object type.

### Structure Fields Common to All Object Types

Field	Description
_NAME	Object name, or the filename if at the top level
_ICONTYPE	Name of associated icon, used by H5_BROWSER
_TYPE	Object type, such as GROUP, DATASET, DATATYPE, ATTRIBUTE, or LINK

*Table 3-7: Structure Fields Common to All Object Types*

### Additional Fields for Groups, Datasets, and Named Datatypes

Field	Description
_FILE	The filename to which the object belongs
_PATH	Full path to the group, dataset, or datatype within the file

*Table 3-8: Additional Fields for Groups, Datasets, and Named Datatypes*

### Additional Fields for Groups

Field	Description
_COMMENT	Comment string

*Table 3-9: Additional Fields for Groups*

### Additional Fields for Datasets, Attributes, and Named Datatypes

Field	Description
_DATATYPE	Datatype class, such as H5T_INTEGER
_STORAGESIZE	Size of each value in bytes

*Table 3-10: Additional Fields for Datasets, Attributes, and Named Datatypes*



Field	Description
_PRECISION	Precision of each value in bits
_SIGN	For integers, either 'signed' or 'unsigned'; otherwise a null string

*Table 3-10: Additional Fields for Datasets, Attributes, and Named Datatypes (Continued)*

### Additional Fields for Datasets and Attributes

Field	Description
_DATA	Data values stored in the object
_NDIMENSIONS	Number of dimensions in the dataspace
_DIMENSIONS	List of dataspace dimensions
_NELEMENTS	Total number of elements in the dataspace
_HARDLINK	Full path to the object being linked to. If this is not a null string then the current object is actually a hard link to the object denoted by this string.

*Table 3-11: Additional Fields for Datasets and Attributes*

### Additional Fields for Links

Field	Description
_LINKTYPE	If the SHOW_HARDLINKS keyword is set then this field will be added to links and will contain the value 'HARD'. Soft links will not have this field added.

*Table 3-12: Additional Fields Links*

Groups, datasets, datatypes, and attributes will be stored as substructures within *Result*. The tag names for these substructures are constructed from the actual object

name by converting all non-alphanumeric characters to underscores, and converting all characters to uppercase. If a tag name already exists (for example a datatype and an attribute have the same name) then an appropriate suffix is appended on to the end of the tag name, such as "\_ATTR" for attribute, and so on.

If a tag name already exists within the same dataset then the suffix that is appended on to the end of the tag name will consist of \_X where X starts with 1 and increments as needed.

## Arguments

### File

A string giving the name of the file to parse.

### Loc\_id

An integer giving the file or group identifier to access.

### Name

A string giving the name of the group, dataset, or datatype within *Loc\_id* to parse.

## Keywords

### FILE

Set this optional keyword to a string giving the filename associated with the *Loc\_id*. This keyword is used for filling in the `_FILE` field within the returned structure, and is not required. The `FILE` keyword is ignored if the *File* argument is provided.

### PATH

Set this optional keyword to a string giving the full path associated with the *Loc\_id*. This keyword is used for filling in the `_PATH` field within the returned structure, and is not required. The `PATH` keyword is ignored if the *File* argument is provided.

### READ\_DATA

If this keyword is set, then all data from datasets is read in and stored in the returned structure. If `READ_DATA` is not provided then the `_DATA` field for datasets will be set to the string '<unread>'.

**Note**


---

For attribute objects all data is automatically read and stored in the structure.

---

**SHOW\_HARDLINKS**

If this keyword is set, then hardlinks will appear as a LINK structure. The default is to treat hardlinks as copies of the object pointed to.

**Note**


---

Because there is no distinguishable difference between a hard link and the object to which the link points, the first object encountered in the file is taken to be the object and any subsequent apparent copies of the object are taken to be links. This may be different than the actual order in the file.

---

**Example**

The following example shows how to parse a file, and then prints out the parsed structure.

```
File = FILEPATH('hdf5_test.h5', SUBDIR=['examples','data'])
Result = H5_PARSE(File)
help, Result, /STRUCTURE
```

When the above commands are entered, IDL prints:

```
** Structure <5f24468>, 13 tags, length=6872, data length=6664,
refs=1:
  _NAME STRING      'D:\RSI\idl63\examples\data\hdf5_test.h5'
  _ICONTYPE         STRING      'hdf'
  _TYPE            STRING      'GROUP'
  _FILE            STRING      'D:\RSI\idl63\examples\data\hdf5_test.h5'
  _PATH            STRING      '/'
  _COMMENT         STRING      ''
  _2D_INT_ARRAY    STRUCT      -> <Anonymous> Array[1]
  A_NOTE           STRUCT      -> <Anonymous> Array[1]
  SL_TO_3D_INT_ARRAY
  STRUCT          -> <Anonymous> Array[1]
  ARRAYS           STRUCT      -> <Anonymous> Array[1]
  DATATYPES       STRUCT      -> <Anonymous> Array[1]
  IMAGES          STRUCT      -> <Anonymous> Array[1]
  LINKS           STRUCT      -> <Anonymous> Array[1]
```

Now print out the structure of a dataset within the “Images” group:

```
help, Result.images.eskimo, /STRUCTURE
```

IDL prints:

```

** Structure <16f1ca0>, 20 tags, length=840, data length=802,
refs=2:
  _NAME           STRING      'Eskimo'
  _ICONTYPE       STRING      'binary'
  _TYPE           STRING      'DATASET'
  _FILE           STRING
'D:\RSI\debug\examples\data\hdf5_test.h5'
  _PATH           STRING      '/images'
  _DATA           STRING      '<unread>'
  _NDIMENSIONS    LONG        2
  _DIMENSIONS     ULONG64     Array[2]
  _NELEMENTS      ULONG64     389400
  _DATATYPE       STRING      'H5T_INTEGER'
  _STORAGESIZE    ULONG        1
  _PRECISION      LONG        8
  _SIGN           STRING      'unsigned'
  CLASS           STRUCT      -> <Anonymous> Array[1]
  IMAGE_VERSION   STRUCT      -> <Anonymous> Array[1]
  IMAGE_SUBCLASS  STRUCT      -> <Anonymous> Array[1]
  IMAGE_COLORMODEL
                    STRUCT      -> <Anonymous> Array[1]
  IMAGE_MINMAXRANGE
                    STRUCT      -> <Anonymous> Array[1]
  IMAGE_TRANSPARENCY
                    STRUCT      -> <Anonymous> Array[1]
  PALETTE         STRUCT      -> <Anonymous> Array[1]

```

## Version History

5.6	Introduced
6.2	Added <code>_HARDLINK</code> and <code>_LINKTYPE</code> structure fields.

## See Also

[H5\\_BROWSER](#)

# H5A\_CLOSE

The H5A\_CLOSE procedure closes the specified attribute and releases resources used by it. After this routine is used, the attribute's identifier is no longer available until the H5A\_OPEN routines are used again to specify that attribute. Further use of the attribute identifier is illegal.

## Syntax

H5A\_CLOSE, *Attribute\_id*

## Arguments

### Attribute\_id

An integer representing the attribute's identifier to be closed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_OPEN\\_NAME](#), [H5A\\_OPEN\\_IDX](#)

# H5A\_CREATE

The H5A\_CREATE function creates a dataset as an attribute of another group or dataset.

---

**Note**

Attributes are intended to be small objects with a maximum size of 16 kilobytes, data sizes greater than this limit will cause the attribute creation to fail. A large dataset intended as meta data for another dataset can be stored as an additional dataset. An attribute can then be attached to the original dataset as an object reference pointer to the desired supplemental dataset.

---

## Syntax

*Result* = H5A\_CREATE(*Loc\_id*, *Name*, *Datatype\_id*, *Dataspace\_id*)

## Return Value

The *Result* gives the attribute identifier number. This identifier should be released with the H5A\_CLOSE procedure.

## Arguments

### Loc\_id

An integer giving the identifier of the group, dataset, or named datatype to which the attribute will be attached

### Name

A string giving the name of the attribute to create.

### Datatype\_id

An integer giving the datatype identifier of the new attribute.

### Dataspace\_id

An integer giving the dataspace identifier of the new attribute.

## Keywords

None

## Example

See the example under [H5\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5A\\_CLOSE](#), [H5S\\_CREATE\\_SIMPLE](#), [H5T\\_IDL\\_CREATE](#)

# H5A\_DELETE

The H5A\_DELETE procedure removes the attribute specified by its name from a dataset, group, or named datatype.

**Note**

This function requires that all attributes be closed on the specified object and will close any attributes currently open.

## Syntax

H5A\_DELETE, *Loc\_id*, *Name*

## Arguments

**Loc\_id**

An integer giving the identifier of the group, dataset, or named datatype from which the attribute will be deleted.

**Name**

A string giving the name of the attribute to delete.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5A\\_CREATE](#)



# H5A\_GET\_NAME

The H5A\_GET\_NAME function retrieves an attribute name given the attribute identifier number.

## Syntax

```
Result = H5A_GET_NAME(Attribute_id)
```

## Return Value

Returns a string containing the attribute name.

## Arguments

### Attribute\_id

An integer representing the attribute's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_GET\\_SPACE](#), [H5A\\_GET\\_TYPE](#)

# H5A\_GET\_NUM\_ATTRS

The H5A\_GET\_NUM\_ATTRS function returns the number of attributes attached to a group, dataset, or a named datatype.

## Syntax

*Result* = H5A\_GET\_NUM\_ATTRS(*Loc\_id*)

## Return Value

Returns the number of attributes.

## Arguments

### Loc\_id

An integer representing the identifier of the group, dataset, or named datatype to query.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_OPEN\\_IDX](#)

# H5A\_GET\_SPACE

The H5A\_GET\_SPACE function returns the identifier number of a copy of the dataspace for an attribute.

## Syntax

*Result* = H5A\_GET\_SPACE(*Attribute\_id*)

## Return Value

Returns the dataspace's identifier. This identifier can be released with the [H5S\\_CLOSE](#).

## Arguments

### Attribute\_id

An integer representing the attribute's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_GET\\_NAME](#), [H5A\\_GET\\_TYPE](#), [H5S\\_CLOSE](#)

# H5A\_GET\_TYPE

The `H5A_GET_TYPE` function returns the identifier number of a copy of the datatype for an attribute.

## Syntax

```
Result = H5A_GET_TYPE(Attribute_id)
```

## Return Value

Returns the datatype identifier. This identifier should be released with the [H5T\\_CLOSE](#).

## Arguments

### Attribute\_id

An integer representing the attribute identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_GET\\_SPACE](#), [H5A\\_GET\\_NAME](#), [H5T\\_CLOSE](#)

# H5A\_OPEN\_IDX

The H5A\_OPEN\_IDX function opens an existing attribute by the index of that attribute within an HDF5 file.

## Syntax

*Result* = H5A\_OPEN\_IDX(*Loc\_id*, *Index*)

## Return Value

Returns the attribute's identifier number.

## Arguments

### Loc\_id

An integer representing the identifier of the group, dataset, or named datatype containing the attribute within.

### Index

An integer representing the zero-based index of the attribute to be accessed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_OPEN\\_NAME](#), [H5A\\_GET\\_NUM\\_ATTRS](#), [H5A\\_GET\\_NAME](#),  
[H5A\\_CLOSE](#)

# H5A\_OPEN\_NAME

The H5A\_OPEN\_NAME function opens an existing attribute by the name of that attribute within an HDF5 file.

## Syntax

*Result* = H5A\_OPEN\_NAME(*Loc\_id*, *Name*)

## Return Value

Returns the attribute's identifier number.

## Arguments

### Loc\_id

An integer representing the identifier of the group, dataset, or named datatype containing the attribute within.

### Name

A string representing the name of the attribute to be accessed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5A\\_OPEN\\_IDX](#), [H5A\\_CLOSE](#)

# H5A\_READ

The H5A\_READ function reads the data within an attribute, converting from the HDF5 file datatype into the HDF5 memory datatype, and finally into the corresponding IDL datatype.

## Syntax

```
Result = H5A_READ(Attribute_id [, Datatype_id])
```

## Return Value

Returns an IDL variable containing all of the attribute's data. For details on different return types and storage mechanisms, see the [H5D\\_READ](#) function.

## Arguments

### Attribute\_id

A long integer containing the identifier of the attribute to read.

### Datatype\_id

A long integer containing the identifier of the memory datatype to read. This argument is used only when reading part of a compound attribute. If *Datatype\_id* is not supplied, the entire attribute is read.

## Keywords

None

## Version History

5.6	Introduced
6.3	Added the <i>Datatype_id</i> argument.

## See Also

[H5A\\_OPEN\\_NAME](#), [H5A\\_OPEN\\_IDX](#), [H5A\\_CLOSE](#), [H5D\\_READ](#)

# H5A\_WRITE

The H5A\_WRITE procedure writes data to an attribute.

## Syntax

H5A\_WRITE, *Attribute\_id*, *Data*

## Arguments

### Attribute\_id

An integer giving the identifier of the attribute to which to write the data.

### Data

The data to be written. The following table shows how IDL data types are converted to HDF5 datatypes. Pointers, complex numbers, and object references cannot be written to HDF5 attributes. Data passed in via IDL will automatically be converted into the output data type if possible.

IDL Data Type	HDF5 Data Type
Byte	H5T_NATIVE_UINT8
Integer	H5T_NATIVE_INT16
Unsigned integer	H5T_NATIVE_UINT16
Long integer	H5T_NATIVE_INT32
Unsigned long integer	H5T_NATIVE_UINT32
64-bit Integer	H5T_NATIVE_INT64
Unsigned 64-bit integer	H5T_NATIVE_UINT64
Floating point	H5T_NATIVE_FLOAT
Double-precision floating	H5T_NATIVE_DOUBLE
String	H5T_C_S1

Table 3-13: IDL to HDF5 Corresponding Data Types



IDL Data Type	HDF5 Data Type
Reference Structure	H5T_REFERENCE
Structure	(Member datatypes)

*Table 3-13: IDL to HDF5 Corresponding Data Types (Continued)*

---

**Note**

The reference structure is returned from H5R\_CREATE.

---

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5A\\_CREATE](#), [H5S\\_CREATE\\_SIMPLE](#), [H5T\\_IDL\\_CREATE](#),  
[H5T\\_REFERENCE\\_CREATE](#)

# H5D\_CLOSE

The H5D\_CLOSE procedure closes the specified dataset and releases its used resources. After this routine is used, the dataset's identifier is no longer available until the [H5D\\_GET\\_SPACE](#) is used again to specify that dataset.

## Syntax

H5D\_CLOSE, *Dataset\_id*

## Arguments

### Dataset\_id

An integer representing the dataset's identifier to be closed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5D\\_OPEN](#)

# H5D\_CREATE

The H5D\_CREATE function creates a dataset at the specified location.

## Syntax

```
Result = H5D_CREATE(Loc_id, Name, Datatype_id, Dataspace_id  
[, CHUNK_DIMENSIONS=vector [, GZIP=value [, /SHUFFLE]]])
```

## Return Value

The *Result* gives the dataset identifier. This identifier should be released with the H5D\_CLOSE procedure.

## Arguments

### Loc\_id

An integer giving the identifier of the file or group within which to create the dataset.

### Name

A string giving the name of the dataset to create.

### Datatype\_id

An integer giving the datatype identifier to use when creating the dataset.

### Dataspace\_id

An integer giving the dataspace identifier to use when creating the dataset.

## Keywords

### CHUNK\_DIMENSIONS

A vector containing the chunk dimensions for the dataset. **CHUNK\_DIMENSIONS** must have the same number of elements as the number of dimensions in the dataspace specified in *Dataspace\_id*. This keyword must be set if the dataspace specified in *Dataspace\_id* has unlimited or extendable dimensions.

**Note**

Choosing appropriate values for `CHUNK_DIMENSIONS` is not always straight forward and is dependant on the size of the dataspace, the size of the data, how the data will be read, the current operating system, and many other factors. Improper chunk sizes can drastically inflate the size of the resulting file or greatly slow the reading of the data. For a dimension that is immutable a good suggestion is to choose a value that is evenly divisible into the dimension size. Values of less than 100 for dataspaces with dimensions greater than 1000 can result in bloated file sizes.

**GZIP**

Specifies the level of gzip compression applied to the dataset, which should be a value from zero to nine, inclusive. Lower compression levels are faster but result in less compression. If `CHUNK_DIMENSIONS` is not specified this keyword is ignored.

**SHUFFLE**

If set the shuffle filter will be applied to the dataset. If `GZIP` is not specified this keyword is ignored.

The shuffle filter de-interlaces a block of data by reordering the bytes. All bytes from one consistent byte position of each data element are placed together in one block; all bytes from a second consistent byte position of each data element are placed together a second block; and so on. For example, given three data elements of a 4-byte datatype stored as 012301230123, shuffling will re-order data as 000111222333. This can be a valuable step in an effective compression algorithm because the bytes in each byte position are often closely related to each other and putting them together can increase the compression ratio. When the shuffle filter is applied to a dataset, the compression ratio achieved is often superior to that achieved without the shuffle filter.

**Example**

See the example under [H5F\\_CREATE](#).

**Version History**

6.2	Introduced
-----	------------

## See Also

[H5D\\_CLOSE](#), [H5S\\_CREATE\\_SIMPLE](#), [H5T\\_IDL\\_CREATE](#)

# H5D\_EXTEND

The Dataspace of a dataset defines the number of dimensions and the size of each dimension. H5D\_EXTEND is used to change the current dimensions of the Dataset, within the limits of the Dataspace. Each dimension can be extended up to its maximum, or unlimited. The maximum dimension size is set when the Dataset is created and cannot be changed. The size of the dataset cannot be reduced after it is created. The actual dimension size can be incremented with calls to H5D\_EXTEND, up to the maximum.

## Syntax

H5D\_EXTEND, *Dataset\_id*, *Size*

## Arguments

### Dataset\_id

An integer giving the dataset identifier to extend.

### Size

Array containing the new magnitude of each dimension. The number of elements in Size must match the number of dimensions of the dataset.

### Note

---

The Size argument should be specified in IDL column-major order. Internally, the dimensions will be reversed to match HDF5/C row-major order.

---

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5D\\_CREATE](#)

# H5D\_GET\_SPACE

The H5D\_GET\_SPACE function returns an identifier number for a copy of the dataspace for a dataset.

## Syntax

*Result* = H5D\_GET\_SPACE(*Dataset\_id*)

## Return Value

Returns the dataspace's identifier. This identifier can be released with the [H5S\\_CLOSE](#).

## Arguments

### Dataset\_id

An integer representing the dataset's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_CLOSE](#), [H5D\\_GET\\_STORAGE\\_SIZE](#), [H5D\\_GET\\_TYPE](#)



# H5D\_GET\_STORAGE\_SIZE

The H5D\_GET\_STORAGE\_SIZE function returns the amount of storage in bytes required for a dataset. For chunked datasets, this value is the number of allocated chunks times the chunk size.

---

**Note**

This function does not typically need to be called, as IDL will automatically allocate the necessary memory when reading data.

---

## Syntax

*Result* = H5D\_GET\_STORAGE\_SIZE(*Dataset\_id*)

## Return Value

Returns the amount of storage in bytes.

## Arguments

### Dataset\_id

An integer representing the dataset's identifier to be queried.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5S\\_CLOSE](#), [H5D\\_GET\\_SPACE](#), [H5D\\_GET\\_TYPE](#)

# H5D\_GET\_TYPE

The `H5D_GET_TYPE` function returns an identifier number for a copy of the datatype for a dataset.

## Syntax

```
Result = H5D_GET_TYPE(Dataset_id)
```

## Return Value

Returns the datatype's identifier. This identifier can be released with the [H5T\\_CLOSE](#).

## Arguments

### Dataset\_id

An integer representing the dataset's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_CLOSE](#), [H5D\\_GET\\_SPACE](#), [H5D\\_GET\\_STORAGE\\_SIZE](#)

# H5D\_OPEN

The H5D\_OPEN function opens an existing dataset within an HDF5 file.

## Syntax

*Result* = H5D\_OPEN(*Loc\_id*, *Name*)

## Return Value

Returns the dataset's identifier. This identifier can be released with the [H5D\\_CLOSE](#).

## Arguments

### Loc\_id

An integer representing the identifier of the file or group containing the dataset.

### Name

A string representing the name of the dataset to be accessed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5D\\_CLOSE](#)

# H5D\_READ

The H5D\_READ function reads the data within a dataset, converting from the HDF5 file datatype into the HDF5 memory datatype, and finally into the corresponding IDL datatype.

## Syntax

```
Result = H5D_READ(Dataset_id [, Datatype_id] [, FILE_SPACE=id]  
[, MEMORY_SPACE=id] )
```

## Return Value

Returns an IDL variable containing the specified data. The different return types and storage mechanisms are described below.

### Note

---

The dimensions for the *Result* variable are constructed using the following precedence rules:

If MEMORY\_SPACE is specified, then the dimensions of the MEMORY\_SPACE are used.

If only FILE\_SPACE is specified, then the dimensions of the FILE\_SPACE are used.

If neither MEMORY\_SPACE nor FILE\_SPACE are specified, then the dimensions are taken from the *Dataset\_id*.

---

## Arguments

### Dataset\_id

A long integer containing the identifier of the dataset to read.

### Datatype\_id

A long integer containing the identifier of the memory datatype to read. This argument is used only when reading part of a compound dataset. If *Datatype\_id* is not supplied, the entire dataset is read.

## Keywords

### FILE\_SPACE

Set this keyword to the file dataspace identifier that should be used when reading the dataset. The FILE\_SPACE keyword may be used to define hyperslabs or elements for subselection within the dataset. The default is zero (in HDF5 this is equivalent to H5S\_ALL), which indicates that the entire dataspace should be read.

### MEMORY\_SPACE

Set this keyword to the memory dataspace identifier that should be used when copying the data from the file into memory. The MEMORY\_SPACE keyword may be used to define hyperslabs or elements in which to place the data. The default is zero (in HDF5 this is equivalent to H5S\_ALL), which indicates that the memory dataspace is identical to the file dataspace.

## Return Type

When reading in HDF5 datasets, the datatype is first set to the native HDF5 types. These native types are then converted to IDL types as shown in the following table:

HDF5 Class	HDF5 Datatype	IDL Type
H5T_INTEGER	H5T_NATIVE_UINT8	Byte
H5T_BITFIELD	H5T_NATIVE_INT16	Integer
H5T_ENUM	H5T_NATIVE_UINT16	Unsigned integer
	H5T_NATIVE_INT32	Long integer
	H5T_NATIVE_UINT32	Unsigned long integer
	H5T_NATIVE_INT64	64-bit integer
	H5T_NATIVE_UINT64	Unsigned 64-bit integer
H5T_REFERENCE	H5T_STD_REF_OBJ	Unsigned 64-bit integer
	H5T_REF_DSETREG	Structure

Table 3-14: HDF and IDL Datatypes

HDF5 Class	HDF5 Datatype	IDL Type
H5T_FLOAT	H5T_NATIVE_FLOAT	Floating point
	H5T_NATIVE_DOUBLE	Double-precision floating
H5T_STRING	H5T_C_S1	String
H5T_TIME	H5T_C_S1	String
H5T_COMPOUND	(Member datatypes)	Structure
H5T_ARRAY	(Super datatype)	(Super type)

Table 3-14: HDF and IDL Datatypes (Continued)

---

**Note**

Multidimensional datasets are returned in IDL column-major order, with the fastest-varying dimensions listed first. HDF5 uses C row-major order, with the fastest-varying dimensions listed last. In both cases, the memory layout for data elements is identical (i.e., no transpose is needed), and only the order of the dimensions is reversed.

---



---

**Note**

For the H5T\_ARRAY datatype, the array dimensions are concatenated with the dataset dimensions, with the array dimensions varying more rapidly.

---



---

**Note**

Structure tag names are constructed from H5T\_COMPOUND member names by switching to uppercase and converting all non-alphanumeric characters to underscores.

---

## Version History

5.6	Introduced
6.2	Added H5T_STD_REF_DSETREG Datatype (structure IDL type) to the H5T_REFERENCE class
6.3	Added the <i>Datatype_id</i> argument

## See Also

[H5D\\_CLOSE](#), [H5D\\_OPEN](#), [H5A\\_READ](#), [H5S\\_CREATE\\_SIMPLE](#),  
[H5S\\_SELECT\\_ELEMENTS](#), [H5S\\_SELECT\\_HYPERSLAB](#)

# H5D\_WRITE

The H5D\_WRITE procedure writes data to a dataset.

## Syntax

```
H5D_WRITE, Dataset_id, Data [, MEMORY_SPACE_ID=value]  
[, FILE_SPACE_ID=value]
```

## Arguments

### Dataset\_id

An integer giving the dataspace identifier to which to write the data.

### Data

The data containing the selection to be written. The table shows how IDL data types are converted to HDF5 datatypes. Pointers and object references cannot be written to HDF5 datasets. Data passed in via IDL will automatically be converted into the output data type if possible.

## Keywords

### MEMORY\_SPACE\_ID

An integer giving the identifier of the dataspace of the dataset. The default is to use the entire dataset.

### FILE\_SPACE\_ID

An integer giving the identifier of dataset's dataspace in the file. The default is to use the entire dataset.

## Example

See the example under [H5F\\_CREATE](#).



## Version History

6.2	Introduced
-----	------------

## See Also

[H5D\\_CREATE](#), [H5S\\_CREATE\\_SIMPLE](#)

# H5F\_CLOSE

The H5F\_CLOSE procedure closes the specified file and releases resources used by it. After this routine is used, the file's identifier is no longer available.

## Syntax

H5F\_CLOSE, *File\_id*

## Arguments

### File\_id

An integer representing the file's identifier to be closed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5F\\_OPEN](#)

# H5F\_CREATE

The H5F\_CREATE function is the primary function for creating HDF5 files.

**Note**

As an alternative, see [H5\\_CREATE](#).

## Syntax

*Result* = H5F\_CREATE(*Filename*)

## Return Value

*Result* is a file identifier for the newly-created file; this file identifier should be closed by calling H5F\_CLOSE when it is no longer needed.

## Arguments

### Filename

A string giving the name of the file to create.

## Keywords

None

## Example

```
; create HDF5 file
file = 'hdf5_out.h5'
fid = H5F_CREATE(file)

; create some data
data = hanning(100,200)

; create a datatype
datatype_id = H5T_IDL_CREATE(data)

; create a dataspace, allow the dataspace to be extendable
dataspace_id = $
    H5S_CREATE_SIMPLE([100,100],max_dimensions=[200,200])
```

```

; create the dataset
dataset_id = H5D_CREATE(fid,'Hanning',datatype_id,dataspace_id, $
    chunk_dimensions=[20,20])

; extend the size of the dataset to fit the data
H5D_EXTEND,dataset_id,size(data,/dimensions)

; write the data to the dataset
H5D_WRITE,dataset_id,data

; close some identifiers
H5S_CLOSE,dataspace_id
H5T_CLOSE,datatype_id

; create a reference attribute attached to the dataset
dataspace_id = H5S_CREATE_SIMPLE(size(data,/dimensions))

; select a 30x30 element region of interest in the dataset
H5S_SELECT_HYPERSLAB,dataspace_id,[40,40],[1,1], $
    block=[30,30],/reset

; create a dataspace region reference
ref = H5R_CREATE(fid,'Hanning',dataspace=dataspace_id)

; create a datatype for the reference
datatype_id = H5T_REFERENCE_CREATE(/region)

; create a one element dataspace for the single reference
dataspace_id = H5S_CREATE_SIMPLE(1)

; make the reference an attribute of the dataset
attr_id = H5A_CREATE(dataset_id,'Ref',datatype_id,dataspace_id)
H5A_WRITE,attr_id,ref
H5A_CLOSE,attr_id

; create a dummy attribute and delete it
attr_id2 = $
H5A_CREATE(dataset_id,'Dummy',datatype_id,dataspace_id)

; attribute must be closed before it can be deleted
H5A_CLOSE,attr_id2
H5A_DELETE,dataset_id,'Dummy'

; create a group to hold sample datatypes and links
group_id = H5G_CREATE(fid,'Datatypes and links')

; add a comment to the group
H5G_SET_COMMENT,fid,'Datatypes and links', $
    'This is a sample comment'

```

```

; add a datatype to the group
datatype_id2 = H5T_IDL_CREATE(1)

; add the datatype to the group and give it a name
H5T_COMMIT,group_id,'Integer',datatype_id2

; create an array datatype and add it to the group with a name
datatype_id3 = H5T_ARRAY_CREATE(datatype_id2,[3,4])
H5T_COMMIT,group_id,'Integer 2',datatype_id3

; rename previous datatype
H5G_MOVE,group_id,'Integer 2','Integer Array'

; close temporary datatypes
H5T_CLOSE,datatype_id3
H5T_CLOSE,datatype_id2

; create a compound datatype and add it to the group
struct = {float:1.0, double:1.0d}
datatype_id4 = $
    H5T_IDL_CREATE(struct,member_names=['Float','Double'])

; create an integer datatype and insert it in the
; compound datatype
datatype_id5 = H5T_IDL_CREATE(1)
H5T_INSERT,datatype_id4,'Integer',datatype_id5

; add the datatype to the group and give it a name
H5T_COMMIT,group_id,'Compound',datatype_id4

; close datatype identifiers
H5T_CLOSE,datatype_id5
H5T_CLOSE,datatype_id4

; add a hard link from the group to the Hanning dataset
H5G_LINK,fid,'Hanning','Link to Hanning',new_loc_id=group_id

; add a dummy link
H5G_LINK,group_id,'Integer','Link to Integer'

; remove dummy link
H5G_UNLINK,group_id,'Link to Integer'

; close remaining open identifiers
H5G_CLOSE,group_id
H5D_CLOSE,dataset_id
H5T_CLOSE,datatype_id
H5S_CLOSE,dataspace_id
H5F_CLOSE,fid

```

## Version History

6.2	Introduced
-----	------------

## See Also

[H5F\\_CLOSE](#)

# H5F\_IS\_HDF5

The H5F\_IS\_HDF5 function determines if a file is in the HDF5 format.

## Syntax

*Result* = H5F\_IS\_HDF5(*Filename*)

## Return Value

Returns 1 if the file is in the HDF5 format, 0 if otherwise.

## Arguments

### Filename

A string representing the name of the files to be checked.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5F\\_OPEN](#)

# H5F\_OPEN

The H5F\_OPEN function opens an existing HDF5 file.

## Syntax

```
Result = H5F_OPEN(Filename)([, /WRITE])
```

## Return Value

Returns the file identifier number. This identifier can be released with the [H5F\\_CLOSE](#).

## Arguments

### Filename

A string representing the name of the file to be accessed.

## Keywords

### WRITE

If set the file is open for both reading and writing. The default is to open the file in read\_only mode.

## Version History

5.6	Introduced
6.2	Added WRITE keyword.

## See Also

[H5F\\_CLOSE](#), [H5F\\_IS\\_HDF5](#)



# H5G\_CLOSE

The H5G\_CLOSE procedure closes the specified group and releases resources used by it. After this routine is used, the group's identifier is no longer available until the [H5F\\_OPEN](#) routine is used again to specify that group.

## Syntax

H5G\_CLOSE, *Group\_id*

## Arguments

### Group\_id

An integer representing the group's identifier to be closed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_OPEN](#)

# H5G\_CREATE

The H5G\_CREATE function creates a new empty group and gives it a name.

## Syntax

*Result* = H5G\_CREATE(*Loc\_id*, *Name*)

## Return Value

*Result* is the group identifier for the open group; this group identifier should be closed by calling H5G\_CLOSE when it is no longer needed.

## Arguments

### Loc\_id

An integer giving the identifier of the file or group.

### Name

A string giving the name of the new group.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CLOSE](#)

# H5G\_GET\_COMMENT

The H5G\_GET\_COMMENT function retrieves a comment string from a specified object.

## Syntax

*Result* = H5G\_GET\_COMMENT(*Loc\_id*, *Name*)

## Return Value

Returns a string containing the comment, or a null string if no comment exists.

## Arguments

### Loc\_id

An integer representing the identifier of the file or group.

### Name

A string representing the name of the object for which to retrieve the comment.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_GET\\_OBINFO](#)

# H5G\_GET\_LINKVAL

The `H5G_GET_LINKVAL` function returns the name of the object pointed to by a symbolic link.

## Syntax

*Result* = `H5G_GET_LINKVAL`(*Loc\_id*, *Name*)

## Return Value

Returns a string containing the name of the object pointed to by a symbolic link.

## Arguments

### Loc\_id

An integer representing the identifier of the file or group.

### Name

A string representing the name of the symbolic link for which to retrieve the link value.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_GET\\_OBJINFO](#)

# H5G\_GET\_MEMBER\_NAME

The H5G\_GET\_MEMBER\_NAME function retrieves the name of an object within a group, by its zero-based index.

---

**Note**

This function is not part of the standard HDF5 interface, but is provided as a programming convenience. The H5Giterate() C function is used to retrieve the name.

---

## Syntax

*Result* = H5G\_GET\_MEMBER\_NAME(*Loc\_id*, *Name*, *Index*)

## Return Value

Returns a string containing the object's name.

## Arguments

### Loc\_id

An integer representing the identifier of the file or group.

### Name

A string representing the name of the group in which to retrieve the member name.

### Index

An integer representing the zero-based index of the object for which to retrieve the name.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_GET\\_NMEMBERS](#)

# H5G\_GET\_NMEMBERS

The H5G\_GET\_NMEMBERS function returns the number of objects within a group.

**Note**

This function is not part of the standard HDF5 interface, but is provided as a programming convenience. The H5Giterate() C function is used to retrieve the number of members.

## Syntax

```
Result = H5G_GET_NMEMBERS(Loc_id, Name)
```

## Return Value

Returns the number of objects.

## Arguments

**Loc\_id**

An integer representing the identifier of the file or group.

**Name**

A string representing the name of the group for which to retrieve the number of members.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_GET\\_MEMBER\\_NAME](#)

# H5G\_GET\_NUM\_OBJS

The H5G\_GET\_NUM\_OBJS function returns number of objects in the group specified by its identifier.

## Syntax

*Result* = H5G\_GET\_NUM\_OBJS(*Loc\_id*)

## Return Value

*Result* is the number of objects contained in the group.

## Arguments

### Loc\_id

An integer giving the file or group identifier.

## Keywords

None

## Version History

---

6.2	Introduced
-----	------------

---

## See Also

[H5G\\_CREATE](#), [H5G\\_GET\\_OBJ\\_NAME\\_BY\\_IDX](#)



# H5G\_GET\_OBJ\_NAME\_BY\_IDX

The H5G\_GET\_OBJ\_NAME\_BY\_IDX function returns a name of an object specified by an index.

## Syntax

*Result* = H5G\_GET\_OBJ\_NAME\_BY\_IDX(*Loc\_id*, *Index*)

## Return Value

*Result* is a string containing the name of the object.

## Arguments

### Loc\_id

An integer giving file or group identifier.

### Index

An integer index identifying the object.

## Keywords

None

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CREATE](#), [H5G\\_GET\\_NUM\\_OBJS](#)

# H5G\_GET\_OBJINFO

The H5G\_GET\_OBJINFO function retrieves information from a specified object.

## Syntax

```
Result = H5G_GET_OBJINFO(Loc_id, Name [, /FOLLOW_LINK] )
```

## Return Value

Returns a structure of the name H5F\_STAT containing the following fields:

### FILENO

This field contains two integers which, along with the OBJNO field, uniquely identify the object among all open HDF5 files.

### OBJNO

This field contains two integers which, along with the FILENO field, uniquely identify the object among all open HDF5 files. If all four values in FILENO and OBJNO are the same between two objects, then these two objects are the same.

### NLINK

The number of hard links to the object. If this field is zero, then the object is a symbolic link.

### TYPE

A string representing the object type. Possible values are:

- 'LINK'
- 'GROUP'
- 'DATASET'
- 'TYPE'
- 'UNKNOWN'

### MTIME

The modification time for the object, in seconds since 1 January 1970.

**Tip**


---

You can convert the MTIME field from seconds to a date/time string using `SYSTIME(0, mtime)`. See `SYSTIME` for more information.

---

**LINKLEN**

If the object is a symbolic link (and the `FOLLOW_LINK` keyword is not set), then this field will contain the length in characters of the link value. The link value itself may be retrieved using `H5D_GET_LINKVAL`.

**Arguments****Loc\_id**

An integer representing the identifier of the file or group.

**Name**

A string representing the name of the object for which to retrieve the information structure.

**Keywords****FOLLOW\_LINK**

If *Name* is a symbolic link, then set this keyword to follow the symbolic link and retrieve information about the linked object. The default is to return information about the symbolic link itself.

**Version History**

5.6	Introduced
-----	------------

**See Also**

[H5G\\_GET\\_LINKVAL](#)

# H5G\_LINK

The H5G\_LINK procedure creates a link of the specified type. A link can only point to one of the three classes of named objects: group, dataset, and named datatype.

## Syntax

```
H5G_LINK, Loc_id, Current_Name, New_Name [, /SOFTLINK]
      [, NEW_LOC_ID=value]
```

## Arguments

### Loc\_id

An integer giving the file or group identifier.

### Current\_Name

String name of the existing object if link is a hard link. Can be anything for the soft link.

When creating a soft link *Current\_Name* can be absolute or relative and may include path information.

For example, to create a link to an object that exists in the current group use the name of the object:

```
Object1
```

To create a link to an object that exists in a sub group of the current group use a relative path name:

```
Subgroup/Object1 or ./Subgroup/Object1
```

To create a link to an object that exists outside of the current group use an absolute path (a path beginning with the root group of the file, '/');

```
/Group1/Object1
```

### New\_Name

New string name for the object.

## Keywords

### SOFTLINK

If set the link will be a soft link. The default is to create a hard link.

### NEW\_LOC\_ID

An integer giving the file or group identifier for the new link. This keyword is only used when linking to an object in a different file or group.

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CREATE](#), [H5G\\_UNLINK](#)

# H5G\_MOVE

The H5G\_MOVE procedure renames/moves an object within an HDF5 group or file.

## Syntax

```
H5G_MOVE, Loc_id, Src_Name, Dst_Name [, NEW\_LOC\_ID=value]
```

## Arguments

### Loc\_id

An integer giving the file or group identifier.

### Src\_Name

Original string name of the object.

### Dst\_Name

New string name for the object.

## Keywords

### NEW\_LOC\_ID

An integer giving the destination file or group identifier. This keyword is only used when linking to an object in a different file or group.

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CREATE](#)

# H5G\_OPEN

The H5G\_OPEN function opens an existing group within an HDF5 file.

## Syntax

*Result* = H5G\_OPEN(*Loc\_id*, *Name*)

## Return Value

Returns the group's identifier number. This identifier can be released with the [H5G\\_CLOSE](#).

## Arguments

### Loc\_id

An integer representing the identifier of the file or group containing the group to be accessed.

### Name

A string representing the name of the group to be accessed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5G\\_CLOSE](#)

# H5G\_SET\_COMMENT

[Syntax](#) | [Arguments](#) | [Keywords](#) | [Example](#) | [Version History](#) | [See Also](#)

The H5G\_SET\_COMMENT procedure sets a comment for a specified object.

## Syntax

H5G\_SET\_COMMENT, *Loc\_id*, *Name*, *Comment*

## Arguments

### Loc\_id

An integer giving the file or group identifier containing the object.

### Name

Name of the object within Loc\_id whose comment is to be set or reset.

### Comment

New comment for the object.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CREATE](#)



# H5G\_UNLINK

The H5G\_UNLINK procedure removes the link to an object from a group.

## Syntax

H5G\_UNLINK, *Loc\_id*, *Name*

## Arguments

### Loc\_id

An integer giving the file or group identifier containing the object.

### Name

Name of the object within Loc\_id to unlink.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5G\\_CREATE](#), [H5G\\_LINK](#)

# H5I\_GET\_FILE\_ID

The `H5I_GET_FILE_ID` function retrieves an identifier for the file containing the specified object.

## Syntax

*Result* = `H5I_GET_FILE_ID(Loc_id)`

## Return Value

The *Result* is the identifier of the file.

## Arguments

### Loc\_id

An integer giving the identifier of the object whose associated file identifier will be returned.

## Keywords

NONE

## Version History

6.2	Introduced
-----	------------

# H5I\_GET\_TYPE

The H5I\_GET\_TYPE function returns the object's type.

## Syntax

*Result* = H5I\_GET\_TYPE(*Obj\_id*)

## Return Value

Returns a string representing the object type. Possible return values include:

- 'FILE'
- 'GROUP'
- 'DATATYPE'
- 'DATASPACE'
- 'DATASET'
- 'ATTR'
- 'BADID'

## Arguments

### Obj\_id

An integer representing the object's identifier for which to return the type.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

# H5R\_CREATE

The `H5R_CREATE` function creates a reference to either an object or a dataspace region of a dataset.

## Syntax

```
Result = H5R_CREATE(Loc_id, Name [, DATASPACE_ID=value])
```

## Return Value

The *Result* is the reference pointing to the specified object. It is returned as either an integer, if an object reference is returned, or a named structure, if a dataspace region reference is returned.

## Arguments

### Loc\_id

An integer giving the identifier used to locate the object being pointed to. This is the identifier of the object containing *Name*.

### Name

The name of the object contained within *Loc\_id*.

## Keywords

### DATASPACE\_ID

An integer giving the identifier of the selection. Use of this keyword will create a dataspace region reference. If not supplied then an object reference will be created.

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5S\\_CREATE\\_SIMPLE](#)

# H5R\_DEREFERENCE

The H5R\_DEREFERENCE function opens a reference and returns the object identifier.

## Syntax

*Result* = H5R\_DEREFERENCE(*Loc\_id*, *Reference*)

## Return Value

The *Result* is the identifier number. This identifier should be released using the appropriate close procedure.

## Arguments

### Loc\_id

An integer giving the identifier in which the reference dataset is located.

### Reference

An integer or H5 reference structure giving the reference number to open.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5R\\_GET\\_OBJECT\\_TYPE](#)

# H5R\_GET\_OBJECT\_TYPE

The `H5R_GET_OBJECT_TYPE` function returns the type of object that an object reference points to.

## Syntax

*Result* = `H5R_GET_OBJECT_TYPE(Loc_id, Reference)`

## Return Value

The *Result* is a string giving the object type. Possible return values include:

- 'DATASET'
- 'GROUP'
- 'LINK'
- 'TYPE'
- 'UNKNOWN'

## Arguments

### Loc\_id

An integer giving the identifier in which the reference dataset is located.

### Reference

An integer giving the reference number to query.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5R\\_DEREFERENCE](#)



# H5R\_GET\_REGION

The H5R\_GET\_REGION function retrieves a dataspace associated with a region reference.

## Syntax

*Result* = H5R\_GET\_REGION(*Dataset\_id*, *Reference*)

## Return Value

The *Result* gives the identifier of the dataspace with the region selected.

## Arguments

### Dataset\_id

An integer giving the identifier in which the reference dataset is located.

### Reference

An H5 reference structure giving the reference number to open.

## Keywords

None

## Example

Assuming the file, 'hdf5\_out.h5' was created using the example in H5F\_CREATE, the dataspace region saved in the reference attached to the “Hanning” dataset could be obtained as follows:

```
fid = H5F_OPEN('hdf5_out.h5')
dataset_id = H5D_OPEN(fid, 'Hanning')
attr_id = H5A_OPEN_NAME(dataset_id, 'Ref')
ref = H5A_READ(attr_id)
dataspace_id = H5R_GET_REGION(dataset_id, ref)
```

## Version History

6.2	Introduced
-----	------------

## See Also

[H5R\\_CREATE](#), [H5D\\_CREATE](#), [H5D\\_CLOSE](#)

# H5S\_CLOSE

The H5S\_CLOSE procedure releases and terminates access to a dataspace. After this routine is used, the dataspace's identifier is no longer available.

**Warning**

---

Failure to release a dataspace using this procedure will result in resource leaks.

---

## Syntax

H5S\_CLOSE, *Dataspace\_id*

## Arguments

**Dataspace\_id**

An integer representing the dataspace's identifier to close.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5D\\_GET\\_SPACE](#)

# H5S\_COPY

The H5S\_COPY function copies an existing dataspace.

## Syntax

*Result* = H5S\_COPY(*Dataspace\_id*)

## Return Value

Returns the dataspace's identifier number. The dataspace identifier can be released with the [H5S\\_CLOSE](#).

## Arguments

### Dataspace\_id

An integer representing the dataspace identifier to copy.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_CREATE\\_SIMPLE](#), [H5S\\_CLOSE](#)

# H5S\_CREATE\_SCALAR

[Syntax](#) | [Return Value](#) | [Arguments](#) | [Keywords](#) | [Version History](#)

The H5S\_CREATE\_SCALAR function creates a scalar dataspace.

---

**Note**

Scalar dataspace have no dimensionality thus H5S\_GET\_SIMPLE\_EXTENT\_DIMS and H5S\_GET\_SIMPLE\_EXTENT\_NDIMIS will both return 0.

---

## Syntax

*Result* = H5S\_CREATE\_SCALAR()

## Return Value

The *Result* gives the dataspace identifier. This identifier should be released with the H5S\_CLOSE procedure.

## Arguments

None

## Keywords

None

## Version History

---

6.2	Introduced
-----	------------

---

# H5S\_CREATE\_SIMPLE

The H5S\_CREATE\_SIMPLE function creates a simple dataspace.

## Syntax

*Result* = H5S\_CREATE\_SIMPLE(*Dimensions* [, MAX\_DIMENSIONS=*vector*])

## Return Value

Returns the dataspace's identifier number. This dataspace identifier can be released with the [H5S\\_CLOSE](#).

## Arguments

### Dimensions

Set this argument to a vector containing the dimensions for the dataspace.

#### Note

---

The *Dimensions* argument should be specified in IDL's column-major order. Internally, the dimensions will be reversed to match HDF5/C's row-major order.

---

## Keywords

### MAX\_DIMENSIONS

Set this keyword to a vector containing the maximum dimensions for the dataspace. The MAX\_DIMENSIONS must have the same number of elements as the *Dimensions* argument. If MAX\_DIMENSIONS is omitted then the maximum dimensions are set to *Dimensions*. You can use a value of -1 in MAX\_DIMENSIONS to indicate an unlimited dimension.

#### Note

---

The values specified in the MAX\_DIMENSIONS keyword should be equal to or greater than the corresponding values of the *Dimensions* argument.

---

**Note**

The `MAX_DIMENSIONS` keyword should be specified in IDL's column-major order. Internally, the dimensions will be reversed to match HDF5/C's row-major order.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_CLOSE](#), [H5S\\_COPY](#)

# H5S\_GET\_SELECT\_BOUNDS

The H5S\_GET\_SELECT\_BOUNDS function retrieves the coordinates of the bounding box containing the current dataspace selection.

## Syntax

*Result* = H5S\_GET\_SELECT\_BOUNDS(*Dataspace\_id*)

## Return Value

Returns an ( $m \times 2$ ) array, where  $m$  is the number of dimensions (or rank) of the dataspace. The first row in the array is the starting coordinates of the bounding box, while the second row is the ending coordinates.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#), [H5S\\_GET\\_SELECT\\_NPOINTS](#),  
[H5S\\_GET\\_SELECT\\_ELEM\\_NPOINTS](#),  
[H5S\\_GET\\_SELECT\\_HYPER\\_NBLOCKS](#)



# H5S\_GET\_SELECT\_ELEM\_NPOINTS

The H5S\_GET\_SELECT\_ELEM\_NPOINTS function determines the number of element points in the current dataspace selection.

## Syntax

*Result* = H5S\_GET\_SELECT\_ELEM\_NPOINTS(*Dataspace\_id*)

## Return Value

Returns the number of element points.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_BOUNDS](#), [H5S\\_GET\\_SELECT\\_HYPER\\_NBLOCKS](#),  
[H5S\\_GET\\_SELECT\\_NPOINTS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#)

# H5S\_GET\_SELECT\_ELEM\_POINTLIST

The `H5S_GET_SELECT_ELEM_POINTLIST` function returns a list of the element points in the current dataspace selection.

## Syntax

```
Result = H5S_GET_SELECT_ELEM_POINTLIST(Dataspace_id [, START=value]
    [, NUMBER=value] )
```

## Return Value

The *Result* is an ( $m \times n$ ) array, where  $m$  is the number of dimensions (or rank) of the dataspace, and  $n$  is the number of selected points. Each row contains the coordinates for an element selection point.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

### START

Set this keyword to an integer representing the point to start with, counting from 0. The default is `START = 0`.

### NUMBER

Set this keyword to an integer representing the number of element points to return. The default is `NUMBER = (N - START)`, where  $N$  is the total number of element points in the selection.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_ELEM\\_NPOINTS](#), [H5S\\_GET\\_SELECT\\_NPOINTS](#)

# H5S\_GET\_SELECT\_HYPER\_BLOCKLIST

The H5S\_GET\_SELECT\_HYPER\_BLOCKLIST function returns a list of the hyperslab blocks in the current dataspace selection.

## Syntax

```
Result = H5S_GET_SELECT_HYPER_BLOCKLIST(Dataspace_id  
[, START=value] [, NUMBER=value] )
```

## Return Value

Returns an ( $m \times 2n$ ) array, where  $m$  is the number of dimensions (or rank) of the dataspace. The  $2n$  rows of *Result* contain the list of blocks. The first row contains the start coordinates of the first block, followed by the next row which contains the opposite corner coordinates, followed by the next row which contains the start coordinates of the second block, etc.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

### START

Set this keyword to an integer representing the block to start with, counting from 0. The default is `START = 0`.

### NUMBER

Set this keyword to an integer representing the number of blocks to return. The default is `NUMBER = (N - START)`, where  $N$  is the total number of blocks in the selection.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_HYPER\\_NBLOCKS](#), [H5S\\_GET\\_SELECT\\_NPOINTS](#)

# H5S\_GET\_SELECT\_HYPER\_NBLOCKS

The `H5S_GET_SELECT_HYPER_NBLOCKS` function determines the number of hyperslab blocks in the current dataspace selection.

## Syntax

*Result* = `H5S_GET_SELECT_HYPER_NBLOCKS(Dataspace_id)`

## Return Value

Returns the number of blocks.

## Arguments

### `Dataspace_id`

An integer representing the dataspace identifier to be queried.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5S\\_GET\\_SELECT\\_BOUNDS](#), [H5S\\_GET\\_SELECT\\_ELEM\\_NPOINTS](#),  
[H5S\\_GET\\_SELECT\\_NPOINTS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#)

# H5S\_GET\_SELECT\_NPOINTS

The H5S\_GET\_SELECT\_NPOINTS function determines the number of elements in a dataspace selection.

## Syntax

*Result* = H5S\_GET\_SELECT\_NPOINTS(*Dataspace\_id*)

## Return Value

Returns the number of elements.

## Arguments

### Dataspace\_id

An integer representing the dataspace identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_BOUNDS](#), [H5S\\_GET\\_SELECT\\_ELEM\\_NPOINTS](#),  
[H5S\\_GET\\_SELECT\\_HYPER\\_NBLOCKS](#),  
[H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#)

# H5S\_GET\_SIMPLE\_EXTENT\_DIMS

The `H5S_GET_SIMPLE_EXTENT_DIMS` function returns the dimension sizes for a dataspace.

## Syntax

```
Result = H5S_GET_SIMPLE_EXTENT_DIMS(Dataspace_id  
[, MAX_DIMENSIONS=variable] )
```

## Return Value

Returns a vector containing the dimension sizes.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

### MAX\_DIMENSIONS

Set this keyword to a named variable to return the maximum dimension sizes for the dataspace.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SIMPLE\\_EXTENT\\_NDIMS](#),  
[H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_TYPE](#)



# H5S\_GET\_SIMPLE\_EXTENT\_NDIMS

The H5S\_GET\_SIMPLE\_EXTENT\_NDIMS function determines the number of dimensions (or rank) of a dataspace.

## Syntax

*Result* = H5S\_GET\_SIMPLE\_EXTENT\_NDIMS(*Dataspace\_id*)

## Return Value

Returns the number of dimensions.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SIMPLE\\_EXTENT\\_DIMS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_TYPE](#)

# H5S\_GET\_SIMPLE\_EXTENT\_NPOINTS

The `H5S_GET_SIMPLE_EXTENT_NPOINTS` function determines the number of elements in a dataspace.

## Syntax

*Result* = `H5S_GET_SIMPLE_EXTENT_NPOINTS(Dataspace_id)`

## Return Value

Returns the number of elements.

## Arguments

### **Dataspace\_id**

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SIMPLE\\_EXTENT\\_DIMS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_NDIMS](#),  
[H5S\\_GET\\_SIMPLE\\_EXTENT\\_TYPE](#)

# H5S\_GET\_SIMPLE\_EXTENT\_TYPE

The `H5S_GET_SIMPLE_EXTENT_TYPE` function returns the current class of a dataspace.

## Syntax

```
Result = H5S_GET_SIMPLE_EXTENT_TYPE(Dataspace_id)
```

## Return Value

Returns a string containing the class. Possible values are:

- 'H5S\_SCALAR'
- 'H5S\_SIMPLE'
- 'H5S\_COMPLEX'
- 'H5S\_NO\_CLASS'

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SIMPLE\\_EXTENT\\_DIMS](#), [H5S\\_GET\\_SIMPLE\\_EXTENT\\_NDIMS](#),  
[H5S\\_GET\\_SIMPLE\\_EXTENT\\_NPOINTS](#)

# H5S\_IS\_SIMPLE

The H5S\_IS\_SIMPLE function determines whether a dataspace is a simple dataspace.

## Syntax

*Result* = H5S\_IS\_SIMPLE(*Dataspace\_id*)

## Return Value

Returns 1 if the dataspace is simple and 0 if it is not.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

# H5S\_OFFSET\_SIMPLE

The H5S\_OFFSET\_SIMPLE procedure sets the selection offset for a simple dataspace. The offset allows the same shaped selection to be moved to different locations within the dataspace.

## Syntax

H5S\_OFFSET\_SIMPLE, *Dataspace\_id*, *Offset*

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier on which to set the selection offset.

### Offset

An  $m$ -element vector of integers, where  $m$  is the number of dataspace dimensions, containing the offsets.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_BOUNDS](#), [H5S\\_SELECT\\_ELEMENTS](#),  
[H5S\\_SELECT\\_HYPERSLAB](#)

# H5S\_SELECT\_ALL

The H5S\_SELECT\_ALL procedure selects the entire extent of a dataspace.

## Syntax

H5S\_SELECT\_ALL, *Dataspace\_id*

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be selected.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_NPOINTS](#), [H5S\\_SELECT\\_ELEMENTS](#),  
[H5S\\_SELECT\\_HYPERSLAB](#), [H5S\\_SELECT\\_NONE](#)

# H5S\_SELECT\_ELEMENTS

The H5S\_SELECT\_ELEMENTS procedure selects array elements to be included in the selection for a dataspace.

## Syntax

H5S\_SELECT\_ELEMENTS, *Dataspace\_id*, *Coordinates* [, /RESET]

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier on which to set the selection.

### Coordinates

An  $m$ -element vector, or an  $(m \times n)$  array, where  $m$  is the number of dimensions (or rank) of the dataspace, and  $n$  is the number of selected points. Each row contains the coordinates for an element selection point.

## Keywords

### RESET

Set this keyword to replace the existing selection with the new *Coordinates*. The default is RESET = 0 which adds the new selection to the existing selection.

### Note

---

The RESET keyword must be set (/RESET or RESET = 1) or the H5S\_SELECT\_ELEMENTS routine will result in an error message. This error message comes from the HDF5 library, which forces a default of RESET = 0 but insists on this keyword being set for this routine to work.

---

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_ELEM\\_NPOINTS](#),  
[H5S\\_GET\\_SELECT\\_ELEM\\_POINTLIST](#), [H5S\\_GET\\_SELECT\\_NPOINTS](#),  
[H5S\\_SELECT\\_HYPERSLAB](#)



# H5S\_SELECT\_HYPERSLAB

The H5S\_SELECT\_HYPERSLAB procedure selects a hyperslab region to be included in the selection for a dataspace.

---

**Note**

If all of the elements in the selected hyperslab region are already selected, then a new hyperslab region is not created.

---

## Syntax

```
H5S_SELECT_HYPERSLAB, Dataspace_id, Start, Count, [, BLOCK=vector]  
[, /RESET] [, STRIDE=vector]
```

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier on which to set the selection.

### Start

An  $m$ -element vector of integers, where  $m$  is the number of dataspace dimensions, containing the starting location for the hyperslab.

### Count

An  $m$ -element vector of integers containing the number of blocks to select in each dimension.

## Keywords

### BLOCK

Set this keyword to an  $m$ -element vector of integers containing the size of a block. The default is a single element in each dimension (for example BLOCK is set to a vector of all 1's).

### RESET

Set this keyword to replace the existing selection with the new selection. The default is RESET=0 which adds the new selection to the existing selection.

## STRIDE

Set this keyword to an  $m$ -element vector of integers containing the number of elements to move in each dimension when selecting blocks. The default is to move a single element in each dimension (for example STRIDE is set to a vector of all 1's). STRIDE values must be greater than zero.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_HYPER\\_BLOCKLIST](#),  
[H5S\\_GET\\_SELECT\\_HYPER\\_NBLOCKS](#), [H5S\\_GET\\_SELECT\\_NPOINTS](#),  
[H5S\\_SELECT\\_ELEMENTS](#)

# H5S\_SELECT\_NONE

The H5S\_SELECT\_NONE procedure resets the dataspace selection region to include no elements.

## Syntax

H5S\_SELECT\_NONE, *Dataspace\_id*

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be reset.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5S\\_GET\\_SELECT\\_NPOINTS](#), [H5S\\_SELECT\\_ALL](#),  
[H5S\\_SELECT\\_ELEMENTS](#), [H5S\\_SELECT\\_HYPERSLAB](#)

# H5S\_SELECT\_VALID

The H5S\_SELECT\_VALID function verifies that the selection is within the extent of a dataspace.

## Syntax

*Result* = H5S\_SELECT\_VALID(*Dataspace\_id*)

## Return Value

Returns 1 if the selection is within the dataspace and 0 if it is not.

## Arguments

### Dataspace\_id

An integer representing the dataspace's identifier to be queried.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5S\\_GET\\_SELECT\\_NPOINTS](#), [H5S\\_SELECT\\_ELEMENTS](#),  
[H5S\\_SELECT\\_HYPERSLAB](#)

# H5S\_SET\_EXTENT\_NONE

[Syntax](#) | [Arguments](#) | [Keywords](#) | [Version History](#) | [See Also](#)

The H5S\_SET\_EXTENT\_NONE removes the extent of a dataspace and sets the type to H5S\_NO\_CLASS. As such the dataspace cannot be resized or used in the creation of datasets or attributes.

## Syntax

H5S\_SET\_EXTENT\_NONE, *Dataspace\_id*

## Arguments

### Dataspace\_id

An integer giving the dataspace identifier.

## Keywords

None

## Version History

6.2	Introduced
-----	------------

## See Also

[H5S\\_CREATE\\_SIMPLE](#), [H5S\\_SET\\_EXTENT\\_SIMPLE](#)

# H5S\_SET\_EXTENT\_SIMPLE

[Syntax](#) | [Arguments](#) | [Keywords](#) | [Version History](#) | [See Also](#)

The H5S\_SET\_EXTENT\_SIMPLE procedure sets or resets the extent of a dataspace.

## Syntax

```
H5S_SET_EXTENT_SIMPLE, Dataspace_id, Dimensions  
[,MAX_DIMENSIONS=vector]
```

## Arguments

### Dataspace\_id

An integer giving the dataspace identifier.

### Dimensions

An integer array or scalar giving the size of each array dimension. The number of elements in Dimensions defines the number of dimensions in the resulting array datatype.

---

#### Note

The values specified in the MAX\_DIMENSIONS keyword should be equal to or greater than the corresponding values of the *Dimensions* argument.

---

---

#### Note

The Dimensions argument should be specified in IDL column-major order. Internally, the dimensions will be reversed to match HDF5/C row-major order.

---

## Keywords

### MAX\_DIMENSIONS

A vector containing the maximum dimensions for the dataspace. MAX\_DIMENSIONS must have the same number of elements as the Dimensions argument. If MAX\_DIMENSIONS is omitted then the maximum dimensions are set to Dimensions. You can use a value of -1 in MAX\_DIMENSIONS to indicate an unlimited dimension.

## Version History

6.2	Introduced
-----	------------

## See Also

[H5S\\_CREATE\\_SIMPLE](#), [H5S\\_SET\\_EXTENT\\_NONE](#)

# H5T\_ARRAY\_CREATE

The `H5T_ARRAY_CREATE` function creates an array datatype object.

## Syntax

*Result* = `H5T_ARRAY_CREATE(Datatype_id, Dimensions)`

## Return Value

The *Result* gives the identifier of the new datatype. The datatype identifier returned from this function should be released with `H5T_CLOSE`.

## Arguments

### Datatype\_id

An integer giving the datatype identifier of the datatype of each element in the resulting array.

### Dimensions

An integer array giving the size of each array dimension. The number of elements in `Dimensions` defines the number of dimensions in the resulting array datatype.

### Note

---

The `Dimensions` argument should be specified in IDL column-major order. Internally, the dimensions will be reversed to match HDF5/C row-major order.

---

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).



## Version History

6.2	Introduced
-----	------------

## See Also

[H5T\\_IDL\\_CREATE](#), [H5T\\_REFERENCE\\_CREATE](#)

# H5T\_CLOSE

The H5T\_CLOSE procedure releases the specified datatype's identifier and releases resources used by it. After this routine is used, the datatype's identifier is no longer available until the H5T\_OPEN routine is used again to specify that datatype.

## Syntax

H5T\_CLOSE, *Datatype\_id*

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be closed.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_OPEN](#)

# H5T\_COMMIT

The H5T\_COMMIT procedure commits a transient datatype to a file, creating a new named datatype.

**Note**

A named datatype can be shared by objects within the same HDF5 file, but not by objects in other files.

## Syntax

H5T\_COMMIT, *Loc\_id*, *Name*, *Datatype\_id*

## Arguments

**Loc\_id**

An integer giving the identifier of a file or group.

**Name**

The name of the new datatype.

**Datatype\_id**

An integer giving the identifier of the datatype to commit.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5T\\_COMMITTED](#), [H5T\\_IDL\\_CREATE](#)

# H5T\_COMMITTED

The H5T\_COMMITTED function determines whether a datatype is a named datatype or a transient type.

## Syntax

*Result* = H5T\_COMMITTED(*Datatype\_id*)

## Return Value

Returns 1 if the datatype is named and 0 if the datatype is transient.

## Arguments

### Datatype\_id

An integer representing the datatyped identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_COMMIT](#)

# H5T\_COMPOUND\_CREATE

The H5T\_COMPOUND\_CREATE function creates a compound datatype object. See “[Compound Datatypes](#)” on page 124 for a discussion of compound datatypes.

## Syntax

*Result* = H5T\_COMPOUND\_CREATE(*Datatype\_id*, *Name*)

## Return Value

Returns a long integer containing the identifier of the new compound datatype.

### Note

Datatype identifiers created by this function should be released with H5T\_CLOSE.

## Arguments

### Datatype\_id

A long integer or array of long integers containing the datatype identifiers to use when creating the compound datatype. The number of elements in *Datatype\_id* must match the number of elements in *Name*.

### Name

A scalar string or string array containing the names to use when creating the compound datatype. The number of elements in *Name* must match the number of elements in *Datatype\_id*.

## Keywords

None

## Example

```
dt1 = H5T_ENUM_CREATE()  
H5T_ENUM_SET_DATA, dt1, ['Radar_1', 'Radar_2'], [1, 2]  
dt2 = H5T_IDL_CREATE(1ul)  
dt = H5T_COMPOUND_CREATE([dt1, dt2], ['Radar_Id', 'Ctrl_Num'])
```

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ARRAY\\_CREATE](#), [H5T\\_IDL\\_CREATE](#), [H5T\\_CLOSE](#)

# H5T\_COPY

The H5T\_COPY function copies an existing datatype. The returned type is transient and unlocked.

## Syntax

*Result* = H5T\_COPY(*Datatype\_id*)

## Return Value

Returns the datatype's identifier number. This identifier can be released with the H5T\_CLOSE procedure.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be copied.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_CLOSE](#), [H5T\\_OPEN](#)



# H5T\_ENUM\_CREATE

The H5T\_ENUM\_CREATE function creates an enumeration datatype object.

---

**Note**

Name/value pairs must be assigned to the datatype *before* it is used to create a dataset. The dataset stores the state of the datatype at the time the dataset is created; additional changes to the datatype will not be reflected in the dataset.

---

See “[Enumeration Datatypes](#)” on page 127 for a discussion of enumeration datatypes.

## Syntax

*Result* = H5T\_ENUM\_CREATE()

## Return Value

Returns a long integer containing the identifier of the new enumeration datatype.

---

**Note**

Datatype identifiers created by this function should be released with H5T\_CLOSE.

---

## Arguments

None

## Keywords

None

## Example

See “[Enumeration Datatypes](#)” on page 127 for an example using this routine.

## Version History

---

6.3	Introduced
-----	------------

---

## See Also

[H5T\\_ENUM\\_INSERT](#), [H5T\\_CLOSE](#)

# H5T\_ENUM\_GET\_DATA

The `H5T_ENUM_GET_DATA` function retrieves the name/value pairs from an enumeration datatype object.

This routine is written in the IDL language. Its source code can be found in the file `h5t_enum_get_data.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

*Result* = `H5T_ENUM_GET_DATA(Datatype_id)`

## Return Value

Returns an array of `IDL_H5_ENUM` structures. Each structure has two fields:

Name	A string containing the name of the member
Value	The value of the corresponding member

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype for which the data is desired.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_ENUM\\_INSERT](#), [H5T\\_ENUM\\_SET\\_DATA](#)

# H5T\_ENUM\_INSERT

The H5T\_ENUM\_INSERT procedure inserts a new member into an existing enumeration datatype.

## Syntax

H5T\_ENUM\_INSERT, *Datatype\_id*, *Name*, *Value*

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype to which the new member will be added.

### Name

A scalar string containing the name of the member to be added.

### Value

A scalar integer giving the value of the member to be added.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#)

# H5T\_ENUM\_NAMEOF

The H5T\_ENUM\_NAMEOF function retrieves the name of a member of an enumeration datatype corresponding to the specified value.

## Syntax

*Result* = H5T\_ENUM\_NAMEOF(*Datatype\_id*, *Value*)

## Return Value

Returns a string containing the name that corresponds to the specified value.

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype.

### Value

An integer containing the value of the datatype member for which the name should be returned.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_ENUM\\_VALUEOF](#)

# H5T\_ENUM\_SET\_DATA

The `H5T_ENUM_SET_DATA` procedure sets all the name/value pairs on an enumeration datatype object.

This routine is written in the IDL language. Its source code can be found in the file `h5t_enum_set_data.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

`H5T_ENUM_SET_DATA, Datatype_id, Data, Values`

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype.

### Data

A string array or array of named structures:

- If *Data* is a string array, it contains the *names* of the members of the enumeration datatype, and the *Values* argument is required.
- If *Data* is an array of named structures, the *Values* argument is ignored. The structures that make up *Data* must be of type `IDL_H5_ENUM`, which has the following signature:

```
{IDL_H5_ENUM, NAME:'', VALUE:0}
```

### Values

An integer array containing the *values* of the members of the enumeration datatype. The *Values* array must have the same number of elements as the string array specified by *Data*. This argument is ignored if *Data* is an array of structures.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_ENUM\\_GET\\_DATA](#), [H5T\\_ENUM\\_INSERT](#)

# H5T\_ENUM\_VALUEOF

The H5T\_ENUM\_VALUEOF function retrieves the value of a member of an enumeration datatype corresponding to the specified name.

## Syntax

*Result* = H5T\_ENUM\_VALUEOF(*Datatype\_id*, *Name*)

## Return Value

Returns an integer containing the value that corresponds to the specified name.

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype.

### Name

A string containing the name of the datatype member for which the value should be returned.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_ENUM\\_NAMEOF](#)



# H5T\_ENUM\_VALUES\_TO\_NAMES

The `H5T_ENUM_VALUES_TO_NAMES` function converts values to the corresponding names of an enumeration datatype.

This routine is written in the IDL language. Its source code can be found in the file `h5t_enum_values_to_names.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

*Result* = `H5T_ENUM_VALUES_TO_NAMES`(*Datatype\_id*, *Values*)

## Return Value

Returns a string array with the same number of elements as *Values*. Each element in *Result* will be the name corresponding to the value in *Values*. If an individual value specified in *Values* is not present in the enumeration datatype, the corresponding element in *Result* will be a null string.

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype.

### Values

An integer array of values for which names are desired.

### Note

---

The [H5D\\_READ](#) function returns an array suitable for use as the *Values* argument.

---

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_NAMEOF](#)

# H5T\_EQUAL

The `H5T_EQUAL` function determines whether two datatype identifiers refer to the same datatype.

## Syntax

*Result* = `H5T_EQUAL(Datatype_id1, Datatype_id2)`

## Return Value

Returns 1 if the identifiers refer to the same datatype and 0 if they do not.

## Arguments

### Datatype\_id1

An integer representing the first datatype identifier.

### Datatype\_id2

An integer representing the second datatype identifier.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_COPY](#)

# H5T\_GET\_ARRAY\_DIMS

The H5T\_GET\_ARRAY\_DIMS function returns the dimension sizes for an array datatype object.

## Syntax

*Result* = H5T\_GET\_ARRAY\_DIMS(*Datatype\_id* [, [PERMUTATIONS](#)=*variable*])

## Return Value

Returns a vector containing the dimension sizes.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

### PERMUTATIONS

Set this keyword to a named variable in which to return the dimension permutations (C versus FORTRAN).

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_ARRAY\\_NDIMS](#)

# H5T\_GET\_ARRAY\_NDIMS

The H5T\_GET\_ARRAY\_NDIMS function determines the number of dimensions (or rank) of an array datatype object.

## Syntax

*Result* = H5T\_GET\_ARRAY\_NDIMS(*Datatype\_id*)

## Return Value

Returns the number of dimensions.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_ARRAY\\_DIMS](#)

# H5T\_GET\_CLASS

The H5T\_GET\_CLASS function returns the datatype's class.

## Syntax

```
Result = H5T_GET_CLASS(Datatype_id)
```

## Return Value

Returns a string containing the datatype's class. Possible return values include:

- 'H5T\_INTEGER'
- 'H5T\_FLOAT'
- 'H5T\_TIME'
- 'H5T\_STRING'
- 'H5T\_BITFIELD'
- 'H5T\_OPAQUE'
- 'H5T\_COMPOUND'
- 'H5T\_REFERENCE'
- 'H5T\_ENUM'
- 'H5T\_VLEN'
- 'H5T\_ARRAY'
- 'H5T\_NO\_CLASS'

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_SIZE](#), [H5T\\_GET\\_SUPER](#)

# H5T\_GET\_CSET

The H5T\_GET\_CSET function returns the character set type of a string datatype.

## Syntax

*Result* = H5T\_GET\_CSET(*Datatype\_id*)

## Return Value

Returns a string containing the character set type. Possible values are:

- 'ASCII' — US ASCII
- 'ERROR'

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------



# H5T\_GET\_EBIAS

The H5T\_GET\_EBIAS function returns the exponent bias of a floating-point type.

## Syntax

*Result* = H5T\_GET\_EBIAS(*Datatype\_id*)

## Return Value

Returns the exponent bias.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_FIELDS](#)

# H5T\_GET\_FIELDS

The H5T\_GET\_FIELDS function retrieves information about the positions and sizes of bit fields within a floating-point datatype.

## Syntax

*Result* = H5T\_GET\_FIELDS(*Datatype\_id*)

## Return Value

Returns a structure named H5T\_GET\_FIELDS containing the following tags:

### TYPE\_ID

The datatype's identifier *Datatype\_id*.

### SIGN\_POS

The position of the floating-point sign bit.

### EXP\_POS

The bit position of the exponent.

### EXP\_SIZE

The size of the exponent in bits.

### MAN\_POS

The bit position of the mantissa.

### MAN\_SIZE

The size of the mantissa in bits.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_EBIAS](#), [H5T\\_GET\\_INPAD](#), [H5T\\_GET\\_NORM](#), [H5T\\_GET\\_OFFSET](#),  
[H5T\\_GET\\_ORDER](#), [H5T\\_GET\\_PAD](#), [H5T\\_GET\\_PRECISION](#)

# H5T\_GET\_INPAD

The H5T\_GET\_INPAD function returns the padding method for unused internal bits within a floating-point datatype.

## Syntax

*Result* = H5T\_GET\_INPAD(*Datatype\_id*)

## Return Value

Returns the padding method. Possible values are:

- 0 — Background set to zeroes
- 1 — Background set to ones
- 2 — Background left unchanged

## Arguments

### Datatype\_id

An integer representing the datatype identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_FIELDS](#)

# H5T\_GET\_MEMBER\_CLASS

The H5T\_GET\_MEMBER\_CLASS function returns the datatype class of a compound datatype member.

## Syntax

*Result* = H5T\_GET\_MEMBER\_CLASS(*Datatype\_id*, *Member*)

## Return Value

Returns a string containing the datatype class. Possible values are:

- 'H5T\_INTEGER'
- 'H5T\_FLOAT'
- 'H5T\_TIME'
- 'H5T\_STRING'
- 'H5T\_BITFIELD'
- 'H5T\_OPAQUE'
- 'H5T\_COMPOUND'
- 'H5T\_REFERENCE'
- 'H5T\_ENUM'
- 'H5T\_VLEN'
- 'H5T\_ARRAY'
- 'H5T\_NO\_CLASS'

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

### Member

An integer representing the member index, starting at zero.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5T\\_GET\\_MEMBER\\_NAME](#), [H5T\\_GET\\_MEMBER\\_OFFSET](#),  
[H5T\\_GET\\_MEMBER\\_TYPE](#), [H5T\\_GET\\_NMEMBERS](#)

# H5T\_GET\_MEMBER\_INDEX

The H5T\_GET\_MEMBER\_INDEX function retrieves the index of a specified member of a compound or enumeration datatype.

## Syntax

*Result* = H5T\_GET\_MEMBER\_INDEX(*Datatype\_id*, *Field\_name*)

## Return Value

Returns an integer containing the index of the specified datatype member.

## Arguments

### Datatype\_id

A long integer containing the identifier of the compound or enumeration datatype.

### Field\_name

A string containing the name of the field or element for which the index will be returned.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_GET\\_MEMBER\\_VALUE](#)

# H5T\_GET\_MEMBER\_NAME

The H5T\_GET\_MEMBER\_NAME function retrieves the name of a compound or enumeration datatype member.

## Syntax

*Result* = H5T\_GET\_MEMBER\_NAME(*Datatype\_id*, *Member*)

## Return Value

Returns a string containing the name of the specified datatype member.

## Arguments

### Datatype\_id

A long integer containing the identifier of the compound or enumeration datatype.

### Member

An integer containing the member index. Member indices are zero-based.

## Keywords

None

## Version History

5.6	Introduced
6.3	Added support for enumeration datatypes

## See Also

[H5T\\_GET\\_MEMBER\\_CLASS](#), [H5T\\_GET\\_MEMBER\\_OFFSET](#),  
[H5T\\_GET\\_MEMBER\\_TYPE](#), [H5T\\_GET\\_NMEMBERS](#)



# H5T\_GET\_MEMBER\_OFFSET

The `H5T_GET_MEMBER_OFFSET` function returns the byte offset of a field within a compound datatype.

## Syntax

*Result* = `H5T_GET_MEMBER_OFFSET(Datatype_id, Member)`

## Return Value

Returns an integer representing the byte offset.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

### Member

An integer representing the member index, starting at zero.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_MEMBER\\_CLASS](#), [H5T\\_GET\\_MEMBER\\_NAME](#),  
[H5T\\_GET\\_MEMBER\\_TYPE](#), [H5T\\_GET\\_NMEMBERS](#)

# H5T\_GET\_MEMBER\_TYPE

The `H5T_GET_MEMBER_TYPE` function returns the datatype identifier for a specified member within a compound datatype.

## Syntax

```
Result = H5T_GET_MEMBER_TYPE(Datatype_id, Member)
```

## Return Value

Returns the datatype identifier. This identifier should be closed using [H5T\\_CLOSE](#).

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

### Member

An integer representing the member index, starting at zero.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_MEMBER\\_CLASS](#), [H5T\\_GET\\_MEMBER\\_NAME](#),  
[H5T\\_GET\\_MEMBER\\_OFFSET](#), [H5T\\_CLOSE](#), [H5T\\_GET\\_NMEMBERS](#)

# H5T\_GET\_MEMBER\_VALUE

The H5T\_GET\_MEMBER\_VALUE function retrieves the value of an enumeration datatype member.

## Syntax

*Result* = H5T\_GET\_MEMBER\_VALUE(*Datatype\_id*, *Member*)

## Return Value

Returns an integer containing the value of the specified datatype member.

## Arguments

### Datatype\_id

A long integer containing the identifier of the enumeration datatype.

### Member

An integer containing the member index. Member indices are zero-based.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ENUM\\_CREATE](#), [H5T\\_GET\\_MEMBER\\_INDEX](#)

# H5T\_GET\_NMEMBERS

The H5T\_GET\_NMEMBERS function returns the number of fields in a compound datatype.

## Syntax

*Result* = H5T\_GET\_NMEMBERS(*Datatype\_id*)

## Return Value

Returns the number of fields.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_MEMBER\\_CLASS](#), [H5T\\_GET\\_MEMBER\\_NAME](#),  
[H5T\\_GET\\_MEMBER\\_OFFSET](#), [H5T\\_GET\\_MEMBER\\_TYPE](#)

# H5T\_GET\_NORM

The H5T\_GET\_NORM function returns the mantissa normalization of a floating-point datatype.

## Syntax

*Result* = H5T\_GET\_NORM(*Datatype\_id*)

## Return Value

Returns a string containing the mantissa normalization. Possible values are:

- ‘IMPLIED’ — Most-significant bit of mantissa not stored, always 1
- ‘MSBSET’ — Most-significant bit of mantissa is always 1
- ‘NORM’ — Mantissa is not normalized
- ‘ERROR’

## Arguments

### Datatype\_id

An integer representing the datatype’s identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_FIELDS](#)

# H5T\_GET\_OFFSET

The `H5T_GET_OFFSET` function returns the bit offset of the first significant bit in an atomic datatype. The offset is the number of bits of padding that follows the significant bits (for big endian) or precedes the significant bits (for little endian).

## Syntax

*Result* = `H5T_GET_OFFSET(Datatype_id)`

## Return Value

Returns the bit offset.

## Arguments

### **Datatype\_id**

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_FIELDS](#)

# H5T\_GET\_ORDER

The H5T\_GET\_ORDER function returns the byte order of an atomic datatype.

## Syntax

*Result* = H5T\_GET\_ORDER(*Datatype\_id*)

## Return Value

Returns a string representing the byte order. Possible values are:

- 'LE' — Little endian
- 'BE' — Big endian
- 'VAX' — VAX mixed ordering
- 'NONE'
- 'ERROR'

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_INPAD](#), [H5T\\_GET\\_PAD](#), [H5T\\_GET\\_PRECISION](#)

# H5T\_GET\_PAD

The `H5T_GET_PAD` function returns the padding method of the least significant bit (*lsb*) and most significant bit (*msb*) of an atomic datatype.

## Syntax

*Result* = `H5T_GET_PAD(Datatype_id)`

## Return Value

Returns a two-element vector [*lsb*, *msb*]. Possible values are:

- 0 — Background set to zeroes
- 1 — Background set to ones
- 2 — Background left unchanged.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_INPAD](#), [H5T\\_GET\\_ORDER](#), [H5T\\_GET\\_PRECISION](#)



# H5T\_GET\_PRECISION

The `H5T_GET_PRECISION` function returns the precision in bits of an atomic datatype. The precision is the number of significant bits which, unless padded, is 8 times larger than the byte size from [H5T\\_GET\\_CSET](#).

## Syntax

*Result* = `H5T_GET_PRECISION(Datatype_id)`

## Return Value

Returns the bit precision, or 0 if the datatype is not atomic.

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_INPAD](#), [H5T\\_GET\\_ORDER](#), [H5T\\_GET\\_PAD](#), [H5T\\_GET\\_SIZE](#)

# H5T\_GET\_SIGN

The H5T\_GET\_SIGN function returns the sign type for an integer datatype.

## Syntax

*Result* = H5T\_GET\_SIGN(*Datatype\_id*)

## Return Value

Returns the sign type. Possible values are:

- -1 — Error
- 0 — Unsigned integer type
- 1 — Two's complement signed integer type

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_ORDER](#), [H5T\\_GET\\_PAD](#), [H5T\\_GET\\_PRECISION](#)

# H5T\_GET\_SIZE

The H5T\_GET\_SIZE function returns the size of a datatype in bytes.

## Syntax

*Result* = H5T\_GET\_SIZE(*Datatype\_id*)

## Return Value

Represents the size (in bytes) of the first element found within the datatype.

### Note

---

When H5T\_GET\_SIZE is given a datatype containing a string, it will return the number of characters + 1.

---

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5T\\_GET\\_CLASS](#), [H5T\\_GET\\_SUPER](#)

# H5T\_GET\_STRPAD

The H5T\_GET\_STRPAD function returns the padding method for a string datatype.

## Syntax

*Result* = H5T\_GET\_STRPAD(*Datatype\_id*)

## Return Value

Returns a string containing the padding method. Possible values are:

- 'NULLTERM' — Null terminate (like C)
- 'NULLPAD' — Pad with zeroes
- 'SPACEPAD' — Pad with spaces (like FORTRAN)
- 'ERROR'

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_CSET](#), [H5T\\_GET\\_SIZE](#)

# H5T\_GET\_SUPER

The `H5T_GET_SUPER` function returns the base datatype from which a datatype is derived.

## Syntax

*Result* = `H5T_GET_SUPER(Datatype_id)`

## Return Value

Returns the base datatype's identifier number. This identifier can be released with the [H5T\\_CLOSE](#).

## Arguments

### Datatype\_id

An integer representing the datatype's identifier to be queried.

## Keywords

None

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_GET\\_CLASS](#), [H5T\\_GET\\_SIZE](#)

# H5T\_GET\_TAG

The `H5T_GET_TAG` function retrieves a tag string from an opaque data type. See “[Opaque Datatypes](#)” on page 125 for a discussion of opaque datatypes.

## Syntax

*Result* = `H5T_GET_TAG(Datatype_id)`

## Return Value

Returns a string containing the tag associated with the specified opaque datatype, or a null string if no tag exists.

## Arguments

### `Datatype_id`

A long integer containing the identifier of the opaque datatype.

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_IDL\\_CREATE](#), [H5T\\_SET\\_TAG](#)

# H5T\_IDL\_CREATE

The H5T\_IDL\_CREATE function creates a datatype object based on the IDL type of the supplied data.

## Syntax

```
Result = H5T_IDL_CREATE(Data [,MEMBER_NAMES=vector] [, /OPAQUE])
```

## Return Value

Returns a long integer containing the identifier of the new datatype.

### Note

---

Datatype identifiers created by this function should be released with H5T\_CLOSE.

---

## Arguments

### Data

An IDL variable containing the type of data that will be used by the resulting datatype. If a structure is passed in a compound datatype will be created based on the fields of the structure. The following table shows how IDL data types are converted to HDF5 datatypes. Pointers, complex numbers, and object references cannot be written to HDF5 datatypes.

IDL type	HDF5 Datatype
Byte	H5T_NATIVE_UINT8
Integer	H5T_NATIVE_INT16
Unsigned integer	H5T_NATIVE_UINT16
Long integer	H5T_NATIVE_INT32
Unsigned long integer	H5T_NATIVE_UINT32
64-bit Integer	H5T_NATIVE_INT64
Unsigned 64-bit integer	H5T_NATIVE_UINT64

Table 3-15: IDL Types and Corresponding HDF5 Datatypes

IDL type	HDF5 Datatype
Floating point	H5T_NATIVE_FLOAT
Double-precision floating	H5T_NATIVE_DOUBLE
String	H5T_C_S1
Structure	(Member datatypes)

Table 3-15: IDL Types and Corresponding HDF5 Datatypes (Continued)

### Note

If the data is an array, the datatype is constructed from the first element in the array. If an HDF5 array datatype is desired, then the datatype returned in this routine should be passed into `H5T_ARRAY_CREATE`. Using the first element could affect the size of a string datatype. All elements of a string datatype will have the same length, or number of characters. Strings smaller than the datatype length will be stored appropriately, but strings longer than the datatype length will be truncated. The size of the returned datatype will include a null termination character and thus will be one more than the number of characters in the string. For example:

```
datatype_id = H5T_IDL_CREATE('dog')
```

This produces a datatype with a size of 4. A dataset created with this datatype will only store up to 4 characters per element of the data being written. The following:

```
datatype_id = H5T_IDL_CREATE(['dog', 'dragon'])
```

will still produce a datatype with a size of 4 because the first element of the array is used when creating the datatype. When creating a string datatype the longest string needed should be used. Note that an excessively long string could result in a bloated file.

## Keywords

### MEMBER\_NAMES

A string vector giving the name of each member of the compound datatype. This keyword is ignored if *Data* is not an IDL structure. If *Data* is an IDL structure and this keyword is not provided, the member names will be constructed from the field names in the structure, converting all letters to uppercase and all non-alphanumeric



characters to underscores. If the number of elements in `MEMBER_NAMES` is less than the number of elements in the structure, field names will be used for member names where needed. If the number of elements in `MEMBER_NAMES` is greater than the number of elements in the structure, the extra string values will be ignored.

Elements of `MEMBER_NAMES` are assigned to fields in a depth-first, left-to-right traversal of the structure. For example, if *Data* contains a structure that looks like:

```
{ a:01, b:{d:01, e:01}, c:01 }
```

and `MEMBER_NAMES` contains:

```
[ 'cat', 'dog', 'dragon', 'emu' ]
```

then the resulting compound datatype uses the name 'cat' to refer to the datatype created from field a, 'dog' to refer to field b, 'dragon' to refer to field d, and 'emu' to refer to field e. Since only four names are provided, the compound datatype uses the name 'C' to refer to field c.

## OPAQUE

Set this keyword to create an opaque datatype. The size of the datatype will be determined by the size of the *Data* argument.

### Note

Opaque datatypes store data as a simple string of bytes, regardless of the form the data is in when written to the datatype. An opaque datatype is always a single element, regardless of the number of bytes. See “[Opaque Datatypes](#)” on page 125 for additional information.

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
6.3	Added support for opaque datatypes and OPAQUE keyword

## See Also

[H5T\\_ARRAY\\_CREATE](#), [H5T\\_CLOSE](#), [H5T\\_REFERENCE\\_CREATE](#)

# H5T\_IDLTYPE

The H5T\_IDLTYPE function returns the IDL type code corresponding to a datatype.

---

**Note**

This function is not part of the standard HDF5 interface, but is provided as a programming convenience.

---

## Syntax

```
Result = H5T_IDLTYPE(Datatype_id  
[, ARRAY_DIMENSIONS=variable][, STRUCTURE=variable])
```

## Return Value

The *Result* gives the IDL type code.

---

**Note**

For a list of IDL type codes and their definitions, see “IDL Type Codes and Names” in the *IDL Reference Guide* manual under the SIZE function.

---

## Arguments

### Datatype\_id

An integer giving the datatype identifier for which to return the IDL type code.

## Keywords

### ARRAY\_DIMENSIONS

Set this keyword to a named variable in which to return a vector containing the array dimensions, if the datatype is an array. If the datatype is not an array, then a scalar value of 0 is returned.

### STRUCTURE

Set this keyword to a named variable in which to return the IDL structure definition, if the datatype is a compound datatype. If the datatype is not compound, then a scalar value of 0 is returned.

## Version History

5.6	Introduced
-----	------------

## See Also

[H5T\\_MEMTYPE](#)

# H5T\_INSERT

The H5T\_INSERT procedure adds a new member to the end of a compound datatype.

## Syntax

H5T\_INSERT, *Datatype\_id*, *Name*, *Field\_id*

## Arguments

### Datatype\_id

An integer giving the identifier of the compound datatype to modify.

### Name

Name of the field to insert.

### Field\_id

An integer giving the identifier of the datatype of the field to insert.

## Keywords

None

## Example

See the example under [H5F\\_CREATE](#).

## Version History

---

6.2	Introduced
-----	------------

---

## See Also

[H5T\\_IDL\\_CREATE](#)

# H5T\_MEMTYPE

The H5T\_MEMTYPE function returns the native memory datatype corresponding to a file datatype.

---

**Note**

This function is not part of the standard HDF5 interface, but is provided as a programming convenience.

---

## Syntax

*Result* = H5T\_MEMTYPE(*Datatype\_id*)

## Return Value

The *Result* gives the datatype identifier. If the file datatype is not immutable, then the memory datatype identifier should be closed using H5T\_CLOSE.

---

**Note**

For a list of IDL type codes and their definitions, see “[IDL Type Codes and Names](#)” in the *IDL Reference Guide* manual under the SIZE function.

---

## Arguments

### Datatype\_id

An integer giving the file datatype identifier for which to return the memory datatype.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5T\\_IDLTYPE](#)

# H5T\_OPEN

The H5T\_OPEN function opens a named datatype.

## Syntax

*Result* = H5T\_OPEN(*Loc\_id*, *Name*)

## Return Value

Returns the datatype's identifier number. This identifier can be released with the [H5T\\_CLOSE](#).

## Arguments

### Loc\_id

An integer representing the identifier of the file or group containing the datatype.

### Name

A string representing the name of the datatype to be accessed.

## Keywords

None

## Version History

---

5.6	Introduced
-----	------------

---

## See Also

[H5T\\_CLOSE](#)

# H5T\_REFERENCE\_CREATE

The `H5T_REFERENCE_CREATE` function creates a reference datatype object.

## Syntax

*Result* = `H5T_REFERENCE_CREATE`([/[REGION](#)])

## Return Value

The *Result* is either an integer (if an object reference is created) or a structure (if a dataspace region reference is created) giving the identifier of the new datatype. The datatype identifier returned from this function should be released with `H5T_CLOSE`.

## Arguments

None

## Keywords

### REGION

If set a dataspace region reference will be created. The default is to create an object reference.

## Example

See the example under [H5F\\_CREATE](#).

## Version History

6.2	Introduced
-----	------------

## See Also

[H5T\\_ARRAY\\_CREATE](#), [H5T\\_IDL\\_CREATE](#), [H5T\\_CLOSE](#)



# H5T\_SET\_TAG

The H5T\_SET\_TAG procedure sets a tag string on an opaque data type. See “[Opaque Datatypes](#)” on page 125 for a discussion of opaque datatypes.

## Syntax

```
H5T_SET_TAG(Datatype_id, Tag)
```

## Arguments

### Datatype\_id

A long integer containing the identifier of the opaque datatype.

### Tag

A string containing the new tag for the opaque datatype.

### Note

---

Tag strings can contain a maximum of 255 characters.

---

## Keywords

None

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_GET\\_TAG](#), [H5T\\_IDL\\_CREATE](#)

# H5T\_STR\_TO\_VLEN

The H5T\_STR\_TO\_VLEN function converts an IDL string array to an IDL\_H5\_VLEN array of strings.

This routine is written in the IDL language. Its source code can be found in the file `h5t_str_to_vlen.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

```
Result = H5T_STR_TO_VLEN(Array [, /NO_COPY])
```

## Return Value

Returns an array of named structures of type IDL\_H5\_VLEN, each with a single field PDATA containing a pointer to a scalar string.

## Arguments

### Array

A string array to be converted to an HDF5 variable length array.

## Keywords

### NO\_COPY

Set this keyword to delete the contents of *Array* after creating the corresponding array of IDL\_H5\_VLEN structures. The default is to leave a copy of the data in *Array*.

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_VLEN\\_TO\\_STR](#), [H5T\\_VLEN\\_CREATE](#)

# H5T\_VLEN\_CREATE

The H5T\_VLEN\_CREATE function creates a variable length array datatype object. See “[Variable Length Array Datatypes](#)” on page 129 for a discussion of variable length array datatypes.

## Syntax

```
Result = H5T_VLEN_CREATE(Datatype_id)
```

## Return Value

Returns a long integer containing the identifier of the new variable length array datatype.

### Note

---

Datatype identifiers created by this function should be released with H5T\_CLOSE.

---

## Arguments

### Datatype\_id

A long integer containing the datatype identifier to use when creating the variable length array datatype. All elements of the array will be of this datatype.

## Keywords

None

## Example

See “[Variable Length Array Datatypes](#)” on page 129 for an example using this routine.

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_ARRAY\\_CREATE](#), [H5T\\_IDL\\_CREATE](#), [H5T\\_CLOSE](#)

# H5T\_VLEN\_TO\_STR

The H5T\_VLEN\_TO\_STR function converts an IDL\_H5\_VLEN array of strings to an IDL string array.

This routine is written in the IDL language. Its source code can be found in the file `h5t_vlen_to_str.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

```
Result = H5T_VLEN_TO_STR(Array [, /PTR_FREE])
```

## Return Value

Returns an IDL string array.

## Arguments

### Array

An array of named structures of type IDL\_H5\_VLEN, each with a PDATA field pointing to a scalar string.

## Keywords

### PTR\_FREE

Set this keyword to free the pointers in the input array of IDL\_H5\_VLEN structures. The default is to not free the pointers.

## Version History

6.3	Introduced
-----	------------

## See Also

[H5T\\_STR\\_TO\\_VLEN](#), [H5T\\_VLEN\\_CREATE](#)





# Chapter 4

# Hierarchical Data Format

The following topics are covered in this appendix:

---

Overview of the HDF Format .....	312	HDF Scientific Dataset ID Numbers .....	317
HDF Interfaces .....	313	Alphabetical Listing of HDF Routines ...	322
Creating HDF Files .....	315		

# Overview of the HDF Format

The Hierarchical Data Format (HDF) is a multi-object file format that facilitates the transfer of various types of data between machines and operating systems. HDF is a product of the National Center for Supercomputing Applications (NCSA). HDF is designed to be flexible, portable, self-describing and easily extensible for future enhancements or compatibility with other standard formats. The HDF library contains interfaces for storing and retrieving images and multi-dimensional scientific data. This version of IDL supports HDF 4.1r5.

**Note**

---

On the AIX platform, the HDF library supports version 4.1r3.

---

IDL's HDF routines all begin with the prefix "HDF\_".

Further information about HDF can be found on the World Wide Web at the HDF Information Server:

<http://hdf.ncsa.uiuc.edu>

Alternately, you can send e-mail to:

[hdfhelp@ncsa.uiuc.edu](mailto:hdfhelp@ncsa.uiuc.edu).



# HDF Interfaces

There are two basic interfaces to HDF files: the single-file application interface and the multiple-file application interface. These interfaces support eight different types (or “models”) of data access. The table below lists the different models and the names of the IDL routines that access those models. Each model is described in more detail after the table.

Model	IDL Routine Name Prefix
24-bit raster	HDF_DF24_
annotation data	HDF_DFAN_
palette data	HDF_DFP_
8-bit raster	HDF_DFR8_
scientific data	HDF_SD_
multi-file scientific data	HDF_SD_
VData	HDF_VD_
VGroup	HDF_VG_

*Table 4-1: Data Access Models and Routine Prefixes*

## Single File Application Interfaces

In this mode, access is limited to one file at a time. This interface supports the 8-bit raster, 24-bit raster, palette, scientific data, and annotation models. The interfaces are described in more detail after the table.

- 8-bit Raster Model: The HDF\_DFR8\_ routines access 8-bit images.
- Palette Model: The HDF\_DFP\_ routines are used to work with the HDF\_DFR8\_ routines to manipulate palettes associated with 8-bit HDF images.
- 24-bit Raster Model: The HDF\_DFR24\_ routines access 24-bit images.
- Scientific Data Models (SDs): Used to manipulate arrays of arbitrary dimension and type. Under this model, an array accompanied by a record of its data type, dimensions and descriptors is called a Scientific Dataset (SD).

- **Annotation Model:** The annotation model is used to describe the contents of the file through such items as labels, data descriptors, and dimension scales.
- **Vdata Model:** This interface allows for the creation of customized tables. Each table consists of a series of Vdata records whose values are stored in fixed length fields. As described in more detail in the Vdata example below, a Vdata can contain three kinds of identifying information: a Vdata name, Vdata Class, and multiple Vdata field names. The Vdata model is accessed through the routines that begin with the HDF\_VD\_ prefix.
- **Vgroup Model:** A collection of one or more data objects, Vdata sets, or Vgroups is known as a Vgroup. Each Vgroup can be given a Vgroup name and Vgroup class. The Vgroup model is accessed through the routines that begin with the HDF\_VG\_ prefix.

## Multi-File Application Interface

The HDF\_SD\_ routines allow operations on more than one file at a time. This multi-file interoperability is achieved through HDF's use of a modified version of the NetCDF library. IDL's interface to HDF's multi-file capability is the HDF\_SD\_SETTEXTFILE routine.

# Creating HDF Files

The following IDL commands should be used to create a new HDF file:

- `HDF_OPEN`: Call this procedure first to open an HDF file. The `CREATE` keyword must be set if you want to create a new file instead of opening an existing one.
- `HDF_DFAN_ADDFDS`: Optionally, add a file description.
- `HDF_DFAN_ADDFID`: Optionally, add a file annotation.

## Adding Data to an HDF File

The routines used to add data to an HDF file vary based on the interface model being used:

- To add an 8-bit image (with or without a palette), use `HDF_DFR8_ADDIMAGE` or `DFR8_PUTIMAGE`.
- To add a palette, use `HDF_DFP_ADDPAL` or `HDF_DFP_PUTPAL`.
- To add a 24-bit image, use `HDF_DF24_ADDIMAGE` or `HDF_DF24_PUTIMAGE`.
- To add a Multi-File Scientific Dataset, use the following commands:
  - `HDF_SD_CREATE` or `HDF_SD_SELECT` to create an SDS or select an existing one.
  - `HDF_SD_DIMSET` to set dimension information.
  - `HDF_SD_ATTRSET` to set attribute information.
  - `HDF_SD_SETINFO` to insert optional information about the data.
  - `HDF_SD_ADDDATA` to insert the data.
  - `HDF_SD_SETEXTFILE` to move the data to an external file (optional).
  - `HDF_SD_ENDACCESS` to end access to the SDS.
- To add a Vdata, use the following commands:
  - `HDF_VD_ATTACH` to get a Vdata identifier.
  - `HDF_VD_SETINFO` to write information about the Vdata (optional).
  - `HDF_VD_FDEFINE` to prepare non-trivial fields (optional).
  - `HDF_VD_WRITE` to write the Vdata.

- To add a Vdata to a Vgroup, use the following commands:
  - HDF\_VG\_ATTACH to get a Vgroup identifier.
  - HDF\_VG\_SETINFO to set the Vgroup name and class (optional).
  - HDF\_VG\_INSERT to add the Vdata to a Vgroup.
  - HDF\_VG\_DETACH to close the Vgroup.
  - HDF\_CLOSE to close the file.

## HDF Examples

### Example Code

---

Two example files that demonstrate the use of the HDF routines can be found in the `examples/doc/sdf` subdirectory of the IDL distribution. The file `hdf_info.pro` prints a summary of basic information about an HDF file. The file `hdf_rdwr.pro` creates a new HDF file and then reads the information back from that file.

---

## HDF Scientific Dataset ID Numbers

IDL's HDF\_SD\_ routines can accept two different types of ID numbers.

Documentation for these routines in the *IDL Reference Guide* refers to these ID numbers as the SDinterface\_id and SDdataset\_id arguments.

The SDinterface\_id is the Scientific Dataset interface ID. There is only one SDinterface\_id per HDF file. For each actual dataset used, you will also need an SDdataset\_id, which is the ID for the particular dataset.

Some routines, such as HDF\_SD\_ATTRFIND, accept either an SDinterface\_id or an SDdataset\_id. In these cases, the documentation refers to the ID as an SD\_id, meaning that either type of ID is accepted.

## IDL and HDF Data Types

HDF and IDL support many different data types. Many of the HDF routines allow you to perform a data type conversion “on the fly” by setting keywords such as FLOAT. When the data type desired is not explicitly specified, IDL uses the conversions shown in the following tables. Note that single-precision floating-point is the default data type and that the complex data type is not supported.

When writing IDL data to an HDF file, IDL data types are converted to the HDF data types shown in the following table:

IDL Data Type	HDF Data Type
BYTE	DFNT_UINT8 (IDL bytes are unsigned)
INT	DFNT_INT16
UINT	DFNT_UINT16
LONG	DFNT_INT32
ULONG	DFNT_UINT32
FLOAT	DFNT_FLOAT32
DOUBLE	DFNT_DOUBLE
STRING	DFNT_CHAR8

Table 4-2: Type Conversions when Writing IDL Data to an HDF File

When reading data from an HDF file, HDF data types are converted to the IDL data types shown in the following table:

HDF Data Type	IDL Data Type
DFNT_CHAR8	STRING
DFNT_UINT8	BYTE
DFNT_INT16	INT
DFNT_UINT16	UINT
DFNT_INT32	LONG
DFNT_UINT32	ULONG
DFNT_INT64	LONG
DFNT_UINT64	ULONG
DFNT_FLOAT32 or DFNT_NONE	FLOAT

*Table 4-3: Type Conversions when Reading HDF Data into IDL*

HDF type codes for the supported HDF data types are shown in the table below:

HDF Data Type	Type Code
DFNT_UCHAR	3
DFNT_CHAR	4
DFNT_FLOAT32	5
DFNT_FLOAT64	6
DFNT_INT8	20
DFNT_UINT8	21
DFNT_INT16	22
DFNT_UINT16	23
DFNT_INT32	24

*Table 4-4: HDF Data Type Codes*

HDF Data Type	Type Code
DFNT_UINT32	25
DFNT_INT64	26
DFNT_UINT64	27

*Table 4-4: HDF Data Type Codes (Continued)*

## Common HDF Tag Numbers

The following table lists common HDF tag numbers and their meanings.

Tag Number	Meaning
030	Version Identifier
100	File Identifier
101	File Description
102	Tag Identifier
103	Tag Description
104	Data Identifier Label
105	Data Identifier Annotation
106	Number Type
107	Machine Type
200	Obsolete
201	Obsolete
202	Obsolete
203	Obsolete
204	Obsolete
300	RIG Image Dimension
301	Raster Image Look Up Table (LUT)

*Table 4-5: Common HDF Tag Numbers*

<b>Tag Number</b>	<b>Meaning</b>
302	Raster Image
303	Compressed Raster Image
306	Raster Image Group (RIG)
307	RIG LUT Dimension
308	RIG Matte Dimension
309	Raster Image Matte Data
310	Raster Image Color Correction
311	Raster Image Color Format
312	Raster Image Aspect Ratio
400	Composite Image Descriptor
500	XY Position
602	Vector Image - Tek4014 Stream
603	Vector Image - Tek4105 Stream
701	SD Dimension Record
702	SD Data
703	SD Scales
704	SD Labels
705	SD Units
706	SD Formats
707	SD Max/Min
708	SD Coordinates
710	SD Link
720	SD Descriptor (NDG)
731	SD Calibration Information

*Table 4-5: Common HDF Tag Numbers (Continued)*



<b>Tag Number</b>	<b>Meaning</b>
732	SD Fill Value
1962	Vdata Description
1963	Vdata
1965	Vgroup

*Table 4-5: Common HDF Tag Numbers (Continued)*

# Alphabetical Listing of HDF Routines

The HDF routines are listed in the following section.

---

**Note**

The routines `HDF_BROWSER` and `HDF_READ`, introduced in IDL version 5.1, allow you to read HDF data files and import data into IDL using a graphical user interface. Using these two routines, you can avoid the need to use most of the rest of IDL's HDF interface. [HDF\\_BROWSER](#) and [HDF\\_READ](#) are discussed in the *IDL Reference Guide*.

---

`HDF_AN_ANNLEN`

`HDF_AN_ANNLIST`

`HDF_AN_ATYPE2TAG`

`HDF_AN_CREATE`

`HDF_AN_CREATEF`

`HDF_AN_END`

`HDF_AN_ENDACCESS`

`HDF_AN_FILEINFO`

`HDF_AN_GET_TAGREF`

`HDF_AN_ID2TAGREF`

`HDF_AN_NUMANN`

`HDF_AN_READANN`

`HDF_AN_SELECT`

`HDF_AN_START`

`HDF_AN_TAG2ATYPE`

`HDF_AN_TAGREF2ID`

`HDF_AN_WRITEANN`

`HDF_BROWSER`

`HDF_CLOSE`

`HDF_DELDD`

HDF\_DF24\_ADDIMAGE  
HDF\_DF24\_GETIMAGE  
HDF\_DF24\_GETINFO  
HDF\_DF24\_LASTREF  
HDF\_DF24\_NIMAGES  
HDF\_DF24\_READREF  
HDF\_DF24\_RESTART  
HDF\_DFAN\_ADDFDS  
HDF\_DFAN\_ADDFID  
HDF\_DFAN\_GETDESC  
HDF\_DFAN\_GETFDS  
HDF\_DFAN\_GETFID  
HDF\_DFAN\_GETLABEL  
HDF\_DFAN\_LABLIST  
HDF\_DFAN\_LASTREF  
HDF\_DFAN\_PUTDESC  
HDF\_DFAN\_PUTLABEL  
HDF\_DFP\_ADDPAL  
HDF\_DFP\_GETPAL  
HDF\_DFP\_LASTREF  
HDF\_DFP\_NPALS  
HDF\_DFP\_PUTPAL  
HDF\_DFP\_READREF  
HDF\_DFP\_RESTART  
HDF\_DFP\_WRITEREF  
HDF\_DFR8\_ADDIMAGE  
HDF\_DFR8\_GETIMAGE  
HDF\_DFR8\_GETINFO

HDF\_DFR8\_LASTREF  
HDF\_DFR8\_NIMAGES  
HDF\_DFR8\_PUTIMAGE  
HDF\_DFR8\_READREF  
HDF\_DFR8\_RESTART  
HDF\_DFR8\_SETPALETTE  
HDF\_DUPDD  
HDF\_EXISTS  
HDF\_GR\_ATTRINFO  
HDF\_GR\_CREATE  
HDF\_GR\_END  
HDF\_GR\_ENDACCESS  
HDF\_GR\_FILEINFO  
HDF\_GR\_FINDATTR  
HDF\_GR\_GETATTR  
HDF\_GR\_GETCHUNKINFO  
HDF\_GR\_GETIMINFO  
HDF\_GR\_GETLUTID  
HDF\_GR\_GETLUTINFO  
HDF\_GR\_IDTOREF  
HDF\_GR\_LUTTOREF  
HDF\_GR\_NAMETOINDEX  
HDF\_GR\_READIMAGE  
HDF\_GR\_READLUT  
HDF\_GR\_REFTOINDEX  
HDF\_GR\_SELECT  
HDF\_GR\_SETATTR  
HDF\_GR\_SETCHUNK

HDF\_GR\_SETCHUNKCACHE  
HDF\_GR\_SETCOMPRESS  
HDF\_GR\_SETEXTERNALFILE  
HDF\_GR\_START  
HDF\_GR\_WRITEIMAGE  
HDF\_GR\_WRITELUT  
HDF\_HDF2IDLTYPE  
HDF\_IDL2HDFTYPE  
HDF\_ISHDF  
HDF\_LIB\_INFO  
HDF\_NEWREF  
HDF\_NUMBER  
HDF\_OPEN  
HDF\_PACKDATA  
HDF\_READ  
HDF\_SD\_ADDDATA  
HDF\_SD\_ATTRFIND  
HDF\_SD\_ATTRINFO  
HDF\_SD\_ATTRSET  
HDF\_SD\_CREATE  
HDF\_SD\_DIMGET  
HDF\_SD\_DIMGETID  
HDF\_SD\_DIMSET  
HDF\_SD\_END  
HDF\_SD\_ENDACCESS  
HDF\_SD\_FILEINFO  
HDF\_SD\_GETDATA  
HDF\_SD\_GETINFO

HDF\_SD\_IDTOREF  
HDF\_SD\_ISCOORDVAR  
HDF\_SD\_NAMETOINDEX  
HDF\_SD\_REFTOINDEX  
HDF\_SD\_SELECT  
HDF\_SD\_SETCOMPRESS  
HDF\_SD\_SETTEXTFILE  
HDF\_SD\_SETINFO  
HDF\_SD\_START  
HDF\_UNPACKDATA  
HDF\_VD\_ATTACH  
HDF\_VD\_ATTRFIND  
HDF\_VD\_ATTRINFO  
HDF\_VD\_ATTRSET  
HDF\_VD\_DETACH  
HDF\_VD\_FDEFINE  
HDF\_VD\_FEXIST  
HDF\_VD\_FIND  
HDF\_VD\_GET  
HDF\_VD\_GETID  
HDF\_VD\_GETINFO  
HDF\_VD\_INSERT  
HDF\_VD\_ISATTR  
HDF\_VD\_ISVD  
HDF\_VD\_ISVG  
HDF\_VD\_LONE  
HDF\_VD\_NATTRS  
HDF\_VD\_READ

HDF\_VD\_SEEK  
HDF\_VD\_SETINFO  
HDF\_VD\_WRITE  
HDF\_VG\_ADDTR  
HDF\_VG\_ATTACH  
HDF\_VG\_DETACH  
HDF\_VG\_GETID  
HDF\_VG\_GETINFO  
HDF\_VG\_GETNEXT  
HDF\_VG\_GETTR  
HDF\_VG\_GETTRS  
HDF\_VG\_INQTR  
HDF\_VG\_INSERT  
HDF\_VG\_ISVD  
HDF\_VG\_ISVG  
HDF\_VG\_LONE  
HDF\_VG\_NUMBER  
HDF\_VG\_SETINFO

# HDF\_AN\_ANNLEN

This function returns the number of characters contained in the HDF AN annotation specified by the annotation identifier *Annotation\_id*.

## Syntax

*Result* = HDF\_AN\_ANNLEN(*Annotation\_id*)

## Return Value

The number of characters contained in the HDF AN annotation.

## Arguments

### Annotation\_id

Annotation identifier returned by HDF\_AN\_CREATE, HDF\_AN\_CREATEF, or HDF\_AN\_SELECT.

## Keywords

None

## Version History

5.2	Introduced
-----	------------



# HDF\_AN\_ANNLIST

This function obtains a list of identifiers of the annotations that are of the type specified by the parameter `Annotation_type` and are attached to the object identified by its tag, `Object_tag`, and its reference number, `Object_ref`.

## Syntax

```
Result = HDF_AN_ANNLIST(Annotation_id, Annotation_type, Object_tag,  
                        Object_ref, Annotation_list)
```

## Return Value

Returns SUCCEED (0) or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF AN interface identifier returned by `HDF_AN_START`.

### Annotation\_type

Type of the annotation. Since this routine is implemented only to obtain the identifiers of data annotations and not file annotations, the valid values of `Annotation_type` are:

- 0 = data label
- 1 = data description

### Object\_tag

HDF tag of the object.

### Object\_ref

HDF reference number of the object.

### Annotation\_list

A named variable that will contain the annotation identifiers.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_ATYPE2TAG

This function returns the HDF tag that corresponds to the annotation type specified by the parameter *Annotation\_type*.

## Syntax

*Result* = HDF\_AN\_ATYPE2TAG(*Annotation\_type*)

## Return Value

Returns the HDF annotation tag (*Annotation\_tag*) if successful, or not found (0) otherwise.

## Arguments

### Annotation\_type

Type of the annotation. The following table lists the valid values of *Annotation\_type* in the left column and the corresponding values for the returned annotation tag on the right.

Annotation Type	HDF Annotation Tag
0 = Data Label (AN_DATA_LABEL)	104 (DFTAG_DIL)
1 = Data Description (AN_DATA_DESC)	105 (DFTAG_DIA)
2 = File Label (AN_FILE_LABEL)	100 (DFTAG_FID)
3 = File Description (AN_FILE_DESC)	101 (DFTAG_FD)

Table 4-6: Valid *Annotation\_type* and *Annotation\_tag* values.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_CREATE

This function creates an HDF AN data annotation of type *Annotation\_type* for the object specified by its HDF tag, *Object\_tag*, and its HDF reference number, *Object\_ref*. Use HDF\_AN\_CREATEF to create a file annotation. Currently, the user must write to a newly-created annotation before creating another annotation of the same type. Creating two consecutive annotations of the same type causes the second call to HDF\_AN\_CREATE to return FAIL (-1).

## Syntax

```
Result = HDF_AN_CREATE(Annotation_id, Object_tag, Object_ref,  
Annotation_type)
```

## Return Value

Returns the data annotation identifier (*Annotation\_id*) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF\_AN\_INTERFACE identifier returned by HDF\_AN\_START.

### Object\_tag

HDF tag of the object to be annotated.

### Object\_ref

HDF reference number of the object to be annotated.

### Annotation\_type

Type of the data annotation.

The returned data annotation identifier can represent either a data label or a data description. Valid values for *Annotation\_type* are:

- 0 = data label
- 1 = data description

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_CREATEF

This function creates an HDF AN file annotation of the type specified by the parameter *Annotation\_type*. Use `HDF_AN_CREATE` to create a data annotation. Currently, the user must write to a newly-created annotation before creating another annotation of the same type. Creating two consecutive annotations of the same type causes the second call to `HDF_AN_CREATE` to return `FAIL (-1)`

## Syntax

*Result* = `HDF_AN_CREATEF(Annotation_id, Annotation_type)`

## Return Value

Returns the file annotation identifier (*Annotation\_id*) if successful or `FAIL (-1)` otherwise.

## Arguments

### Annotation\_id

HDF\_AN\_INTERFACE identifier returned by `HDF_AN_START`.

### Annotation\_type

Type of the file annotation. The file annotation identifier returned can either represent a file label or a file description. Valid values for *Annotation\_type* are:

- 2 = file label
- 3 = file description

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_END

This procedure terminates access to the HDF AN interface identified by *Annotation\_id*, which is previously initialized by a call to HDF\_AN\_START. Note that there must be one call to HDF\_AN\_END for each call to HDF\_AN\_START.

## Syntax

HDF\_AN\_END, *Annotation\_id*

## Arguments

### Annotation\_id

HDF AN interface identifier returned by HDF\_AN\_START.

## Keywords

None

## Version History

5.2	Introduced
-----	------------



# HDF\_AN\_ENDACCESS

This procedure terminates access to the annotation identified by the parameter `Annotation_id`. Note that there must be one call to `HDF_AN_ENDACCESS` for every call to `HDF_AN_SELECT`, `HDF_AN_CREATE` or `HDF_AN_CREATEF`.

## Syntax

`HDF_AN_ENDACCESS, Annotation_id`

## Arguments

### Annotation\_id

Annotation identifier returned by `HDF_AN_CREATE`, `HDF_AN_CREATEF` or `HDF_AN_SELECT`.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_FILEINFO

This function retrieves the total number of the four kinds of annotations and stores them in the appropriate parameters. Note that the numbers of data labels and descriptions refer to the total number of data labels and data descriptions in the file, not for a specific object. Use `HDF_AN_NUMANN` to determine these numbers for a specific object. This function is generally used to find the range of acceptable indices for `HDF_AN_SELECT` calls.

## Syntax

```
Result = HDF_AN_FILEINFO(Annotation_id, n_file_labels, n_file_descs,  
                        n_data_labels, n_data_descs)
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **Annotation\_id**

HDF AN interface identifier returned by `HDF_AN_START`.

### **n\_file\_labels**

A named variable that will contain the number of file labels.

### **n\_file\_descs**

A named variable that will contain the number of file descriptions.

### **n\_data\_labels**

A named variable that will contain the total number of data labels of all data objects in the file.

### **n\_data\_descs**

A named variable that will contain the total number of data descriptions of all data objects in the file.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_GET\_TAGREF

This function retrieves the HDF tag and reference number of the annotation identified by its index and by its annotation type.

## Syntax

```
Result = HDF_AN_GET_TAGREF(Annotation_id, index, Annotation_type,  

Annotation_tag, Annotation_ref)
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF AN interface identifier returned by HDF\_AN\_START.

### Index

Index of the annotation. This parameter is a nonnegative integer and is less than the total number of annotations of type *Annotation\_type* in the file. Use HDF\_AN\_FILEINFO to obtain the total number of annotations of each type in the file.

### Annotation\_type

Type of the annotation. The following table lists the valid values of the parameter *Annotation\_type* in the left column, and the corresponding values of the parameter *Annotation\_tag* in the right column.

Annotation Type	HDF Annotation Tag
0 = Data Label (AN_DATA_LABEL)	104 (DFTAG_DIL)
1 = Data Description (AN_DATA_DESC)	105 (DFTAG_DIA)

Table 4-7: Valid *Annotation\_type* and *Annotation\_tag* values.

Annotation Type	HDF Annotation Tag
2 = File Label (AN_FILE_LABEL)	100 (DFTAG_FID)
3 = File Description (AN_FILE_DESC)	101 (DFTAG_FD)

*Table 4-7: Valid Annotation\_type and Annotation\_tag values.*

### **Annotation\_tag**

A named variable that will contain the HDF tag of the annotation.

### **Annotation\_ref**

A named variable that will contain the HDF reference number of the annotation.

## **Keywords**

None

## **Version History**

5.2	Introduced
-----	------------

# HDF\_AN\_ID2TAGREF

This function retrieves the HDF tag/reference number pair of the HDF AN annotation identified by its annotation identifier.

## Syntax

*Result* = HDF\_AN\_ID2TAGREF(*Annotation\_id*, *Annotation\_tag*, *Annotation\_ref*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF AN annotation identifier returned by HDF\_AN\_SELECT, HDF\_AN\_CREATE or HDF\_AN\_CREATEF.

### Annotation\_tag

A named variable that will contain the HDF tag of the annotation. Possible values returned in Annotation\_tag are:

- 104 = data label (DFTAG\_DIL)
- 105 = data description (DFTAG\_DIA)
- 100 = file label (DFTAG\_FID)
- 101 = file description (DFTAG\_FD)

### Annotation\_ref

A named variable that will contain the HDF reference number of the annotation.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_NUMANN

This function returns the total number of HDF AN annotations that are of a given type and that are attached to the object identified by its HDF tag and its HDF reference number.

## Syntax

*Result* = HDF\_AN\_NUMANN(*Annotation\_id*, *Annotation\_type*, *Object\_tag*, *Object\_ref*)

## Return Value

Returns the number of annotations or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF AN interface identifier returned by HDF\_AN\_START.

### Annotation\_type

Type of the annotation. The following table lists the valid values of the parameter *Annotation\_type* in the left column, and the corresponding values of the parameter *Annotation\_tag* in the right column.

Annotation Type	HDF Annotation Tag
0 = Data Label (AN_DATA_LABEL)	104 (DFTAG_DIL)
1 = Data Description (AN_DATA_DESC)	105 (DFTAG_DIA)
2 = File Label (AN_FILE_LABEL)	100 (DFTAG_FID)
3 = File Description (AN_FILE_DESC)	101 (DFTAG_FD)

Table 4-8: Valid *Annotation\_type* and *Annotation\_tag* values.

### Object\_tag

HDF tag of the object.



## Object\_ref

HDF reference number of the object. Since this routine is implemented only to obtain the total number of data annotations and not file annotations, the valid values of Annotation\_type are:

- 0 = data label
- 1 = data description

To obtain the total number of file annotations or all data annotations, use HDF\_AN\_FILEINFO.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_READANN

This function reads the HDF AN annotation identified by the annotation identifier and stores the annotation into a variable.

## Syntax

```
Result = HDF_AN_READANN( Annotation_id, annotation
    [, LENGTH=characters] )
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

Annotation identifier returned by HDF\_AN\_CREATE, HDF\_AN\_CREATEF or HDF\_AN\_SELECT.

### Annotation

A named variable that will contain the annotation.

## Keywords

### LENGTH

Specifies the number of characters to be read from the annotation argument. If LENGTH is not set, or LENGTH is greater than the number of characters in annotation, then the entire annotation is read.

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_SELECT

This function obtains the HDF AN identifier of the annotation specified by its index and by its annotation type.

## Syntax

```
Result = HDF_AN_SELECT(Annotation_id, index, Annotation_type)
```

## Return Value

Returns the annotation identifier (*Annotation\_id*) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF\_AN\_INTERFACE identifier returned by HDF\_AN\_START.

### Index

Location of the annotation in the file. This parameter is a nonnegative integer and is less than the total number of annotations of type *Annotation\_type* in the file minus 1. Use HDF\_AN\_FILEINFO to obtain the total number of annotations of each type in the file.

### Annotation\_type

Type of the annotation. Valid values of *Annotation\_type* are:

- 0 = data labels
- 1 = data descriptions
- 2 = file labels
- 3 = file descriptions

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_START

This function initializes the HDF AN interface for the specified file. A call to `HDF_AN_START` is required before any HDF AN functions can be invoked. `HDF_AN_START` is used with the `HDF_AN_END` function to define the extent of an HDF AN session. A call to `HDF_AN_END` is required for each call to `HDF_AN_START`.

## Syntax

*Result* = `HDF_AN_START(file_id)`

## Return Value

Returns the HDF AN interface identifier (`Annotation_id`) if successful or `FAIL (-1)` otherwise.

## Arguments

### File\_id

File identifier returned by `HDF_OPEN`. Note that each call to `HDF_OPEN` *must* be terminated with a call to `HDF_CLOSE`.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_TAG2ATYPE

This function returns the HDF AN annotation type that corresponds to the specified HDF annotation tag.

## Syntax

*Result* = HDF\_AN\_TAG2ATYPE(*Annotation\_tag*)

## Return Value

Returns the annotation type if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_tag

HDF tag of the annotation.

The following table lists the valid values of Annotation\_tag in the left column and the corresponding values of the returned annotation type in the right column.

Annotation Type	HDF Annotation Tag
0 = Data Label (AN_DATA_LABEL)	104 (DFTAG_DIL)
1 = Data Description (AN_DATA_DESC)	105 (DFTAG_DIA)
2 = File Label (AN_FILE_LABEL)	100 (DFTAG_FID)
3 = File Description (AN_FILE_DESC)	101 (DFTAG_FD)

*Table 4-9: Valid Annotation\_type and Annotation\_tag values.*

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_TAGREF2ID

This function returns the HDF AN identifier of the annotation specified by its HDF tag and its HDF reference number.

## Syntax

*Result* = HDF\_AN\_TAGREF2ID(*Annotation\_id*, *Annotation\_tag*, *Annotation\_ref*)

## Return Value

Returns the annotation identifier (*Annotation\_id*) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

HDF\_AN\_INTERFACE identifier returned by HDF\_AN\_START.

### Annotation\_tag

HDF tag of the annotation. Valid values are:

- 104 = data label (DFTAG\_DIL)
- 105 = data description (DFTAG\_DIA)
- 100 = file label (DFTAG\_FID)
- 101 = file description (DFTAG\_FD)

### Annotation\_ref

HDF reference number of the annotation.

## Keywords

None



## Version History

5.2	Introduced
-----	------------

# HDF\_AN\_WRITEANN

This function writes the annotation text provided in the parameter *annotation* to the HDF AN annotation specified by the parameter *Annotation\_id*.

## Syntax

```
Result = HDF_AN_WRITEANN( Annotation_id, annotation
    [, LENGTH=characters] )
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### Annotation\_id

Annotation identifier returned by HDF\_AN\_CREATE, HDF\_AN\_CREATEF, or HDF\_AN\_SELECT.

### Annotation

Text or IDL variable to be written as the annotation.

## Keywords

### LENGTH

Length of the annotation text to be written. If not specified, the entire annotation will be written. If the keyword LENGTH is set, then only LENGTH characters of the annotation will be written. If the annotation has already been written, HDF\_AN\_WRITEANN will overwrite the current text.

## Version History

5.2	Introduced
-----	------------

# HDF\_BROWSER

See [HDF\\_BROWSER](#) in the *IDL Reference Guide*.

# HDF\_CLOSE

The HDF\_CLOSE procedure closes the HDF file associated with the given file handle.

## Syntax

HDF\_CLOSE, *FileHandle*

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

## Keywords

None

## Version History

---

Pre 4.0	Introduced
---------	------------

---

## See Also

[HDF\\_OPEN](#)

# HDF\_DELDD

The HDF\_DELDD procedure deletes a tag or reference from the list of data descriptors in an HDF file.

## Syntax

HDF\_DELDD, *FileHandle*, *Tag*, *Ref*

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### Tag

The data descriptor tag to delete.

### Reference

The data descriptor reference number to delete.

## Keywords

None

## Version History

Pre 4.0	Introduced
---------	------------

# HDF\_DF24\_ADDIMAGE

The HDF\_DF24\_ADDIMAGE procedure writes a 24-bit raster image to an HDF file. The interlace is set automatically based upon the dimensions of the image being written: ARR(3, Width, Height) for pixel interlace, ARR(Width, 3, Height) for scan-line interlace, and ARR(Width, Height, 3) for scan-plane interlace.

---

## Note

HDF\_DF24\_ADDIMAGE chooses an interlace based upon the location of the '3'-sized dimension. For 3x3xN, 3xNx3 and Nx3x3 images, if the first '3' encountered is supposed to be a width or height, HDF\_DF24\_ADDIMAGE will choose the 'wrong' interlace. However, as long as one reads in the image using the same interlace, the image will be read correctly anyway. Avoid writing 24-bit-deep raster images with a width or height of 3 pixels.

---



---

## Note

Input data is converted to bytes before being written to the file, as images in the DF24 HDF model are necessarily byte images.

---

## Syntax

HDF\_DF24\_ADDIMAGE, *Filename*, *Image* [, /FORCE\_BASELINE{useful only if QUALITY<25}] [, /JPEG | , /RLE] [, QUALITY=*value*{0 to 100}]

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Image

A 3-dimensional array of values representing the 3 planes (Red, Green, and Blue) of the 24-bit image. One of the dimensions *must* be 3 (e.g., a 3 x 100 x 100 array).

## Keywords

### FORCE\_BASELINE

Set this keyword to force the JPEG quantization tables to be constrained to the range 1 to 255. This provides full baseline compatibility with external JPEG applications,

but only makes a difference if the `QUALITY` keyword is set to a value less than 25. The default is `TRUE`.

## JPEG

Set this keyword to compress the image being added using the JPEG (Joint Photographic Expert Group) method. Note that JPEG compression is *lossy*; see `WRITE_JPEG` in the *IDL Reference Guide* for more information about when this method is appropriate. (In other words, using JPEG compression to reduce the size of an image changes the values of the pixels and hence may alter the meaning of the corresponding data.) Setting either the `QUALITY` or the `FORCE_BASELINE` keyword implies this method.

## QUALITY

Set this keyword equal to the JPEG “quality” desired. This value should be in the range 0 (terrible image quality but excellent compression) to 100 (excellent image quality but minimum compression). The default is 75. Setting this keyword implies that the `JPEG` keyword is set. Lower values of `QUALITY` produce higher compression ratios and smaller files.

## RLE

Set this keyword to store the image using run length compression. RLE compression is lossless, and is recommended for images where data retention is critical.

## Version History

4.0	Introduced
-----	------------

## See Also

[WRITE\\_JPEG](#)

# HDF\_DF24\_GETIMAGE

The HDF\_DF24\_GETIMAGE procedure reads a 24-bit raster image from an HDF file. The default is to use the same format for reading as that used in writing the image. Note: it is slower to read an image in a different interlace than the one in which the image was originally written.

## Syntax

```
HDF_DF24_GETIMAGE, Filename, Image [, /LINE | , /PIXEL | , /PLANE]
```

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Image

A named variable in which the image data is returned.

## Keywords

### LINE

Set this keyword to force the image to be read with scan-line interlace.

### PIXEL

Set this keyword to force the image to be read with pixel interlace.

### PLANE

Set this keyword to force the image to be read with scan-plane interlace.

## Version History

4.0	Introduced
-----	------------



# HDF\_DF24\_GETINFO

The HDF\_DF24\_GETINFO procedure retrieves information about the current 24-bit HDF image.

## Syntax

HDF\_DF24\_GETINFO, *Filename*, *Width*, *Height*, *Interlace*

## Arguments

### Filename

A string containing the name of the file to be read.

### Width

A named variable in which the width of the image is returned.

### Height

A named variable in which the height of the image is returned.

### Interlace

A named variable in which the interface method is returned. The returned value is 0 for pixel interlacing, 1 for scan-line interlacing, and 2 for scan-plane interlacing.

## Keywords

None

## Examples

```
; Open the file myhdf.hdf:
h = HDF_OPEN('myhdf.hdf')
; Return information about the 24-bit image:
HDF_DF24_GETINFO, 'myhdf.hdf', width, height, interlace
; Print information about the returned variables:
HELP, width, height, interlace
HDF_CLOSE('myhdf.hdf') ; Close the HDF file.
```

## IDL Output

If the image were 536 by 412 pixels, and scan-line interlaced, IDL would print:

```
WIDTH LONG = 536
HEIGHT LONG = 412
INTERLACE LONG = 1
```

## Example Code

---

For a more detailed example, see the file `hdf_info.pro`, located in the `examples/doc/sdf` subdirectory of the IDL distribution.

---

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_DF24\\_GETIMAGE](#), [HDF\\_DF24\\_LASTREF](#), [HDF\\_DF24\\_NIMAGES](#),  
[HDF\\_DF24\\_READREF](#), [HDF\\_DF24\\_RESTART](#)

# HDF\_DF24\_LASTREF

The HDF\_DF24\_LASTREF function returns the reference number of the most recently read or written 24-bit image in an HDF file.

## Syntax

*Result* = HDF\_DF24\_LASTREF()

## Return Value

Returns the reference number of the most recently read or written image.

## Arguments

None

## Keywords

None

## Examples

```
; Open an HDF file.
h=HDF_OPEN('myhdf.hdf')
PRINT, HDF_DF24_LASTREF()
; IDL prints 0, meaning that the call was successful,
; but no reference number was available.

; Create a 3D array, representing a 24-bit image:
a = BINDGEN(3,100,100)

; Write the 24-bit image to the file:
HDF_DF24_ADDIMAGE, 'myhdf.hdf', a

PRINT, HDF_DF24_LASTREF()
; IDL prints a reference number for the last operation
; (for example, 2). Note the reference number is not
; simply a 1-based "image number"; the reference number
; could easily be "2" or "3", etc.

; Write another image to the file:
HDF_DF24_ADDIMAGE, 'myhdf.hdf', a
```

```
; Print the last reference number:
PRINT, HDF_DF24_LASTREF()
PRINT, HDF_DF24_NIMAGES('myhdf.hdf')
; IDL prints "2" because we've written two images to the file.
; Close the file
HDF_CLOSE, h
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DF24\\_ADDIMAGE](#), [HDF\\_DF24\\_GETIMAGE](#), [HDF\\_DF24\\_GETINFO](#),  
[HDF\\_DF24\\_NIMAGES](#), [HDF\\_DF24\\_READREF](#), [HDF\\_DF24\\_RESTART](#),  
[HDF\\_DFR8\\_LASTREF](#)

# HDF\_DF24\_NIMAGES

The HDF\_DF24\_NIMAGES function returns the number of 24-bit images in an HDF file.

## Syntax

*Result* = HDF\_DF24\_NIMAGES(*Filename*)

## Return Value

Returns the number of images in the file or -1 if the specified file is invalid or damaged

## Arguments

### Filename

A string containing the name of the file to be searched.

## Keywords

None

## Examples

```
; Open HDF file:
h = HDF_OPEN('myhdf.hdf')
; Return the number of 24-bit images in the file:
number = HDF_DF24_NIMAGES('myhdf.hdf')
; Print information about the returned value. If there were five
; images in the file, IDL would print NUMBER LONG = 5
HELP, number
; Close the HDF file:
HDF_CLOSE, h
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DF24\\_GETIMAGE](#), [HDF\\_DF24\\_GETINFO](#), [HDF\\_DF24\\_READREF](#),  
[HDF\\_DF24\\_RESTART](#), [HDF\\_DFR8\\_NIMAGES](#)

# HDF\_DF24\_READREF

The HDF\_DF24\_READREF procedure sets the reference number of the image in an HDF file to be read by the next call to HDF\_DF24\_GETIMAGE.

## Syntax

HDF\_DF24\_READREF, *Filename*, *Reference\_number*

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Reference\_number

The reference number for a 24-bit raster image.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DF24\_RESTART

The HDF\_DF24\_RESTART procedure causes the next call to HDF\_DF24\_GETIMAGE to read the first 24-bit image in the HDF file.

## Syntax

```
HDF_DF24_RESTART
```

## Arguments

None

## Keywords

None

## Version History

4.0	Introduced
-----	------------



# HDF\_DFAN\_ADDFDS

The HDF\_DFAN\_ADDFDS procedure adds a file description to an HDF file.

## Syntax

HDF\_DFAN\_ADDFDS, *Filename*, *Description*

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Description

A string or an array of bytes containing the information to be written.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFAN\_ADDFID

The HDF\_DFAN\_ADDFID procedure adds a file annotation to an HDF file. A file can have multiple annotations added.

## Syntax

HDF\_DFAN\_ADDFID, *Filename, Label*

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Label

A string containing the annotation string.

## Keywords

None

## Examples

```

; Open the HDF file:
filename = 'FID.hdf'
hid = HDF_OPEN(filename, /CREATE)
; Write two file annotations:
HDF_DFAN_ADDFID, filename, 'File Annotation #1'
HDF_DFAN_ADDFID, filename, 'File Annotation #2'
; Read the two annotations back:
HDF_DFAN_GETFID, filename, fid1
HDF_DFAN_GETFID, filename, fid2
HELP, fid1, fid2
; Try to read a non-existent FID:
HDF_DFAN_GETFID, filename, fid3
; Read the FIRST fid again, using the FIRST keyword:
HDF_DFAN_GETFID, filename, fid4, /FIRST
HELP, fid4
; Close the HDF file:
HDF_CLOSE, hid

```

## IDL Output

```
FID1          STRING    = 'File Annotation #1'  
FID2          STRING    = 'File Annotation #2'  
  
% HDF_DFAN_GETFID: Could not read ID length  
  
FID4          STRING    = 'File Annotation #1'
```

## Version History

4.0	Introduced
-----	------------

# HDF\_DFAN\_GETDESC

The HDF\_DFAN\_GETDESC procedure reads the description for the given tag and reference number in an HDF file.

## Syntax

HDF\_DFAN\_GETDESC, *Filename*, *Tag*, *Ref*, *Description* [, /STRING]

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Tag

The tag number.

### Reference

The reference number.

### Description

A named variable in which the description is returned as a vector of bytes.

If a description does not exist, the *Description* variable will contain either a 0L (long-integer zero) or a blank string, and a warning message will be printed. Warning messages can be suppressed by setting the !QUIET system variable to a non-zero value.

## Keywords

### STRING

Set this keyword to return the description as a string rather than a vector of bytes.

## Examples

```
desc1 = 'FILE DESCRIPTION NUMBER 1'  
tag_image = 302  
file = 'DEMOfdesc.hdf'  
fid = HDF_OPEN(file, /CREATE)
```

```

HDF_DFR8_ADDIMAGE, file, DIST(10)
HDF_DFAN_PUTDESC, file, tag_image, HDF_DFR8_LASTREF(), desc1
; Read the description and return a vector of bytes:
HDF_DFAN_GETDESC, file, tag_image, HDF_DFR8_LASTREF(), out_desc1
HELP, out_desc1
PRINT, STRING(out_desc1)
; Read the description and return an IDL string variable:
HDF_DFAN_GETDESC, file, tag_image, HDF_DFR8_LASTREF(), $
    out_desc2, /STRING
HELP, out_desc2
HDF_CLOSE, fid

```

### IDL Output

```

OUT_DESC1      BYTE      = Array(25)

FILE DESCRIPTION NUMBER 1

OUT_DESC2      STRING    = 'FILE DESCRIPTION NUMBER 1'

```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DFAN\\_PUTDESC](#)

# HDF\_DFAN\_GETFDS

The HDF\_DFAN\_GETFDS procedure reads the next available file description from an HDF file.

## Syntax

```
HDF_DFAN_GETFDS, Filename, Description [, /FIRST] [, /STRING]
```

## Arguments

### Filename

A string containing the name of the file to be read.

### Description

A named variable in which the description is returned. By default, the description is returned as a vector of bytes. Set the STRING keyword to return the description as a string.

If a description does not exist, the *Description* variable will contain either a 0L (long-integer zero) or a blank string, and a warning message will be printed. Warning messages can be suppressed by setting the !QUIET system variable to a non-zero value.

## Keywords

### FIRST

Set this keyword to read the first file description in the file. If FIRST is not set, the next available file description (which can be the first file description) will be read.

### STRING

Set this keyword to return *Description* as a string instead of a vector of bytes.

## Examples

```
filename = 'DEMOfds.hdf'  
fds1 = 'FILE DESCRIPTION NUMBER 1'  
fds2 = 'SHORT FDS 2'  
; Create an HDF file:
```

```

fid = HDF_OPEN(filename, /CREATE)
; Add first file description:
HDF_DFAN_ADDFDS, filename, fds1
; Add second file description:
HDF_DFAN_ADDFDS, filename, fds2
; Get the first file description:
HDF_DFAN_GETFDS, filename, out_fds1, /FIRST
HELP, out_fds1
PRINT, STRING(out_fds1)
; Get the second file description:
HDF_DFAN_GETFDS, filename, out_fds2, /STRING
HELP, out_fds2
; Close the HDF file:
HDF_CLOSE, fid

```

### IDL Output

```

OUT_FDS1          BYTE          = Array(25)

FILE DESCRIPTION NUMBER 1

OUT_FDS2          STRING        = 'SHORT FDS 2'

```

## Version History

4.0	Introduced
-----	------------

### See Also

[HDF\\_DFAN\\_ADDFDS](#), [HDF\\_DFAN\\_ADDFID](#), [HDF\\_DFAN\\_GETDESC](#),  
[HDF\\_DFAN\\_GETFID](#)

# HDF\_DFAN\_GETFID

The HDF\_DFAN\_GETFID procedure reads the next available file annotation from an HDF file.

## Syntax

```
HDF_DFAN_GETFID, Filename, Label [, /FIRST]
```

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Label

A named variable in which the annotation is returned as a string.

## Keywords

### FIRST

Set this keyword to read the first annotation in the file. Otherwise, the next available annotation is read (which may be the first annotation).

## Examples

For an example using this routine, see “[HDF\\_DFAN\\_ADDFID](#)” on page 370.

## Version History

4.0	Introduced
-----	------------



# HDF\_DFAN\_GETLABEL

The `HDF_DFAN_GETLABEL` procedure reads the label for the given tag-reference pair in an HDF file.

## Syntax

`HDF_DFAN_GETLABEL, Filename, Tag, Ref, Label`

## Arguments

### Filename

A scalar string that contains the name of the file to be read.

### Tag

The tag number.

### Reference

The reference number.

### Label

A named variable in which the label is returned as a string.

## Keywords

None

## Examples

```
fid = HDF_OPEN('test.hdf', /ALL)
label = 'TEST LABEL'
tag = 105 ; The annotation tag.
ref = 2 ; Choose a reference number.
; Write the label:
HDF_DFAN_PUTLABEL, 'test.hdf', tag, ref, label
; Read back the label:
HDF_DFAN_GETLABEL, 'test.hdf', tag, ref, out1
HELP, out1 ; They look the same...
; Close the HDF file:
HDF_CLOSE, fid
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_DFAN\\_GETDESC](#), [HDF\\_DFAN\\_LABLIST](#), [HDF\\_DFAN\\_PUTDESC](#),  
[HDF\\_DFAN\\_PUTLABEL](#)

# HDF\_DFAN\_LABLIST

The HDF\_DFAN\_LABLIST function retrieves a list of the reference numbers and the corresponding labels for a given tag in an HDF file.

## Syntax

```
Result = HDF_DFAN_LABLIST( Filename, Tag, Reflist, Labellist  
    [, LISTSIZE=value] [, MAXLABEL=value] [, STARTPOS=value] [, /STRING] )
```

## Return Value

If successful, the number of entries found is returned.

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Tag

The tag number.

### Reflist

A named variable in which an array of reference numbers associated with the given tag is returned.

### Labellist

A named variable in which an array of labels is returned. Unless the `STRING` keyword is set, *Labellist* will contain an `N_ELEMENTS(Reflist)` by `MAXLABEL` array of bytes. Note that array elements containing labels that are shorter than `MAXLABEL` will be padded with zeroes.

## Keywords

### LISTSIZE

Set the maximum size of the *Reflist* and *Labellist* returned. The default is to read all references present, or 20 if the inquiry to obtain the number of references fails.

## MAXLABEL

Use this keyword to override the default label length of 16.

## STARTPOS

Use this keyword to set the default starting position in the *Reflist* array.

## STRING

Set this keyword to return an array of strings rather than an array of bytes. If **STRING** is set, the **MAXLABEL** keyword is ignored and full-length strings are returned.

## Examples

```

tag_image = 302
file = 'DEMOLablist.hdf'
n_images = HDF_DFAN_LABLIST(file, tag_image, refs, list, /STRING)
help, n_images, refs, list
PRINT, list(0)
; Find all the compressed images:
tag_image_comp = 303
n_comp_images = HDF_DFAN_LABLIST(file, tag_image_comp, $
    refs, list, MAXLABEL=5)
HELP, n_comp_images, refs, list

```

### IDL Output

```

N_IMAGES      LONG      =          2
REFS          INT       = Array(2)
LIST          STRING    = Array(2)

SAMPLE IMAGE LABEL

N_COMP_IMAGES LONG      =          3
REFS          INT       = Array(3)
LIST          BYTE      = Array(5, 3)

```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DFAN\\_GETLABEL](#), [HDF\\_DFAN\\_PUTLABEL](#)

# HDF\_DFAN\_LASTREF

The HDF\_DFAN\_LASTREF function returns the reference number of the most recently read or written annotation in an HDF file.

## Syntax

*Result* = HDF\_DFAN\_LASTREF( )

## Return Value

Returns the reference number of the most recently read or written annotation.

## Arguments

None

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFAN\_PUTDESC

The HDF\_DFAN\_PUTDESC procedure writes a description for the given tag and reference number in an HDF file.

## Syntax

HDF\_DFAN\_PUTDESC, *Filename*, *Tag*, *Ref*, *Description*

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Tag

The tag number.

### Reference

The reference number.

### Description

A string or array of bytes containing the information to be written.

If a description does not exist, the *Description* variable will contain either a 0L (long-integer zero) or a blank string, and a warning message will be printed. Warning messages can be suppressed by setting the !QUIET system variable to a non-zero value.

## Keywords

None

## Examples

See the example for “[HDF\\_DFAN\\_GETDESC](#)” on page 372.

## Version History

4.0	Introduced
-----	------------



# HDF\_DFAN\_PUTLABEL

The HDF\_DFAN\_PUTLABEL procedure writes a label for the given tag and reference number in an HDF file.

## Syntax

HDF\_DFAN\_PUTLABEL, *Filename*, *Tag*, *Ref*, *Label*

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Tag

The tag number.

### Ref

The reference number.

### Label

A string containing the description to write.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_ADDPAL

The HDF\_DFP\_ADDPAL procedure appends a palette to an HDF file.

## Syntax

HDF\_DFP\_ADDPAL, *Filename*, *Palette*

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Palette

A vector or array containing palette data. Palettes must be either [3, 256] arrays or 786-element vectors.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_GETPAL

The HDF\_DFP\_GETPAL procedure reads the next available palette from an HDF file.

## Syntax

HDF\_DFP\_GETPAL, *Filename*, *Palette*

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Palette

A named variable in which the palette data is returned.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_LASTREF

The HDF\_DFP\_LASTREF function returns the reference number of the most recently read or written palette in an HDF file.

## Syntax

*Result* = HDF\_DFP\_LASTREF()

## Return Value

Returns the reference number of the most recently read or written palette.

## Arguments

None

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_NPALS

The HDF\_DFP\_NPALS function returns the number of palettes present in an HDF file. This number includes palettes associated with RIS8 (8-bit raster) images.

## Syntax

*Result* = HDF\_DFP\_NPALS(*Filename*)

## Return Value

Returns the number of palettes.

## Arguments

### Filename

A scalar string containing the name of the desired HDF file.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_PUTPAL

The `HDF_DFP_PUTPAL` procedure appends a palette to an HDF file.

## Syntax

```
HDF_DFP_PUTPAL, Filename, Palette [, /DELETE] [, /OVERWRITE]
```

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Palette

A vector or array containing palette data. Palettes must be either [3, 256] arrays or 786-element vectors.

## Keywords

### DELETE

Set this keyword to delete the HDF file (if it exists) and create a new HDF file with the specified palette as its first object.

#### Note

---

The HDF file must be closed before the DELETE keyword is specified. Attempting to delete an open HDF file will result in an error.

---

### OVERWRITE

Set this keyword to overwrite the previous palette with the one specified by *Palette*.

## Examples

```
; Create HDF file:
id = HDF_OPEN('test.hdf', /CREATE, /RDWR)
; Add a palette:
HDF_DFP_PUTPAL, 'test.hdf', FINDGEN(3,256)
; Print number of palettes:
PRINT, HDF_DFP_NPALS('test.hdf')
```

```

; Append a palette:
HDF_DFP_PUTPAL, 'test.hdf', findgen(3,256)
; Print the number of palettes:
PRINT, HDF_DFP_NPALS('test.hdf')
; Overwrite the last palette:
HDF_DFP_PUTPAL, 'test.hdf', FINDGEN(3,256), /OVERWRITE
; Print the number of palettes:
PRINT, HDF_DFP_NPALS('test.hdf')
; An attempt to delete a file and add a new palette
; without first closing the HDF file fails:
HDF_DFP_PUTPAL, 'test.hdf', $
    FINDGEN(3,256), /DELETE
; Close the HDF file:
HDF_CLOSE, id
; Delete file and add a new palette:
HDF_DFP_PUTPAL, 'test.hdf', FINDGEN(3,256), /DELETE
; Print the number of palettes:
PRINT, HDF_DFP_NPALS('test.hdf')

```

### IDL Output

```

1

2

2

% HDF_DFP_PUTPAL: Could not write palette
% Execution halted at: $MAIN$

1

```

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_READREF

The HDF\_DFP\_READREF procedure sets the reference number of the palette in an HDF file to be read by the next call to HDF\_DFP\_GETPAL.

## Syntax

HDF\_DFP\_READREF, *Filename*, *Reference\_number*

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Reference\_number

The reference number of a palette.

## Keywords

None

## Version History

4.0	Introduced
-----	------------



# HDF\_DFP\_RESTART

The HDF\_DFP\_RESTART procedure causes the next call to HDF\_DFR8\_GETPAL to read from the first palette in an HDF file.

## Syntax

```
HDF_DFP_RESTART
```

## Arguments

None

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFP\_WRITEREF

The HDF\_DFP\_WRITEREF procedure sets the reference number for the next palette to be written to an HDF file. Normally, the HDF library automatically chooses a reference number for the palette. This procedure allows you to override that choice.

## Syntax

HDF\_DFP\_WRITEREF, *Filename*, *Reference\_number*

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Reference\_number

The new reference number.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFR8\_ADDIMAGE

The HDF\_DFR8\_ADDIMAGE procedure appends an 8-bit raster image to the specified HDF file.

---

**Note**

Input data is converted to bytes before being written to the file, as images in the DFR8 HDF model are necessarily byte images.

---

## Syntax

```
HDF_DFR8_ADDIMAGE, Filename, Image [, /FORCE_BASELINE {useful only if  
QUALITY<25}] [, /JPEG | , /RLE] [[, /IMCOMP] , PALETTE=vector or array]  
[, QUALITY=value]
```

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Image

A two-dimensional array containing the image data. If this array is not byte-type data, it is converted to bytes before writing.

## Keywords

### FORCE\_BASELINE

Set this keyword to force the JPEG quantization tables to be constrained to the range 1...255. This provides full baseline compatibility with external JPEG applications, but only makes a difference if the QUALITY keyword is set to a value less than 25. The default is TRUE.

### JPEG

Set this keyword to compress the image being added using the JPEG (Joint Photographic Expert Group) method. Note that JPEG compression is *lossy*; see WRITE\_JPEG in the *IDL Reference Guide* for more information about when this method is appropriate. (In other words, using JPEG compression to reduce the size of

an images changes the values of the pixels and hence may alter the meaning of the corresponding data.) Setting either the `QUALITY` or the `FORCE_BASELINE` keywords implies this method.

## IMCOMP

Set this keyword to store the image using `imcomp` data compression. Note that you *must* specify a palette. Note also that the `JPEG` and `RLE` compression methods are far superior; `imcomp` data compression should only be used if the images will be viewed on monitors with a very small number of colors (monochrome or 16-color).

## PALETTE

Set this keyword to a vector or array containing valid palette data. Palettes must be either `[3, 256]` arrays or 786-element vectors. Set `PALETTE` equal to zero to specify that no palette be used. If the `PALETTE` keyword is not specified, the current palette (which may be no palette, if a palette has not been specified elsewhere or if the null palette has been explicitly specified with `HDF_DFR8_SETPALETTE`) will be used.

Note that if a palette is specified, it becomes the current palette, even if a default palette has been specified with `HDF_DFR8_SETPALETTE`.

Note also that if `IMCOMP` data reduction is used, you *must* specify a valid palette with the `PALETTE` keyword. It is not sufficient to set the current palette via other means.

## QUALITY

Set this keyword equal to the `JPEG` “quality” desired. This value should be in range 0 (terrible image quality but excellent compression) to 100 (excellent image quality but minimum compression). The default is 75. Setting this keyword implies that the `JPEG` keyword is set. Lower values of `QUALITY` produce higher compression ratios and smaller files.

## RLE

Set this keyword to store the image using run length compression. `RLE` compression is lossless, and is recommended for images where data retention is critical.

## Examples

Assuming that we start with a file, `new.hdf`, with no 8-bit raster images, images could be appended and overwritten, with the following commands:

```
; Write the first image to the file:
```

```
HDF_DFR8_ADDIMAGE, 'new.hdf', Image1
; Append 2nd image:
HDF_DFR8_ADDIMAGE, 'new.hdf', Image2
; Append 3rd image:
HDF_DFR8_ADDIMAGE, 'new.hdf', Image3
; Use HDF_DFR8_PUTIMAGE to erase all previous images and
; write a new image at the first position in the file:
HDF_DFR8_PUTIMAGE, 'new.hdf', Image4
; Append 2nd image:
HDF_DFR8_ADDIMAGE, 'new.hdf', Image5
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_DFR8\\_GETIMAGE](#), [HDF\\_DFR8\\_PUTIMAGE](#), [WRITE\\_JPEG](#)

# HDF\_DFR8\_GETIMAGE

The HDF\_DFR8\_GETIMAGE procedure retrieves an image and optionally, its palette, from an HDF file.

## Syntax

```
HDF_DFR8_GETIMAGE, Filename, Image [, Palette]
```

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Image

A named variable in which the image is returned.

### Palette

A named variable in which the palette is returned as a 3-element by 256-element byte array. If the image does not have an associated palette, this variable is returned as 0.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFR8\_GETINFO

The `HDF_DFR8_GETINFO` procedure retrieves information about the current 8-bit HDF image.

## Syntax

`HDF_DFR8_GETINFO, Filename, Width, Height, Has_Palette`

## Arguments

### Filename

A string containing the name of the file to be read.

### Width

A named variable in which the width of the image is returned.

### Height

A named variable in which the height of the image is returned.

### Has\_Palette

A named variable in which 1 is returned if a palette is present. Otherwise, 0 is returned.

## Keywords

None

## Examples

```
; Open the file myhdf.hdf:
h = HDF_OPEN('myhdf.hdf')
; Retrieve info about an image:
HDF_DFR8_GETINFO, 'myhdf.hdf', width, height, has_palette
; Print info about returned variables:
HELP, width, height, has_palette
; Close the HDF file:
HDF_CLOSE('myhdf.hdf')
```

## IDL Output

```
WIDTH LONG = 536
HEIGHT LONG = 412
HAS_PALETTE LONG = 1
```

## Example Code

---

For a more detailed example, see the file `hdf_info.pro`, located in the `examples/doc/sdf` subdirectory of the IDL distribution.

---

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DFR8\\_GETIMAGE](#), [HDF\\_DFR8\\_NIMAGES](#), [HDF\\_DFR8\\_READREF](#),  
[HDF\\_DFR8\\_RESTART](#)



# HDF\_DFR8\_LASTREF

The HDF\_DFR8\_LASTREF function returns the reference number of the most recently read or written 8-bit image in an HDF file.

## Syntax

*Result* = HDF\_DFR8\_LASTREF()

## Return Value

Returns the reference number of the most recently read or written image.

## Arguments

None

## Keywords

None

## Examples

```
h = HDF_OPEN('myhdf.hdf') ; Open an hdf file.
; IDL prints "0", meaning that the call was successful,
; but no reference number was available:
PRINT, HDF_DFR8_LASTREF()
; Create a 2D array representing an 8-bit image:
a = BINDGEN(100,100)
; Write the image to the file:
HDF_DFR8_ADDIMAGE, 'myhdf.hdf', a
; IDL prints the reference number for the last 8-bit image
; operation (for example, "2"). Note the reference number
; is not simply a 1-based "image number"; it could easily be
; "2" or "3" for the first operation on the file:
PRINT, HDF_DFR8_LASTREF()
HDF_DFR8_ADDIMAGE, 'myhdf.hdf', a ; Add another image.
; IDL prints "2", because we've put two 8-bit images in the file:
PRINT, HDF_DFR8_NIMAGES('myhdf.hdf')
HDF_CLOSE, h ; Close the file.
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_DFR8\\_ADDIMAGE](#), [HDF\\_DFR8\\_GETIMAGE](#), [HDF\\_DFR8\\_GETINFO](#),  
[HDF\\_DFR8\\_LASTREF](#), [HDF\\_DFR8\\_NIMAGES](#), [HDF\\_DFR8\\_READREF](#),  
[HDF\\_DFR8\\_RESTART](#)

# HDF\_DFR8\_NIMAGES

The HDF\_DFR8\_NIMAGES function returns the number of 8-bit images in the specified HDF file.

## Syntax

*Result* = HDF\_DFR8\_NIMAGES(*Filename*)

## Return Value

Returns the number of 8-bit images in the given HDF file. The function returns -1 if the specified file is invalid or damaged.

## Arguments

### Filename

A string containing the name of the file to be read.

## Keywords

None

## Examples

```
; Open the file myhdf.hdf:  
h = HDF_OPEN('myhdf.hdf')  
; Retrieve the number of 8-bit images in the file into a variable:  
number = HDF_DFR8_NIMAGES('myhdf.hdf')  
HDF_CLOSE, h ; Close the file.
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DFR8\\_GETIMAGE](#), [HDF\\_DFR8\\_GETINFO](#), [HDF\\_DFR8\\_READREF](#)  
[HDF\\_DFR8\\_RESTART](#)

# HDF\_DFR8\_PUTIMAGE

The `HDF_DFR8_PUTIMAGE` procedure writes an 8-bit raster image as the first image in an HDF file. If there are images in the file, this procedure erases all other 8-bit and 24-bit images and writes *Image* as the first image in the file.

## Note

---

Input data is converted to bytes before being written to the file, as images in the DFR8 HDF model are necessarily byte images.

---

## Syntax

```
HDF_DFR8_PUTIMAGE, Filename, Image [, /FORCE_BASELINE{useful only if  
QUALITY<25}] [, /IMCOMP] , PALETTE=vector or array] [, /JPEG | , /RLE]  
[, QUALITY=value]
```

## Arguments

### Filename

A scalar string containing the name of the file to be written.

### Image

A two-dimensional array containing the image data. If this array is not byte-type data, it is converted to bytes before writing.

## Keywords

### FORCE\_BASELINE

Set this keyword to force the JPEG quantization tables to be constrained to the range 1...255. This provides full baseline compatibility with external JPEG applications, but only makes a difference if the `QUALITY` keyword is set to a value less than 25. The default is `TRUE`.

### JPEG

Set this keyword to compress the image being added using the JPEG (Joint Photographic Expert Group) method. Note that JPEG compression is *lossy*; see `WRITE_JPEG` in the *IDL Reference Guide* for more information about when this

method is appropriate. (In other words, using JPEG compression to reduce the size of an image changes the values of the pixels and hence may alter the meaning of the corresponding data.) Setting either the `QUALITY` or the `FORCE_BASELINE` keywords implies this method.

## **IMCOMP**

Set this keyword to store the image using `imcomp` data compression. Note that you *must* specify a palette. Note also that the JPEG and RLE compression methods are far superior; `imcomp` data compression should only be used if the images will be viewed on monitors with a very small number of colors (monochrome or 16-color).

## **PALETTE**

Set this keyword to a vector or array containing valid palette data. Palettes must be either [3, 256] arrays or 786-element vectors. Set `PALETTE` equal to zero to specify that no palette be used. If the `PALETTE` keyword is not specified, the current palette (which may be no palette, if a palette has not been specified elsewhere or if the null palette has been explicitly specified with `HDF_DFR8_SETPALETTE`) will be used.

Note that if a palette is specified, it becomes the current palette, even if a default palette has been specified with `HDF_DFR8_SETPALETTE`.

Note also that if `IMCOMP` data reduction is used, you *must* specify a valid palette with the `PALETTE` keyword. It is not sufficient to set the current palette via other means.

## **QUALITY**

Set this keyword equal to the JPEG “quality” desired. This value should be in range 0 (terrible image quality but excellent compression) to 100 (excellent image quality but minimum compression). The default is 75. Setting this keyword implies that the `JPEG` keyword is set. Lower values of `QUALITY` produce higher compression ratios and smaller files.

## **RLE**

Set this keyword to store the image using run length compression. RLE compression is lossless, and is recommended for images where data retention is critical.

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_DFR8\\_ADDIMAGE](#), [HDF\\_DFR8\\_GETIMAGE](#), [WRITE\\_JPEG](#)

# HDF\_DFR8\_READREF

The HDF\_DFR8\_READREF procedure sets the reference number of the image to be read from an HDF file by the next call to HDF\_DFR8\_GETIMAGE.

## Syntax

HDF\_DFR8\_READREF, *Filename*, *Reference\_number*

## Arguments

### Filename

A scalar string containing the name of the file to be read.

### Reference\_number

A reference number for an 8-bit raster image.

## Keywords

None

## Version History

4.0	Introduced
-----	------------



# HDF\_DFR8\_RESTART

The HDF\_DFR8\_RESTART procedure causes the next call to HDF\_DFR8\_GETIMAGE to read from the first image in the HDF file.

## Syntax

```
HDF_DFR8_RESTART
```

## Arguments

None

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DFR8\_SETPALETTE

The HDF\_DFR8\_SETPALETTE procedure sets the current palette to be used for subsequent images in an HDF file. The current palette will be used when adding images with the HDF\_DFR8\_ADDIMAGE routine.

## Syntax

HDF\_DFR8\_SETPALETTE, *Palette*

## Arguments

### Palette

A 768-element byte array of palette data. This array be a vector (e.g., BYTARR ( 768 )) or a two-dimensional array (e.g., BYTARR ( 3 , 256 )).

Set the Palette array to the integer zero to set the current palette to no palette.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_DUPDD

The HDF\_DUPDD procedure generates new references to existing data in an HDF file.

## Syntax

HDF\_DUPDD, *FileHandle*, *NewTag*, *NewRef*, *OldTag*, *OldRef*

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### NewTag

An integer tag for new data descriptor.

### NewRef

An integer reference number for the new data descriptor.

### OldTag

The integer tag of data descriptor to duplicate.

### OldRef

The reference number of data descriptor to duplicate.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_EXISTS

The HDF\_EXISTS function returns True if the HDF scientific data format library is supported on the current IDL platform.

This routine is written in the IDL language. Its source code can be found in the file `hdf_exists.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

*Result* = HDF\_EXISTS()

## Return Value

Returns a 1 (True) if the library is supported or a 0 (False) if the library is not supported.

## Arguments

None

## Keywords

None

## Examples

The following IDL command prints an error message if the HDF library is not available:

```
IF HDF_EXISTS() EQ 0 THEN PRINT, 'HDF not supported.'
```

## Version History

4.0	Introduced
-----	------------

# HDF\_GR\_ATTRINFO

This function retrieves the name, data type, and number of values of the attribute for the HDF data object identified by the parameter `obj_id`.

## Syntax

*Result* = HDF\_GR\_ATTRINFO(*obj\_id*, *attr\_index*, *name*, *data\_type*, *count*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **obj\_id**

Raster image identifier (`ri_id`), returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT, or HDF GR interface identifier (`gr_id`), returned by HDF\_GR\_START.

### **attr\_index**

Index of the attribute. The value of this parameter can be obtained using HDF\_GR\_FINDATTR, HDF\_GR\_NAMETOINDEX or HDF\_GR\_REFTOINDEX, depending on available information. Valid values range from 0 to the total number of attributes attached to the object minus 1. The total number of attributes attached to the file can be obtained using the routine HDF\_GR\_FILEINFO. The total number of attributes attached to an image can be obtained using the routine HDF\_GR\_GETIMINFO.

### **name**

A named variable in which the name of the attribute is returned.

### **data\_type**

A named variable in which the attribute data type is returned. See [“IDL and HDF Data Types”](#) on page 317.

### **count**

A named variable in which the number of attributes is returned.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_GR\_CREATE

This function creates an HDF GR raster image. Once a raster image has been created, it is not possible to change its name, data type, dimension sizes or number of pixel components. However, it is possible to create a raster image and close the file before writing any data values to it. Later, the values can be added to or modified in the raster image, which then can be obtained using `HDF_GR_SELECT`.

---

**Note**

On creation, any interlace mode may be set. This mode will be used until the file is closed. If the resulting file is reopened, the interlace mode will revert to pixel-interlace (0). Data can still be read in any interlace mode using the `INTERLACE` keyword to `HDF_GR_READIMAGE`. This is a limitation of the current HDF library.

---

## Syntax

```
Result = HDF_GR_CREATE(gr_id, name, ncomp, data_type, interlace_mode,  
                        dim_sizes)
```

## Return Value

Returns a raster image identifier if successful or FAIL (-1) otherwise.

## Arguments

**gr\_id**

GR interface identifier returned by `HDF_GR_START`.

**name**

Name of the raster image. The length of the name should not be longer than 256 characters.

**ncomp**

Number of pixel components in the image. This parameter must have a value of at least 1.

## data\_type

Type of the image data. This parameter can be any of the data types supported by the HDF library. See “[IDL and HDF Data Types](#)” on page 317.

## interlace\_mode

Interlace mode of the image data. Valid values are:

- 0 = Pixel interlace
- 1 = Line interlace
- 2 = Component interlace

## dim\_sizes

Array of sizes for each dimension of the image. The dimensions must be specified and their values must be greater than 0.

## Keywords

None

## Version History

5.2	Introduced
-----	------------



# HDF\_GR\_END

This procedure terminates the HDF GR interface session identified by the parameter *gr\_id*. HDF\_GR\_END, together with HDF\_GR\_START, define the extent of a HDF GR interface session. HDF\_GR\_END disposes of the internal structures initialized by the corresponding call to HDF\_GR\_START. There must be a call to HDF\_GR\_END for each call to HDF\_GR\_START; failing to provide one may cause loss of data. HDF\_GR\_START and HDF\_GR\_END do not manage file access; use HDF\_OPEN and HDF\_CLOSE to open and close HDF files. HDF\_OPEN must be called before HDF\_GR\_START and HDF\_CLOSE must be called after HDF\_GR\_END. Failure to properly close the HDF file with HDF\_GR\_END and HDF\_CLOSE may result in lost data or corrupted HDF files.

## Syntax

HDF\_GR\_END, *gr\_id*

## Arguments

### **gr\_id**

HDF GR interface identifier returned by HDF\_GR\_START.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_ENDACCESS

This procedure terminates access to the raster image identified by the parameter *ri\_id* and disposes of the raster image identifier. This access is initiated by either HDF\_GR\_SELECT or HDF\_GR\_CREATE. There must be a call to HDF\_GR\_ENDACCESS for each call to HDF\_GR\_SELECT or HDF\_GR\_CREATE; failing to provide this will result in loss of data.

## Syntax

HDF\_GR\_ENDACCESS, *ri\_id*

## Arguments

*ri\_id*

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_FILEINFO

This function retrieves the number of raster images and the number of global attributes for the HDF GR interface identified by the parameter *gr\_id*, and stores them into the parameters *n\_images* and *n\_file\_attrs*, respectively. The term “global attributes” refers to attributes that are assigned to the file instead of individual raster images. These attributes are created by HDF\_GR\_SETATTR with the object identifier parameter set to a HDF GR interface identifier (*gr\_id*) rather than a raster image identifier (*ri\_id*). HDF\_GR\_FILEINFO is useful in finding the range of acceptable indices for HDF\_GR\_SELECT calls.

## Syntax

*Result* = HDF\_GR\_FILEINFO(*gr\_id*, *n\_images*, *n\_file\_attrs*)

## Return Value

Returns SUCCEED (or 0) if successful or FAIL (-1) otherwise.

## Arguments

### **gr\_id**

HDF GR interface identifier returned by HDF\_GR\_START.

### **n\_images**

A named variable that will contain the number of raster images in the file.

### **n\_file\_attrs**

A named variable that will contain the number of global attributes in the file.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_FINDATTR

This function finds the index of an HDF data object's attribute given its attribute name. HDF\_GR\_FINDATTR returns the index of the attribute whose name is specified by the parameter *attr\_name* for the object identified by the parameter *obj\_id*.

## Syntax

*Result* = HDF\_GR\_FINDATTR(*obj\_id*, *attr\_name*)

## Return Value

Returns the index of the attribute if successful or FAIL (-1) otherwise.

## Arguments

### **obj\_id**

Raster image identifier (*ri\_id*), returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT, or HDF GR interface identifier (*gr\_id*), returned by HDF\_GR\_START.

### **attr\_name**

Name of the attribute.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_GETATTR

This function obtains all values of the HDF GR attribute that is specified by its index, *attr\_index*, and is attached to the object identified by the parameter *obj\_id*.

## Syntax

*Result* = HDF\_GR\_GETATTR(*obj\_id*, *attr\_index*, *values*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **obj\_id**

Raster image identifier (*ri\_id*), returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT, or HDF GR interface identifier (*gr\_id*), returned by HDF\_GR\_START.

### **attr\_index**

Index of the attribute.

The value of the parameter *attr\_index* can be obtained by using HDF\_GR\_FINDATTR, HDF\_GR\_NAMETOINDEX, or HDF\_GR\_REFTOINDEX, depending on available information. Valid values of *attr\_index* range from 0 to the total number of attributes of the object - 1. The total number of attributes attached to the file can be obtained using the routine HDF\_GR\_FILEINFO. The total number of attributes attached to the image can be obtained using the routine HDF\_GR\_GETIMINFO. HDF\_GR\_GETATTR only reads all values assigned to the attribute and not a subset.

### **values**

A named variable that will contain the attribute values.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_GETCHUNKINFO

This function retrieves chunking information about the HDF GR raster image identified by the parameter *ri\_id* into the parameters *dim\_length* and *flag*. Note that only chunk dimensions are retrieved; compression information is not available with this function.

## Syntax

*Result* = HDF\_GR\_GETCHUNKINFO(*ri\_id*, *dim\_length*, *flag*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **dim\_length**

A named variable that will contain the array of chunk dimensions.

### **flag**

A named variable that will contain the compression/chunk flag.

The value returned in the parameter *flag* indicates if the raster image is not chunked, chunked, or chunked and compressed. The following table shows the possible values of the parameter *flag* and the corresponding characteristics of the raster image.

Values of flag = Raster Image Characteristics

- -1 = Not chunked
- 0 = Chunked and not compressed
- 1 = Chunked and compressed with either the run-length encoding (RLE), Skipping Huffman or GZIP compression algorithms



## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_GETIMINFO

This function retrieves general information about an HDF GR raster image. HDF\_GR\_GETIMINFO retrieves the name, number of components, data type, interlace mode, dimension sizes, and number of attributes of the raster image identified by the parameter *ri\_id*. It also retrieves the number of attributes attached to the image into the parameter *num\_attrs*.

## Syntax

```
Result = HDF_GR_GETIMINFO(ri_id, gr_name, ncomp, data_type,  
interlace_mode, dim_sizes, num_attrs)
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **gr\_name**

A named variable that will contain the name of the raster image.

### **ncomp**

A named variable that will contain the number of components in the raster image.

### **data\_type**

A named variable that will contain the data type of the raster image data. The valid values of the parameter *data\_type* are listed in “[IDL and HDF Data Types](#)” on page 317.

### **interlace\_mode**

A named variable that will contain the interlace mode of the stored raster image data.

- 0 = Pixel interlace
- 1 = Line interlace

- 2 = Component interlace

### **dim\_sizes**

A named variable that will contain the sizes of the raster image dimensions.

### **num\_attrs**

A named variable that will contain the number of attributes attached to the raster image.

## **Keywords**

None

## **Version History**

5.2	Introduced
-----	------------

# HDF\_GR\_GETLUTID

This function gets the identifier of the HDF GR palette attached to the raster image identified by the parameter *ri\_id*.

## Syntax

*Result* = HDF\_GR\_GETLUTID(*ri\_id*, *pal\_index*)

## Return Value

Returns the palette identifier if successful or FAIL (-1) otherwise.

## Arguments

### *ri\_id*

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### *pal\_index*

Index of the palette. Currently, only one palette can be assigned to a raster image, which means that *pal\_index* should always be set to 0.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_GETLUTINFO

This function retrieves the number of pixel components, data type, interlace mode, and number of color lookup table entries of the palette identified by the parameter *pal\_id*.

## Syntax

```
Result = HDF_GR_GETLUTINFO(pal_id, ncomp, data_type, interlace_mode,  
                           num_entries)
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **pal\_id**

Palette identifier returned by HDF\_GR\_GETLUTID.

### **ncomp**

A named variable in which the number of components in the palette is returned.

### **data\_type**

A named variable in which the HDF data type of the palette is returned. See [“IDL and HDF Data Types”](#) on page 317 for a description of the HDF data types.

### **interlace\_mode**

A named variable in which the interlace mode of the stored palette data is returned.

- 0 = Pixel interlace
- 1 = Line interlace
- 2 = Component interlace

### **num\_entries**

A named variable in which the number of color lookup table entries in the palette is returned.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_IDTOREF

This function returns the HDF reference number of the raster image identified by the parameter *ri\_id*. This routine is commonly used for the purpose of annotating the raster image or including the raster image within an HDF Vgroup. The tag number for a GR is 306.

## Syntax

*Result* = HDF\_GR\_IDTOREF(*ri\_id*)

## Return Value

Returns the HDF reference number of the raster image if successful or not found (0) otherwise.

## Arguments

**ri\_id**

Raster image identifier returned by HDF\_GR\_SELECT or HDF\_GR\_CREATE.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_LUTTOREF

This function returns the HDF reference number of the palette identified by the parameter *pal\_id*. This function is commonly used for the purpose of annotating the palette or including the palette within a HDF Vgroup.

## Syntax

*Result* = HDF\_GR\_LUTTOREF(*pal\_id*)

## Return Value

Returns the reference number of the palette if successful or not found (0) otherwise.

## Arguments

### **pal\_id**

Palette identifier returned by HDF\_GR\_GETLUTID.

## Keywords

None

## Version History

5.2	Introduced
-----	------------



# HDF\_GR\_NAMETOINDEX

This function returns the index of the raster image named *gr\_name* for the HDF GR interface identified by the parameter *gr\_id*.

The value of index can be passed into HDF\_GR\_SELECT to obtain the raster image identifier (*ri\_id*).

## Syntax

*Result* = HDF\_GR\_NAMETOINDEX(*gr\_id*, *gr\_name*)

## Return Value

Returns the index of the raster image if successful or FAIL (-1) otherwise.

## Arguments

### **gr\_id**

HDF\_GR\_ interface identifier returned by HDF\_GR\_START.

### **gr\_name**

Name of the raster image.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_READIMAGE

This function reads the subsample of the HDF GR raster image specified by the parameter *ri\_id* into the variable *data*.

## Syntax

```
Result = HDF_GR_READIMAGE( ri_id, data [, EDGE=array] [, /INTERLACE]  
[, START=array] [, STRIDE=array] )
```

## Return Value

Returns the specified variable containing the image subsample.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT

### **data**

A named variable that will contain the image data.

## Keywords

### **EDGE**

Array specifying the number of values to be read along each dimension. The default is to read the entire specified image.

### **INTERLACE**

Set this keyword to force data to be returned in INTERLACE mode. The default is pixel-interlacing (0) other possible values are 1 (line) and 2 (component).

### **START**

Array specifying the starting location from where raster image data is read. Valid values of each element in the array are 0 to the size of the corresponding raster image dimension minus 1. The default is to read starting at the first pixel in each dimension (start = [0,0]).

## STRIDE

Array specifying the interval between the values that will be read along each dimension. The default is for contiguous reading along each dimension (stride = [1,1]).

---

### Note

The correspondence between the elements in the array *start* and the array *data* dimensions in the HDF GR interface is different from that in the HDF SD interface. The array *stride* specifies the reading pattern along each dimension. For example, if one of the elements of the array *stride* is 1, then every element along the corresponding dimension of the array *data* will be read. If one of the elements of the array *stride* is 2, then every other element along the corresponding dimension of the array *data* will be read, and so on. The correspondence between elements of the array *stride* and the dimensions of the array *data* is the same as described above for the array *start*. Each element of the array *edges* specifies the number of data elements to be read along the corresponding dimension. The correspondence between the elements of the array *edges* and the dimensions of the array *data* is the same as described above for the array *start*.

---

## Version History

---

5.2	Introduced
-----	------------

---

# HDF\_GR\_READLUT

This function reads the palette specified by the parameter *pal\_id* into the *pal\_data* variable.

## Syntax

```
Result = HDF_GR_READLUT( pal_id, pal_data [, /INTERLACE] )
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### pal\_id

Palette identifier returned by HDF\_GR\_GETLUTID.

### pal\_data

A named variable that will contain the palette data.

## Keywords

### INTERLACE

Set this keyword to force *pal\_data* to be returned in INTERLACE mode. The default is pixel-interlacing (0) other possible values are 1 (line) and 2 (component).

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_REFTOINDEX

This function returns the index of the HDF GR raster image specified by the parameter *gr\_ref*.

## Syntax

*Result* = HDF\_GR\_REFTOINDEX(*gr\_id*, *gr\_ref*)

## Return Value

Returns the index of the image if successful or FAIL (-1) otherwise.

## Arguments

### **gr\_id**

HDF GR interface identifier returned by HDF\_GR\_START.

### **gr\_ref**

Reference number of the raster image.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_SELECT

This function obtains the identifier of the HDF GR raster image specified by its index.

## Syntax

*Result* = HDF\_GR\_SELECT(*gr\_id*, *index*)

## Return Value

Returns the raster image identifier if successful or FAIL (-1) otherwise.

## Arguments

### **gr\_id**

HDF GR interface identifier returned by HDF\_GR\_START.

### **index**

Index of the raster image in the file. Valid values range from 0 to the total number of raster images in the file minus 1. The total number of the raster images in the file can be obtained by using HDF\_GR\_FILEINFO.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_SETATTR

This function attaches the attribute to the HDF GR object specified by the parameter *obj\_id*. The attribute is defined by its name, data type, number of attribute values, and the attribute values. `HDF_GR_SETATTR` provides a generic way for users to define metadata. It implements the label = value data abstraction. If an HDF GR interface identifier (*gr\_id*) is specified as the parameter *obj\_id*, a global attribute is created that applies to all objects in the file. If a raster image identifier (*ri\_id*) is specified as the parameter *obj\_id*, an attribute is attached to the specified raster image. Attribute values are passed in the parameter values. The number of attribute values is defined by the parameter count. If more than one value is stored, all values must have the same data type. If an attribute with the given name, data type and number of values exists, it will be overwritten. Currently, the only predefined attribute is the fill value, identified by the attribute name “FillValue”.

## Syntax

*Result* = `HDF_GR_SETATTR(obj_id, attr_name, data_type, count, values)`

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **obj\_id**

Raster image identifier (*ri\_id*), returned by `HDF_GR_CREATE` or `HDF_GR_SELECT` or HDF GR interface identifier (*gr\_id*), returned by `HDF_GR_START`.

### **attr\_name**

Name of the attribute (string).

### **data\_type**

Data type of the attribute (integer). Can be any data type supported by the HDF library. These data types are listed under “[IDL and HDF Data Types](#)” on page 317.

**count**

Number of values in the attribute.

**values**

The attribute value.

**Keywords**

None

**Version History**

5.2	Introduced
-----	------------



# HDF\_GR\_SETCHUNK

This function makes the HDF GR raster image specified by the parameter *ri\_id* a chunked raster image according to the chunking and compression information provided in the parameters *comp\_type* and *comp\_prm*. Data can be compressed using run-length encoding (RLE), Skipping Huffman or GZIP compression algorithms.

## Syntax

*Result* = HDF\_GR\_SETCHUNK(*ri\_id*, *dim\_length*, *comp\_type*, *comp\_prm*)

## Return Value

Returns SUCCEED (or 0) if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **dim\_length**

Chunk dimensions array.

### **comp\_type**

Type of compression. Valid types are:

- 0 = uncompressed data
- 1 = data compressed using the RLE compression algorithm
- 3 = data compressed using the Skipping Huffman compression algorithm
- 4 = data compressed using the GZIP compression algorithm.

### **comp\_prm**

Compression parameters array. Specifies the compression parameters for the Skipping Huffman and GZIP compression methods. It contains only one element, which is set to the skipping size for Skipping Huffman compression or the deflate level for GZIP compression (1-9).

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_SETCHUNKCACHE

This function allows the user to set the maximum number of chunks to be cached (*maxcache*). If HDF\_GR\_SETCHUNKCACHE is not called, *maxcache* is set to the number of chunks along the fastest changing dimension.

## Syntax

*Result* = HDF\_GR\_SETCHUNKCACHE(*ri\_id*, *maxcache*, *flags*)

## Return Value

Returns the value of *maxcache* if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **maxcache**

Maximum number of chunks to cache.

### **flags**

Currently, the only HDF allowed value for flags is zero (cache all).

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_SETCOMPRESS

This function specifies the type of compression for the specified HDF GR raster image.

## Syntax

*Result* = HDF\_GR\_SETCOMPRESS(*ri\_id*, *comp\_type*, *comp\_prm*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **comp\_type**

Compression method for the image data. Valid values are:

- 0 = no compression
- 1 = RLE run-length encoding
- 3 = Skipping Huffman compression
- 4 = GZIP compression
- 6 = JPEG compression

### **comp\_prm**

Compression parameters. If Skipping Huffman is used, set *comp\_parm* to the skipping size (the size in bytes of the data elements). If GZIP compression is used, set *comp\_parm* to an integer ranging from 1 (fastest) to 9 (most compressed).

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_SETEXTTERNALFILE

This function causes the specified HDF GR raster image be written to the specified external file, at the specified offset. Data can be moved only once for any given raster image, and it is the user's responsibility to make sure the external data file is kept with the “original” file. If the raster image already exists, its data will be moved to the external file. Space occupied by the data in the primary file will not be released. If the raster image does not exist, its data will be written to the external file during the subsequent calls to HDF\_GR\_WRITEDATA.

## Syntax

*Result* = HDF\_GR\_SETEXTTERNALFILE(*ri\_id*, *filename*, *offset*)

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### **ri\_id**

Raster image identifier returned by HDF\_GR\_CREATE or HDF\_GR\_SELECT.

### **filename**

Name of the external file.

### **offset**

Offset in bytes from the beginning of the external file to where the data will be written.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_START

This function initializes the HDF GR interface for the specified file. This function is used with the HDF\_GR\_END procedure to define the extent of the HDF GR interface session. As with the start routines in the other interfaces, HDF\_GR\_START initializes the internal interface structures needed for the remaining HDF\_GR\_ routines. Use the general purpose routines HDF\_OPEN and HDF\_CLOSE to manage file access. The HDF\_GR\_ routines will not open and close HDF files.

**Note**

Failure to use HDF\_CLOSE properly may result in lost data or corrupted HDF files.

## Syntax

*Result* = HDF\_GR\_START(*file\_id*)

## Return Value

Returns the HDF GR interface identifier if successful or FAIL (-1) otherwise.

## Arguments

**file\_id**

File identifier returned by HDF\_OPEN.

## Keywords

None

## Version History

5.2	Introduced
-----	------------



# HDF\_GR\_WRITEIMAGE

This function writes the subsample of the raster image data stored in the variable `data` to the specified raster image. The subsample is defined by the values of the parameters `start`, `stride` and `edge`. The array `start` specifies the starting location of the subsample to be written. Valid values of each element in the array `start` are 0 to the size of the corresponding raster image dimension - 1.

## Note

---

The correspondence between elements in the array `start` and the raster image dimensions in the HDF GR interface is different from that in the HDF SD interface. The array `stride` specifies the writing pattern along each dimension. For example, if one of the elements of the array `stride` is 1, then every element along the corresponding dimension of the array data will be written. If one of the elements of the stride array is 2, then every other element along the corresponding dimension of the array data will be written, and so on. The correspondence between elements of the array `stride` and the dimensions of the array data is the same as described above for the array `start`. Each element of the array `edges` specifies the number of data elements to be written along the corresponding dimension. The correspondence between the elements of the array `edges` and the dimensions of the array data is the same as described above for the array `start`.

---

## Syntax

```
Result = HDF_GR_WRITEIMAGE( ri_id, data [, EDGE=array]
    [, INTERLACE={0 | 1 | 2}] [, START=array] [, STRIDE=array] )
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### `ri_id`

Raster image identifier returned by `HDF_GR_CREATE` or `HDF_GR_SELECT`.

### `data`

The image data to be written.

## Keywords

### EDGE

Array containing the number of data elements that will be written along each dimension. If not specified, all data will be written.

### INTERLACE

Set this keyword to a scalar value to select the interlace mode of the input data. Valid values are:

- 0 = Pixel interlace
- 1 = Line interlace
- 2 = Component interlace

HDF\_GR\_WRITEIMAGE will write the data in the correct interlace mode the raster image is in.

### START

Array containing the two-dimensional coordinate of the initial location for the write. If not specified, the write starts at the first pixel in each dimension (start=[0,0]).

### STRIDE

Array containing the number of data locations the current location is to be moved forward before each write. If not specified, data is written contiguously (stride = [1,1]).

#### Note

---

See [HDF\\_GR\\_READIMAGE](#) for further description of the EDGE, START, and STRIDE keywords.

---

## Version History

5.2	Introduced
-----	------------

# HDF\_GR\_WRITE Lut

This function writes a palette with the specified palette data and identifier. The palette data itself is stored in the *pal\_data* variable. The data types supported by HDF are listed in “[IDL and HDF Data Types](#)” on page 317.

## Syntax

```
Result = HDF_GR_WRITE Lut( pal_id, pal_data )
```

## Return Value

Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

## Arguments

### pal\_id

Palette identifier returned by HDF\_GR\_GET LutID.

### pal\_data

Palette data to be written.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# HDF\_HDF2IDLTYPE

This function converts an HDF data type code into an IDL variable type code. See the IDL `SIZE` function and tables 3-2 through 3-4 in *Scientific Data Formats* for actual values.

## Syntax

*Result* = HDF\_HDF2IDLTYPE( *hdfstypecode* )

## Return Value

Returns the IDL variable type code (See `SIZE`). A return value of zero means the type could not be mapped.

## Arguments

### **hdfstypecode**

An HDF data type code (long).

## Keywords

None

## Examples

```
PRINT, HDF_HDF2IDLTYPE( 6 )
```

## Version History

5.2	Introduced
-----	------------

## See Also

[HDF\\_IDL2HDFTYPE](#)

# HDF\_IDL2HDFTYPE

This function converts an IDL variable type code into an HDF data type code. See the IDL `SIZE` function and tables 3-2 through 3-4 in *Scientific Data Formats* for actual values.

## Syntax

```
Result = HDF_IDL2HDFTYPE( idltypecode )
```

## Return Value

Returns the HDF data type code. A return value of zero means the type could not be mapped.

## Arguments

### **idltypecode**

An IDL variable type code (long).

## Keywords

None

## Examples

```
iType = SIZE(5.0d, /TYPE)  
PRINT, HDF_IDL2HDFTYPE( iType )
```

## Version History

5.2	Introduced
-----	------------

## See Also

[HDF\\_HDF2IDLTYPE](#)

# HDF\_ISHDF

The HDF\_ISHDF function determines whether or not a specified file is an HDF file.

## Warning

---

This routine bases its judgement as to whether or not a file is an HDF file on the first few bytes of the file. Therefore, it is possible that HDF\_ISHDF will identify the file as an HDF file, but HDF\_OPEN will not be able to open the file (because it is corrupted).

---

## Syntax

*Result* = HDF\_ISHDF(*Filename*)

## Return Value

Returns true (1) if the file is an HDF file and false (0) if the file either is not an HDF file or does not exist.

## Arguments

### Filename

A scalar string containing the name of the file to be tested.

## Keywords

None

## Version History

Pre 4.0	Introduced
---------	------------

# HDF\_LIB\_INFO

The `HDF_LIB_INFO` procedure returns information about the HDF Library being used by this version of IDL, or information about the version of HDF used to create a particular HDF file.

## Syntax

```
HDF_LIB_INFO, [FileHandle] [, MAJOR=variable] [, MINOR=variable]  
[, RELEASE=variable] [, VERSION=variable]
```

## Arguments

### FileHandle

The HDF filehandle returned from a previous call to `HDF_OPEN`.

## Keywords

### MAJOR

Set this keyword equal to a named variable that will contain the major version number of the HDF library currently in use by IDL. If the *FileHandle* argument is supplied, the variable will contain the major version number of the HDF library used by that particular HDF file.

### MINOR

Set this keyword equal to a named variable that will contain the minor version number of the HDF library currently in use by IDL. If the *FileHandle* argument is supplied, the variable will contain the minor version number of the HDF library used by that particular HDF file.

### RELEASE

Set this keyword equal to a named variable that will contain the release number of the HDF library currently in use by IDL. If the *FileHandle* argument is supplied, the variable will contain the release number of the HDF library used by that particular HDF file.

## VERSION

Set this keyword equal to a named variable that will contain the version number text string of the HDF library currently in use by IDL. If the *FileHandle* argument is supplied, the variable will contain the version number text string of the HDF library used by that particular HDF file.

## Examples

### Example 1

```
HDF_LIB_INFO, MAJOR=MAJOR, MINOR=MINOR, VERSION=VER, RELEASE=REL
PRINT, 'IDL ', !version.release, ' uses HDF Library ', $
      MAJOR, MINOR, REL, FORMAT='(A,A,A,I1,".",I1,"r",I1,A)'
PRINT, VER
```

#### IDL Output

```
IDL 5.3 uses HDF Library 4.1r3
NCSA HDF Version 4.1 Release 3, May 1999
```

### Example 2

The following example tests the version of HDF used to create a particular file. Note that the strings returned will depend solely upon the version of the HDF library used to create the file. In this example, it is the same as the library compiled into the current version of IDL since it is the current IDL that is creating the file.

```
file='example.hdf'
id=HDF_OPEN(file, /CREATE)
HDF_LIB_INFO, id, VERSION=VER
PRINT, 'The file ', file, ' was created with : ', VER
HDF_CLOSE, id
```

#### IDL Output

```
The file example.hdf was created with :
NCSA HDF Version 4.1 Release 3, May 1999
```

## Version History

5.1	Introduced
-----	------------



# HDF\_NEWREF

The HDF\_NEWREF function returns the next available reference number for an HDF file.

## Syntax

*Result* = HDF\_NEWREF(*FileHandle*)

## Return Value

Returns the next available reference number.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

## Keywords

None

## Version History

Pre 4.0	Introduced
---------	------------

# HDF\_NUMBER

The `HDF_NUMBER` function returns the number of tags in an HDF file or the number of references associated with a given tag.

## Syntax

```
Result = HDF_NUMBER( FileHandle [, TAG=integer] )
```

## Return Value

Returns either the number of tags in the file or the number of references associated with the specified tag.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to `HDF_OPEN`.

## Keywords

### TAG

Set this keyword to an integer tag number or the string `'*'`. If this keyword is set to a tag number, `HDF_NUMBER` returns the number of references associated with the given tag. If this keyword is set to the string `'*'`, or is not specified, `HDF_NUMBER` returns the total number of tags in the HDF file.

## Version History

Pre 4.0	Introduced
---------	------------

# HDF\_OPEN

The HDF\_OPEN function opens or creates an HDF file for reading and/or writing. Note that any combination of the READ, WRITE and CREATE keywords is valid.

## Syntax

```
Result = HDF_OPEN( Filename [, /ALL] [, /CREATE] [, NUM_DD=value]  
                  [, /RDWR] [, /READ] [, /WRITE] )
```

## Return Value

If successful, a non-zero file handle (a longword integer) is returned. Longword -1 is returned on failure.

## Arguments

### Filename

A scalar string containing the name of the file to be opened.

## Keywords

### ALL

Set this keyword to create a new HDF file with read and write access. Setting this keyword is equivalent to:

```
HDF_OPEN(filename, /READ, /WRITE, /CREATE)
```

### CREATE

Set this keyword to create a new HDF file.

### NUM\_DD

Use this keyword to override the machine default for the number of data descriptors to be allocated per DD block. For example:

```
H = HDF_OPEN('foo.hdf', /CREATE, /WRITE, NUM_DD=100)
```

## RDWR

Set this keyword to open file with both read and write access. Setting this keyword is equivalent to:

```
HDF_OPEN(filename, /READ, /WRITE)
```

## READ

Set this keyword to open the file with read access.

## WRITE

Set this keyword to open the file with write access.

## Version History

Pre 4.0	Introduced
---------	------------

# HDF\_PACKDATA

This function packs a set IDL variable into an array of raw byte data. It is useful in constructing the input to multi-field HDF Vdata writing routines, such as those found in HDF-EOS, from a set of IDL variables. The packed data is output as an array of bytes which is organized as a number of records. Each record consists of one or more data fields. A record is defined using the `HDF_TYPE` and `HDF_ORDER` keywords. These define the record layout in terms of HDF data types. This function first converts the input arrays into the type defined by the `HDF_TYPE` keyword using IDL type conversion rules. The function then walks through the input IDL arrays and copies the values into output array. There must be as many entries in the `HDF_TYPE` and `HDF_ORDER` keywords as there are data arguments. The function will output as many complete records as can be created from the input data arrays or the value of the `NREC` keyword, whichever is smaller.

## Syntax

```
Result = HDF_PACKDATA( data1 [, data2 [, data3 [, data4 [, data5 [, data6  
    [, data7 [, data8]]]]]] [, HDF_ORDER=array] [, HDF_TYPE=array]  
    [, NREC=records] )
```

## Return Value

Returns a 2-D BYTE array of packed data. The trailing dimension corresponds to each record in the input data.

## Arguments

### data1...data8

These arguments specify IDL arrays to be packed. The arguments are first converted to the types specified by `HDF_TYPE`. If the corresponding `HDF_ORDER` value is greater than one, more than one value will be read from the input array and placed in the packed array for each record. Strings are output as fixed width fields. If an input string is longer than its `HDF_ORDER` value, it is truncated before being packed. If an input string is shorter than its `HDF_ORDER` value, the extra space is filled with the value 0.

## Keywords

### HDF\_ORDER

Set this keyword to an array the same length as the number of data fields. The value in the array is equal to the number of elements in the data argument for each record. In the case of strings, this is the length (in characters) of the string to be packed. A value of zero is interpreted as one element. The default for this keyword is an array of ones.

### HDF\_TYPE

Set this keyword to an array the same length as the number of data fields. The value in the array is an HDF data type for each argument. The IDL variables are converted to these types before being packed into the output array. The default for this keyword is an array of the value 5 (an HDF 32 bit float). See “[IDL and HDF Data Types](#)” on page 317 for valid values.

### NREC

Set this keyword to the number of records to be packed. The default is to pack as many complete records as can be formed by all of the input arrays.

## Examples

See [HDF\\_UNPACKDATA](#).

## Version History

5.2	Introduced
-----	------------

## See Also

[HDF\\_UNPACKDATA](#), [EOS\\_PT\\_WRITELEVEL](#), [HDF\\_VD\\_WRITE](#)

# HDF\_READ

See [HDF\\_READ](#) in the *IDL Reference Guide*.

# HDF\_SD\_ADDDATA

The `HDF_SD_ADDDATA` procedure writes a hyperslab of values to an SD dataset. By default, the output data is transposed. This transposition puts the data in column order, which is more efficient in HDF than row order (which is more efficient in IDL). In the rare cases where it is necessary to write the data without transposing, set the `NOREVERSE` keyword. The `OFFSET`, `COUNT`, and `STRIDE` keywords are similarly affected by the `NOREVERSE` keyword.

## Syntax

```
HDF_SD_ADDDATA, SDdataset_id, Data [, COUNT=vector] [, /NOREVERSE]
  [, START=vector] [, STRIDE=vector]
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by `HDF_SD_SELECT` or `HDF_SD_CREATE`.

### Data

The data to be written.

## Keywords

### COUNT

Set this keyword to a vector of counts (i.e., the number of items) to be written in each dimension. The default is to write all available data. Use caution when using this keyword. See the second example, below.

### NOREVERSE

Set this keyword to prevent `HDF_SD_ADDDATA`'s transposition of *Data* and any vectors specified by keywords into column order.

### START

Set this keyword to a vector that contains the starting position for the data. The default position is `[0, 0, ..., 0]`.



## STRIDE

Set this keyword to a vector that contains the strides, or sampling intervals, between accessed values of the NetCDF variable. The default stride vector is that for a contiguous write: [0, 0, ..., 0].

## Examples

The following example writes a 230-element by 380-element byte image to an SD dataset, then reads it back as a 70 by 100 image starting at (40, 20), sampling every other Y pixel and every third X pixel:

```

start = [40, 20] ; Set the start vector.
count = [70, 100] ; Set the count vector.
stride = [2, 3] ; Set the stride vector.
image = DIST(230, 380) ; Create the image.
TV, image ; Display the image.
; Create a new HDF file in SD mode:
SDinterface_id = HDF_SD_START('image.hdf', /CREATE)
; Define a new SD dataset:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'image', [230, 380],
/BYTE)
HDF_SD_ADDDATA, SDdataset_id, image ; Write the image into the
dataset.
HDF_SD_GETDATA, SDdataset_id, full ; Retrieve the full image.
; Retrieve the sub-sampled image:
HDF_SD_GETDATA, SDdataset_id, small, COUNT=count, $
    START=start, STRIDE=stride
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id
HELP, full, small ; Print information about the images.
ERASE ; Erase the window.
TV, full ; Display the full image.
TV, small ; Display the sub-sampled image.

```

IDL prints:

```

FULL   BYTE = Array(230, 380)
SMALL  BYTE = Array(70, 100)

```

Continuing with our example, suppose we want to write the center 50 by 100 pixels of the image to the file. You might be tempted to try:

```

HDF_SD_ADDDATA, SDdataset_id, image, START=[90, 90],
COUNT=[50,100]

```

You will find, however, that this captures the lower left-hand corner of the original image, rather than the center. To write the data from the center, subset the original image, choosing the data from the center:

```
HDF_SD_ADDDATA, SDdataset_id, image(90:139, 90:189), START=[90,
90],$
    COUNT=[50,100] ; This is the correct way to add the data.
HDF_SD_ENDACCESS, SDdataset_id ; End SD access.
HDF_SD_END, SDinterface_id ; Close the file.
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_GETDATA](#)

# HDF\_SD\_ATTRFIND

The `HDF_SD_ATTRFIND` function locates the index of an HDF attribute given its name. The attribute can be global or from a specific dataset. If an attribute is located, its index is returned. Otherwise, -1 is returned. Once an attribute's index is known, the `HDF_SD_ATTRINFO` function can be used to read that attribute.

## Syntax

*Result* = `HDF_SD_ATTRFIND(SD_id, Name)`

## Arguments

### SD\_id

An SD interface ID as returned by `HDF_SD_START` (i.e., a global attribute's "SDinterface\_id"), or `HDF_SD_SELECT/HDF_SD_CREATE` (i.e., a dataset's "SDdataset\_id").

### Name

A string containing the name of the attribute whose index is to be returned.

## Keywords

None

## Examples

```

; Open an HDF file and start the SD interface:
SDinterface_id = HDF_SD_START('demo.hdf')
; Find "TITLE", a global attribute:
gindex = HDF_SD_ATTRFIND(SDinterface_id, 'TITLE')
; Get the ID for the first dataset:
SDdataset_id = HDF_SD_SELECT(SDinterface_id, 1)
; Read attribute info:
HDF_SD_ATTRINFO,SDinterface_id,gindex, NAME=name, TYPE=type,
COUNT=count
; Print info about the returned variables:
HELP, type, count, name
; Find the "LOCATION" dataset attribute:
dindex = HDF_SD_ATTRFIND(SDdataset_id, 'LOCATION')
; Read attribute info:

```

```
HDF_SD_ATTRINFO, SDDataset_id, dindex, NAME=name, TYPE=type, COUNT=count
```

### IDL Output

```
TYPE STRING = 'STRING'  
COUNT LONG = 8  
NAME STRING = 'TITLE'
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_ATTRINFO](#), [HDF\\_SD\\_ATTRSET](#), [HDF\\_SD\\_SELECT](#)

# HDF\_SD\_ATTRINFO

The `HDF_SD_ATTRINFO` procedure reads or retrieves information about an SD attribute. The attribute can be global or from a specific dataset. If an attribute is not present, an error message is printed.

## Syntax

```
HDF_SD_ATTRINFO, SD_id, Attr_Index [, COUNT=variable] [, DATA=variable]
  [, HDF_TYPE=variable] [, NAME=variable] [, TYPE=variable]
```

## Arguments

### SD\_id

An SD interface ID as returned by `HDF_SD_START` (i.e., a global attribute's "SDinterface\_id"), or `HDF_SD_SELECT/HDF_SD_CREATE` (i.e., a dataset's "SDdataset\_id").

### Attr\_Index

The attribute index, can either be obtained by calling `HDF_SD_ATTRFIND` if a particular attribute name is known or can be obtained with a 0-based index sequentially referencing the attribute.

## Keywords

### COUNT

Set this keyword to a named variable in which the total number of values in the specified attribute is returned.

### DATA

Set this keyword to a named variable in which the attribute data is returned.

### HDF\_TYPE

Set this keyword to a named variable in which the HDF type of the attribute is returned as a scalar string. Possible returned values are `DFNT_NONE`, `DFNT_CHAR8`, `DFNT_FLOAT32`, `DFNT_FLOAT64`, `DFNT_INT8`,

DFNT\_INT16, DFNT\_INT32, DFNT\_UINT8, DFNT\_UINT16, and DFNT\_UINT32. (See “[IDL and HDF Data Types](#)” on page 317 for valid values.)

## NAME

Set this keyword to a named variable in which the name of the attribute is returned.

## TYPE

Set this keyword to a named variable in which the IDL type of the attribute is returned as a scalar string. Possible returned values are BYTE, INT, LONG, FLOAT, DOUBLE, STRING, or UNKNOWN.

## Examples

```

; Open an HDF file and start the SD interface:
SDinterface_id = HDF_SD_START('demo.hdf')
; Find a global attribute:
gindex = HDF_SD_ATTRFIND(SDinterface_id, 'TITLE')
; Retrieve attribute info:
HDF_SD_ATTRINFO, SDinterface_id, gindex, NAME=n, TYPE=t, $
    COUNT=c, DATA=d, HDF_TYPE=h
; Print information about the returned variables:
HELP, n, t, c, h
; Return the SD dataset ID for the first dataset (index 0):
SDdataset_id = HDF_SD_SELECT(SDinterface_id, 0)
; Find a dataset attribute:
dindex = HDF_SD_ATTRFIND(SDdataset_id, 'LOCATION')
; Retrieve attribute info:
HDF_SD_ATTRINFO, SDdataset_id, dindex, NAME=n, TYPE=t, $
    COUNT=c, DATA=d
; Print information about the new returned variables:
HELP, n, t, c, d

```

## IDL Output

```

N STRING = 'TITLE'
T STRING = 'STRING'
C LONG = 17
D STRING = '5th Ave Surf Shop'
H STRING = 'DFNT_CHAR8'

N STRING = 'LOCATION'
T STRING = 'STRING'
C LONG = 15
D STRING = 'MELBOURNE BEACH'

```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_ATTRFIND](#), [HDF\\_SD\\_ATTRSET](#), [HDF\\_SD\\_CREATE](#),  
[HDF\\_SD\\_SELECT](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_ATTRSET

The `HDF_SD_ATTRSET` procedure writes attributes to an open HDF SD dataset. If no data type is specified, the data type is taken from the *Values* argument.

## Syntax

```
HDF_SD_ATTRSET, SD_id, Attr_Name, Values [, Count] [, /BYTE]
  [, /DFNT_CHAR] [, /DFNT_FLOAT32] [, /DFNT_FLOAT64] [, /DFNT_INT8]
  [, /DFNT_INT16] [, /DFNT_INT32] [, /DFNT_UINT8] [, /DFNT_UINT16]
  [, /DFNT_UINT32] [, /DOUBLE] [, /FLOAT] [, /INT] [, /LONG] [, /SHORT]
  [, /STRING]
```

## Arguments

### SD\_id

An SD interface ID as returned by `HDF_SD_START` (i.e., a global attribute's "SDinterface\_id"), or `HDF_SD_SELECT/HDF_SD_CREATE` (i.e., a dataset's "SDdataset\_id").

### Attr\_Name

A string containing the name of the attribute to be written.

### Values

The attribute values to be written.

### Count

An optional integer argument specifying how many items are to be written. Count must be less than or equal to the number of elements in the *Values* argument.

## Keywords

### BYTE

Set this keyword to indicate that the attribute is composed of bytes. Data will be stored with the HDF `DFNT_UINT8` data type. Setting this keyword is the same as setting the `DFNT_UINT8` keyword.



## **DFNT\_CHAR**

Set this keyword to create an attribute of HDF type DFNT\_CHAR. Setting this keyword is the same as setting the STRING keyword.

## **DFNT\_FLOAT32**

Set this keyword to create an attribute of HDF type DFNT\_FLOAT32. Setting this keyword is the same as setting the FLOAT keyword.

## **DFNT\_FLOAT64**

Set this keyword to create an attribute of HDF type DFNT\_FLOAT64. Setting this keyword is the same as setting the DOUBLE keyword.

## **DFNT\_INT8**

Set this keyword to create an attribute of HDF type DFNT\_INT8.

## **DFNT\_INT16**

Set this keyword to create an attribute of HDF type DFNT\_INT16. Setting this keyword is the same as setting either the INT keyword or the SHORT keyword.

## **DFNT\_INT32**

Set this keyword to create an attribute of HDF type DFNT\_INT32. Setting this keyword is the same as setting the LONG keyword.

## **DFNT\_UINT8**

Set this keyword to create an attribute of HDF type DFNT\_UINT8. Setting this keyword is the same as setting the BYTE keyword.

## **DFNT\_UINT16**

Set this keyword to create an attribute of HDF type DFNT\_UINT16.

## **DFNT\_UINT32**

Set this keyword to create an attribute of HDF type DFNT\_UINT32.

## DOUBLE

Set this keyword to indicate that the attribute is composed of double-precision floating-point values. Data will be stored with the HDF DFNT\_FLOAT64 data type. Setting this keyword is the same as setting the DFNT\_FLOAT64 keyword.

## FLOAT

Set this keyword to indicate that the attribute is composed of single-precision floating-point values. Data will be stored with the HDF DFNT\_FLOAT32 data type. Setting this keyword is the same as setting the DFNT\_FLOAT32 keyword.

## INT

Set this keyword to indicate that the attribute is composed of 2-byte integers. Data will be stored with the HDF DFNT\_INT16 data type. Setting this keyword is the same as setting either the SHORT keyword or the DFNT\_INT16 keyword.

## LONG

Set this keyword to indicate that the attribute is composed of longword integers. Data will be stored with the HDF DFNT\_INT32 data type. Setting this keyword is the same as setting the DFNT\_INT32 keyword.

## SHORT

Set this keyword to indicate that the attribute is composed of 2-byte integers. Data will be stored with the HDF DFNT\_INT16 data type. Setting this keyword is the same as setting either the INT keyword or the DFNT\_INT16 keyword.

## STRING

Set this keyword to indicate that the attribute is composed of strings. Data will be stored with the HDF DFNT\_CHAR8 data type. Setting this keyword is the same as setting the DFNT\_CHAR8 keyword.

## Examples

```
fid = HDF_OPEN('demo.hdf', /ALL) ; Create a new HDF file.
SDinterface_id = HDF_SD_START('demo.hdf', /RDWR) ; Start the SD
interface.
; Create a global attribute:
HDF_SD_ATTRSET, SDinterface_id, 'TITLE', 'MY TITLE GLOBAL', 16
; Create another global attribute:
HDF_SD_ATTRSET, SDinterface_id, 'RANGE', [-99.88,55544.2], /DOUBLE
```

```

; Create a dataset:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'var1', [10,20],
/FLOAT)
; Add a dataset attribute:
HDF_SD_ATTRSET, SDdataset_id, 'TITLE', 'MY TITLE SDinterface_id',
15
; Find the recently-created RANGE attribute:
index=HDF_SD_ATTRFIND(SDinterface_id, 'RANGE')
; Retrieve data from RANGE:
HDF_SD_ATTRINFO,SDinterface_id,index,NAME=atn,COUNT=atc,TYPE=att,D
ATA=d
; Print information about the returned variables:
HELP, atn, atc, att
; Print the data returned in variable d with the given format:
PRINT, d, FORMAT='(F8.2,x,F8.2)'
HDF_SD_ENDACCESS, SDdataset_id ; End access to the HDF file.
HDF_SD_END, SDinterface_id
HDF_CLOSE, fid

```

### IDL Output

```

ATN STRING = 'RANGE'
ATC LONG = 2
ATT STRING = 'DOUBLE'

-99.88 55544.20

```

## Version History

4.0	Introduced
-----	------------

### See Also

[HDF\\_SD\\_ATTRFIND](#), [HDF\\_SD\\_ATTRINFO](#), [HDF\\_SD\\_CREATE](#),  
[HDF\\_SD\\_SELECT](#)

# HDF\_SD\_CREATE

The `HDF_SD_CREATE` function creates and defines a Scientific Dataset (SD) for an HDF file. Keywords can be set to specify the data type. If no keywords are present a floating-point dataset is created.

## Syntax

```
Result = HDF_SD_CREATE( SDinterface_id, Name, Dims [, /BYTE]
    [, /DFNT_CHAR8] [, /DFNT_FLOAT32] [, /DFNT_FLOAT64] [, /DFNT_INT8]
    [, /DFNT_INT16] [, /DFNT_INT32] [, /DFNT_UINT8] [, /DFNT_UINT16]
    [, /DFNT_UINT32] [, /DOUBLE] [, /FLOAT] [, HDF_TYPE=type] [, /INT]
    [, /LONG] [, /SHORT] [, /STRING] )
```

## Return Value

The returned value of this function is the SDS ID of the newly-created dataset.

## Arguments

### SDinterface\_id

An SD ID as returned by `HDF_SD_START`.

### Name

A string containing the name of the variable to be created.

### Dims

A 1-based vector specifying the dimensions of the variable. If an UNLIMITED dimension is desired, set the last vector element to zero or a negative number.

## Keywords

### BYTE

Set this keyword to indicate that the dataset is composed of bytes. Data will be stored with the HDF `DFNT_UINT8` data type. Setting this keyword is the same as setting the `DFNT_UINT8` keyword.

## **DFNT\_CHAR8**

Set this keyword to create a data set of HDF type DFNT\_CHAR8. Setting this keyword is the same as setting the STRING keyword.

## **DFNT\_FLOAT32**

Set this keyword to create a data set of HDF type DFNT\_FLOAT32. Setting this keyword is the same as setting the FLOAT keyword.

## **DFNT\_FLOAT64**

Set this keyword to create a data set of HDF type DFNT\_FLOAT64. Setting this keyword is the same as setting the DOUBLE keyword.

## **DFNT\_INT8**

Set this keyword to create a data set of HDF type DFNT\_INT8.

## **DFNT\_INT16**

Set this keyword to create a data set of HDF type DFNT\_INT16. Setting this keyword is the same as setting either the INT keyword or the SHORT keyword.

## **DFNT\_INT32**

Set this keyword to create a data set of HDF type DFNT\_INT32. Setting this keyword is the same as setting the LONG keyword.

## **DFNT\_UINT8**

Set this keyword to create a data set of HDF type DFNT\_UINT8. Setting this keyword is the same as setting the BYTE keyword.

## **DFNT\_UINT16**

Set this keyword to create a data set of HDF type DFNT\_UINT16.

## **DFNT\_UINT32**

Set this keyword to create a data set of HDF type DFNT\_UINT32.

## DOUBLE

Set this keyword to indicate that the dataset is composed of double-precision floating-point values. Data will be stored with the HDF DFNT\_FLOAT64 data type. Setting this keyword is the same as setting the DFNT\_FLOAT64 keyword.

## FLOAT

Set this keyword to indicate that the dataset is composed of single-precision floating-point values. Data will be stored with the HDF DFNT\_FLOAT32 data type. Setting this keyword is the same as setting the DFNT\_FLOAT32 keyword.

## HDF\_TYPE

Set this keyword to the type of data set to create. Valid values are: DFNT\_CHAR8, DFNT\_FLOAT32, DFNT\_FLOAT64, DFNT\_INT8, DFNT\_INT16, DFNT\_INT32, DFNT\_UINT8, DFNT\_UINT16, DFNT\_UINT32. (See “[IDL and HDF Data Types](#)” on page 317 for valid values.)

For example:

```
type = HDF_IDL2HDFTYPE(SIZE(myData, /type))
Sddataset_id = HDF_SD_CREATE(f_id, "name", dims, HDF_TYPE=type)
```

## INT

Set this keyword to indicate that the dataset is composed of 2-byte integers. Data will be stored with the HDF DFNT\_INT16 data type. Setting this keyword is the same as setting either the SHORT keyword or the DFNT\_INT16 keyword.

## LONG

Set this keyword to indicate that the dataset is composed of longword integers. Data will be stored with the HDF DFNT\_INT32 data type. Setting this keyword is the same as setting the DFNT\_INT32 keyword.

## SHORT

Set this keyword to indicate that the dataset is composed of 2-byte integers. Data will be stored with the HDF DFNT\_INT16 data type. Setting this keyword is the same as setting either the INT keyword or the DFNT\_INT16 keyword.

## STRING

Set this keyword to indicate that the dataset is composed of strings. Data will be stored with the HDF DFNT\_CHAR8 data type. Setting this keyword is the same as setting the DFNT\_CHAR8 keyword.

## Examples

```
; Create a new HDF file:
SDinterface_id = HDF_SD_START('test.hdf', /CREATE)
; Create an dataset that includes an unlimited dimension:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'var1', [9,40,0],
/SHORT)
```

The example for [HDF\\_SD\\_ATTRSET](#) also demonstrates the use of this routine.

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_OPEN](#), [HDF\\_SD\\_ENDACCESS](#), [HDF\\_SD\\_SELECT](#)

# HDF\_SD\_DIMGET

The HDF\_SD\_DIMGET procedure retrieves information about an SD dataset dimension.

## Syntax

```
HDF_SD_DIMGET, Dim_ID [, /COUNT] [, COMPATIBILITY=variable]  
[, /FORMAT] [, /LABEL] [, /NAME] [, /NATTR] [, /SCALE] [, /TYPE]  
[, /UNIT]
```

## Arguments

### Dim\_ID

A dimension ID as returned by HDF\_SD\_DIMGETID.

## Keywords

### COUNT

Set this keyword to return the dimension size.

### COMPATIBILITY

Set this keyword to a named variable that will contain a string indicating the dimensional compatibility of the current dimension. Possible values are “BW\_COMP” (backwards compatible), “BW\_INCOMP” (backwards incompatible), or “FAIL” (the information is unavailable). For further information about dimensional compatibilities, see the HDF User’s Guide, and the BW\_INCOMP keyword of HDF\_SD\_DIMSET. By default, IDL writes HDF files in “BW\_COMP” mode.

### FORMAT

Set this keyword to return the dimension format description string.

### LABEL

Set this keyword to return the dimension label description string.



**NAME**

Set this keyword to return the dimension name.

**NATTR**

Set this keyword to return the number of attributes for the dimension.

**SCALE**

Set this keyword to return the scale of the dimension.

**TYPE**

Set this keyword to return a string describing the data's type (i.e., 'BYTE').

**UNIT**

Set this keyword to return the dimension unit description string.

**Examples**

For an example using this routine, see the example for [HDF\\_SD\\_DIMSET](#).

**Version History**

4.0	Introduced
-----	------------

**See Also**

[HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_DIMGETID](#), [HDF\\_SD\\_DIMSET](#),  
[HDF\\_SD\\_SELECT](#)

# HDF\_SD\_DIMGETID

The HDF\_SD\_DIMGETID function returns a dimension ID given a dataset's "SDdataset\_id" and a dimension number.

## Syntax

*Result* = HDF\_SD\_DIMGETID(*SDdataset\_id*, *Dimension\_Number*)

## Return Value

Returns the dimension identifier.

## Arguments

### SDdataset\_id

An SD dataset ID as returned by HDF\_SD\_SELECT or HDF\_SD\_CREATE.

### Dimension\_Number

A zero-based dimension number. The dimension number must be greater than or equal to 0 and less than the maximum dimension number, or *rank*.

## Keywords

None

## Examples

For an example illustrating this routine, see the documentation for [HDF\\_SD\\_DIMSET](#).

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_DIMGET](#), [HDF\\_SD\\_DIMSET](#), [HDF\\_SD\\_SELECT](#)

# HDF\_SD\_DIMSET

The HDF\_SD\_DIMSET procedure sets the scale and data strings for an SD dimension.

## Syntax

```
HDF_SD_DIMSET, Dim_ID [, /BW_INCOMP] [, FORMAT=string]
  [, LABEL=string] [, NAME=string] [, SCALE=vector] [, UNIT=string]
```

## Arguments

### Dim\_ID

A dimension ID as returned by HDF\_SD\_DIMGETID.

## Keywords

### BW\_INCOMP

Set this keyword to write SD dimensions in the “new” (HDF4.1 and later) style. Versions of HDF prior to HDF 4.0 beta 2 were inefficient in the use of SD dimensions. HDF now uses a new internal representation of SD dimensions. If the BW\_INCOMP keyword is not set, or is explicitly set equal to zero, the current version of HDF writes SD dimensions in both the pre-HDF 4.0 format AND the “new” format. This default behavior is called the BW\_COMP dimensional compatibility representation.

Setting the BW\_INCOMP keyword causes the current dimension to be written in only the “new” (HDF4.1 and later) format. Depending on your HDF file, using this new format can reduce the size of the HDF by up to a factor of 2, but at the expense of incompatibility with pre HDF 4.0 beta 2 applications (IDL version 4, for example). The COMPATIBILITY keyword of HDF\_SD\_DIMGET can be used to check the dimensional compatibility of an HDF dimension.

### Note

---

Future versions of HDF will recognize *only* the “new” (BW\_INCOMP) dimensional representation.

---

**FORMAT**

A string for the dimension format.

**LABEL**

A string for the dimension label.

**NAME**

A string for the dimension name.

**SCALE**

A vector containing the dimension scale values.

**UNIT**

A string for the dimension unit.

**Examples**

```

; Initialize the SD interface:
SDinterface_id = HDF_SD_START('myhdf.hdf', /RDWR)
; Create 3 dimensions:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'var1', [10,20,0],
/LONG)
; Select the first dimension:
dim_id=HDF_SD_DIMGETID(SDdataset_id,0)
; Set the data strings and scale for the first dimension:
HDF_SD_DIMSET, dim_id, NAME='d1', LABEL='l1', $
    FORMAT='f1', UNIT='u1', SCALE=FINDGEN(10)
HDF_SD_ENDACCESS, SDdataset_id
; Close the HDF file to ensure everything is written:
HDF_SD_END, SDinterface_id
; Reopen the file:
SDinterface_id = HDF_SD_START('myhdf.hdf')
; Select the first dimension:
dim_id = HDF_SD_DIMGETID(SDdataset_id,0)
; Retrieve the information:
HDF_SD_DIMGET, dim_id, NAME=d1, LABEL=l1, FORMAT=f1, $
    UNIT=u1, SCALE=sc, COUNT=cnt, NATTR=natt, TYPE=type
; Print information about the returned variables:
HELP, d1, l1, f1, u1, sc, cnt, natt, type
; Close the SD interface:
HDF_SD_ENDACCESS,SDdataset_id
HDF_SD_END, SDinterface_id

```

## IDL Output

```
D1 STRING = 'd1'  
L1 STRING = 'l1'  
F1 STRING = 'f1'  
U1 STRING = 'u1'  
SC FLOAT = Array(10)  
CNT LONG = 10  
NATT LONG = 3  
TYPE STRING = 'FLOAT'
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_DIMGET](#), [HDF\\_SD\\_DIMGETID](#),  
[HDF\\_SD\\_SELECT](#)

# HDF\_SD\_END

The `HDF_SD_END` procedure closes the SD interface to an HDF file. Failure to close the file without a call to `HDF_SD_END` results in the loss of any changed or added SD data. Therefore, `HDF_SD_END` calls should always be paired with calls to `HDF_SD_START`. Before `HDF_SD_END` is called, all access to SD datasets should be terminated with calls to `HDF_SD_ENDACCESS`.

## Syntax

```
HDF_SD_END, SDinterface_id
```

## Arguments

### SDinterface\_id

An SD interface ID as returned by `HDF_SD_START`.

## Keywords

None

## Examples

```
; Open a new HDF file:
SDinterface_id = HDF_SD_START('test.hdf', /CREATE)
; Various commands could now be used to access SD data
; in the HDF file.
; When done with datasets, access should be ended with
; calls to HDF_SD_ENDACCESS:
HDF_SD_ENDACCESS, SDdataset_id_1
; When done with an HDF file, it should be closed:
HDF_SD_END, SDinterface_id
```

Another example can be seen in the documentation for [HDF\\_SD\\_ATTRSET](#).

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_CLOSE](#), [HDF\\_OPEN](#), [HDF\\_SD\\_ENDACCESS](#), [HDF\\_SD\\_START](#)



# HDF\_SD\_ENDACCESS

The `HDF_SD_ENDACCESS` procedure closes an SD dataset interface. Failure to close the interface can result in the loss of any changed or added SD data. This routine should be called once for each call to `HDF_SD_START` or `HDF_SD_CREATE`. After all SD dataset interfaces are closed, the HDF file can safely be closed with `HDF_SD_END`.

## Syntax

```
HDF_SD_ENDACCESS, SDinterface_id
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by `HDF_SD_SELECT`, or `HDF_SD_CREATE`.

## Keywords

None

## Examples

```
; Open a new HDF file:
SDinterface_id = HDF_SD_START('test.hdf', /CREATE)
; Access the HDF file:
SDdataset_id_1 = HDF_SD_SELECT(SDinterface_id,0)
; End access to any SD IDs:
HDF_SD_ENDACCESS, SDdataset_id_1
; Close the HDF file:
HDF_SD_END, SDinterface_id
```

Also see the example in [HDF\\_SD\\_ATTRSET](#).

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_CLOSE](#), [HDF\\_OPEN](#), [HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_ENDACCESS](#),  
[HDF\\_SD\\_START](#)

# HDF\_SD\_FILEINFO

The `HDF_SD_FILEINFO` procedure retrieves the number of datasets and global attributes in an HDF file.

## Syntax

`HDF_SD_FILEINFO, SDinterface_id, Datasets, Attributes`

## Arguments

### SDinterface\_id

An SD interface ID as returned by `HDF_SD_START`.

### Datasets

A named variable in which the total number of SD-type objects (i.e., the number of datasets + the number of dimensions) in the file is returned.

### Attributes

A named variable in which the number of global attributes in the file is returned.

## Keywords

None

## Examples

```

; Start the SD interface:
SDinterface_id = HDF_SD_START('demo.hdf', /CREATE)
; Set a global attribute:
HDF_SD_ATTRSET,SDinterface_id, 'TITLE', 'MYTITLE'
; Set another one:
HDF_SD_ATTRSET,SDinterface_id, 'TITLE2', 'MYTITLE2'
; Create a dataset:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'var1', [10,3])
; Retrieve info about the dataset:
HDF_SD_FILEINFO, SDinterface_id, datasets, attributes
; Print information about the returned variables:
HELP, datasets, attributes
; End SD access:
HDF_SD_ENDACCESS, SDdataset_id

```

```
; Close the SD interface:  
HDF_SD_END, SDinterface_id
```

### IDL Output

```
DATASETS LONG = 1  
ATTRIBUTES LONG = 2
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_ATTRFIND](#), [HDF\\_SD\\_ATTRINFO](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_GETDATA

The `HDF_SD_GETDATA` procedure retrieves a hyperslab of values from an SD dataset. By default, the retrieved data is transposed from HDF's column order format into IDL's row order which is more efficient in IDL. To retrieve the dataset without this transposition, set the `NOREVERSE` keyword.

## Syntax

```
HDF_SD_GETDATA, SDdataset_id, Data [, COUNT=vector] [, /NOREVERSE]  
[, START=vector] [, STRIDE=vector]
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by `HDF_SD_SELECT` or `HDF_SD_CREATE`.

### Data

A named variable in which the values are returned.

## Keywords

### COUNT

Set this keyword to a vector containing the counts, or number of items, to be read. The default is to read all available data.

### NOREVERSE

Set the keyword to retrieve the data without transposing the data from column to row order.

### START

Set this keyword to a vector containing the starting position for the read. The default start position is `[0, 0, ..., 0]`.

## STRIDE

Set this keyword to a vector containing the strides, or sampling intervals, between accessed values of the HDF variable. The default stride vector is that for a contiguous read: [0, 0, ..., 0].

## Examples

For an example using this routine, see the documentation for [HDF\\_SD\\_ADDDATA](#).

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_ADDDATA](#), [HDF\\_SD\\_GETINFO](#)

# HDF\_SD\_GETINFO

The `HDF_SD_GETINFO` procedure retrieves information about an SD dataset.

## Warning

Reading a label, unit, format, or coordinate system string that has more than 256 characters can have unpredictable results.

## Syntax

```
HDF_SD_GETINFO, SDdataset_id [, CALDATA=variable]
  [, COORDSYS=variable] [, DIMS=variable] [, FILL=variable]
  [, FORMAT=variable] [, HDF_TYPE=variable] [, LABEL=variable]
  [, NAME=variable] [, NATTS=variable] [, NDIMS=variable] [, /NOREVERSE]
  [, RANGE=variable] [, TYPE=variable] [, UNIT=variable]
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by `HDF_SD_SELECT` or `HDF_SD_CREATE`.

## Keywords

### CALDATA

Set this keyword to a named variable in which the calibration data associated with the SD dataset is returned. The data is returned in a structure of the form:

For more information about calibration data, see the documentation for [HDF\\_SD\\_SETINFO](#).

### COORDSYS

Set this keyword to a named variable in which the coordinate system description string is returned.

### DIMS

Set this keyword to a named variable in which the dimensions of the SD dataset are returned. For efficiency, these dimensions are returned in reverse order from their HDF format unless the `NOREVERSE` keyword is also set.

## FILL

Set this keyword to a named variable in which the fill value of the SD dataset is returned. Note that a fill value *must* be set in the SD dataset. If a fill value is not set, the value of the variable named by this keyword will be undefined, and IDL will issue a warning message.

## FORMAT

Set this keyword to a named variable in which the format description string is returned. If the format description string is not present, this variable will contain an empty string.

## HDF\_TYPE

Set this keyword to a named variable in which the HDF type of the SD dataset is returned as a scalar string. Possible returned values are DFNT\_NONE, DFNT\_CHAR8, DFNT\_FLOAT32, DFNT\_FLOAT64, DFNT\_INT8, DFNT\_INT16, DFNT\_INT32, DFNT\_UINT8, DFNT\_UINT16, and DFNT\_UINT32. (See “[IDL and HDF Data Types](#)” on page 317 for valid values.)

## LABEL

Set this keyword to a named variable in which the label description string is returned. If the label description string is not present, this variable will contain an empty string.

## NAME

Set this keyword to a named variable in which the SD dataset name is returned. If the SD dataset name is not present, this variable will contain an empty string.

## NATTS

Set this keyword to a named variable in which the number of “NetCDF-style” attributes for the SD dataset is returned.

## NDIMS

Set this keyword to a named variable in which the number of dimensions in the dataset is returned.



## NOREVERSE

Set this keyword in conjunction with DIMS to return the variable dimensions in non-reversed form. By default, IDL reverses data and dimensions from the HDF format to improve efficiency.

## RANGE

Set this keyword to a named variable in which the maximum and minimum of the current SD dataset is returned as a two-element vector. Note that a range *must* be set in the SD dataset. If the range is not set, the value of the variable named by this keyword will be undefined, and IDL will issue a warning message.

## TYPE

Set this keyword to a named variable in which the IDL type of the SD dataset is returned as a scalar string. Possible returned values are BYTE, INT, LONG, FLOAT, DOUBLE, STRING, or UNKNOWN.

## UNIT

Set this keyword to a named variable in which the unit description string is returned. If the unit description string is not present, this variable will contain an empty string.

## Examples

For an example using this routine, see the documentation for [HDF\\_SD\\_SETINFO](#).

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_OPEN](#), [HDF\\_SD\\_END](#), [HDF\\_SD\\_SETINFO](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_IDTOREF

The `HDF_SD_IDTOREF` function converts a SD data set ID into a SD data set reference number. The reference number can be used to add the SD data set to a Vgroup through the `HDF_VG` interface. The tag number for an SD is 720.

## Syntax

*Result* = `HDF_SD_IDTOREF(SDdataset_id)`

## Return Value

Returns the SD data set reference number.

## Arguments

### SDdataset\_id

A `SDdataset_id` as returned from `HDF_SD_CREATE` or `HDF_SD_SELECT`.

## Keywords

None

## Examples

```

; Create an SD data set and get the Reference number:
file_id = HDF_OPEN('demo.hdf', /ALL)
SDinterface_id = HDF_SD_START('demo.hdf', /RDWR)
dim=[100]
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'demo_data', dim,
/FLOAT)
ref = HDF_SD_IDTOREF(SDdataset_id)
HDF_SD_ADDDATA, SDdataset_id, FINDGEN(100)/10.45 + 2.98
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id

; Use the Reference number to add the SD to a Vgroup:
SD_TAG = 720
vgID = HDF_VG_GETID(file_id,-1)
vg_handle = HDF_VG_ATTACH(file_id, vgID, /WRITE)
HDF_VG_SETINFO, vg_handle, name='data1', class='demo'
HDF_VG_ADDTR, vg_handle, SD_TAG, ref

```

```
; Use HDF_VG_INQTR to verify the SD was added correctly:
IF HDF_VG_INQTR(vg_handle, SD_TAG, ref) THEN $
  PRINT, 'SUCCESS' ELSE PRINT, 'Failure'
HDF_VG_DETACH, vg_handle
HDF_CLOSE, file_id
```

### IDL Output

```
SUCCESS
```

## Version History

4.0	Introduced
-----	------------

### See Also

[HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_NAMETOINDEX](#), [HDF\\_SD\\_REFTOINDEX](#),  
[HDF\\_SD\\_SELECT](#), [HDF\\_VG\\_ADDTR](#), [HDF\\_VG\\_ATTACH](#),  
[HDF\\_VG\\_DETACH](#), [HDF\\_VG\\_GETID](#), [HDF\\_VG\\_INQTR](#)

# HDF\_SD\_ISCOORDVAR

The HDF\_SD\_ISCOORDVAR function determines whether or not the specified dataset ID represents a NetCDF “coordinate” variable.

## Syntax

*Result* = HDF\_SD\_ISCOORDVAR(*SDdataset\_id*)

## Return Value

Returns True (1) if the supplied data set ID is a NetCDF coordinate variable. Otherwise, False (0) is returned.

## Arguments

### SDdataset\_id

An SD dataset ID as returned by HDF\_SD\_SELECT or HDF\_SD\_CREATE.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_SD\_NAMETOINDEX

The `HDF_SD_NAMETOINDEX` function returns an SD dataset index given its name and SD interface ID. An error message is printed if the dataset cannot be located. The returned index can be used by `HDF_SD_SELECT` to access an SD dataset.

## Syntax

*Result* = `HDF_SD_NAMETOINDEX(SDinterface_id, SDS_Name)`

## Return Value

Returns the specified SD dataset index number.

## Arguments

### **SDinterface\_id**

An SD interface ID as returned by `HDF_SD_START`.

### **SDS\_Name**

A string containing the name of the SD dataset to be located.

## Keywords

None

## Examples

```
; Start the SD interface:
SDinterface_id = HDF_SD_START('demo.hdf')
; Return the index of the 'variable_2' dataset:
index = HDF_SD_NAMETOINDEX(SDinterface_id, 'variable_2')
; Access the dataset:
SDdataset_id=HDF_SD_SELECT(SDinterface_id,index)
; End access:
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id
```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_REFTOINDEX](#), [HDF\\_SD\\_SELECT](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_REFTOINDEX

The `HDF_SD_REFTOINDEX` function returns a scientific dataset's index given its reference number and SD interface ID.

## Syntax

*Result* = `HDF_SD_REFTOINDEX(SDinterface_id, Reference_number)`

## Return Value

Returns the index number associated with the specified SD dataset.

## Arguments

### **SDinterface\_id**

An SD interface ID as returned by `HDF_SD_START`.

### **Reference\_number**

The SD reference number for the desired dataset.

## Keywords

None

## Examples

```
; Initialize the SD interface:
SDinterface_id = HDF_SDSTART('demo.hdf')
; Define the reference number for which we want to search:
Reference_number = 66
; Return the index number:
index = HDF_SD_REFTOINDEX(SDinterface_id, Reference_number)
; Now the dataset can be accessed:
SDdataset_id = HDF_SD_SELECT(SDinterface_id, index)
; End access:
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_SD\\_IDTOREF](#), [HDF\\_SD\\_NAMETOINDEX](#)



# HDF\_SD\_SELECT

The `HDF_SD_SELECT` function returns an SD dataset ID given the current SD interface ID, and the zero-based SD dataset index.

`HDF_SD_FILEINFO` can be used to determine the number of SD datasets in an HDF file, `HDF_SD_REFTOINDEX` can be used to find the index from its SD dataset ID, and `HDF_SD_NAMETOINDEX` can be used to find the index from its name.

## Syntax

```
Result = HDF_SD_SELECT(SDinterface_id, Number)
```

## Return Value

Returns the specified SD dataset's identifier.

## Arguments

### **SDinterface\_id**

A SD interface ID as returned from `HDF_SD_START`.

### **Number**

A zero-based SD dataset index.

## Keywords

None

## Examples

```
; Open an HDF file:
SDinterface_id = HDF_SD_START('test.hdf')
; Access the first SD in the HDF file:
SDdataset_id_1=HDF_SD_SELECT(SDinterface_id, 0)
; End access to any SD ids:
HDF_SD_ENDACCESS, SDdataset_id_1
; Close the file:
HDF_SD_END, SDinterface_id
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_END](#), [HDF\\_SD\\_ENDACCESS](#),  
[HDF\\_SD\\_NAMETOINDEX](#), [HDF\\_SD\\_REFTOINDEX](#), [HDF\\_SD\\_SELECT](#),  
[HDF\\_SD\\_START](#)

# HDF\_SD\_SETCOMPRESS

The `HDF_SD_SETCOMPRESS` procedure compresses an existing HDF SD dataset or sets the compression method of a newly created HDF SD dataset. Available compression methods are No Compression, run-length encoding (RLE), adaptive (skipping) huffman, and GZIP compression. All of these compression methods are lossless. When using skipping huffman compression, IDL automatically determines the correct skipping size. The `EFFORT` keyword determines the effort applied when using GZIP compression (i.e., when `comptype` is 4). In general, the default GZIP compression method is the best combination of speed and file size reduction.

## Syntax

```
HDF_SD_SETCOMPRESS, SDdataset_id, comptype [, EFFORT=integer{1 to 9}]
```

## Arguments

### **`SDdataset_id`**

The HDF SD dataset id as returned by `HDF_SD_CREATE` or `HDF_SD_SELECT`.

### **`Comptype`**

The compression type to be applied to the HDF SD dataset. Allowable values are:

- 0 = NONE (no compression)
- 1 = RLE (run-length encoding)
- 3 = SKIPPING HUFFMAN
- 4 = GZIP

### **Note**

---

All compression types are lossless.

---

## Keywords

### **EFFORT**

If the `comptype` is set to 4 (GZIP), then this keyword specifies the effort that GZIP expends in compressing the dataset. The `EFFORT` keyword is restricted to the range

1 (minimal compression, fastest) to 9 (most compressed, slowest). The default is EFFORT=5.

## Examples

```

; Create an HDF SD file:
SDinterface_id = HDF_SD_START('compress.hdf', /CREATE)
; Create an SDS dataset:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'dataset1', [9,40],
/LONG)
; Maximal GZIP compression:
HDF_SD_SETCOMPRESS,SDdataset_id,4,EFFORT=9
; Write the data to be compressed:
HDF_SD_ADDDATA,SDdataset_id,fix(dist(9,40))
; End access to the SDS:
HDF_SD_ENDACCESS, SDdataset_id
; End access to the SD interface:
HDF_SD_END, SDinterface_id

```

### Note

---

Compression of HDF SD datasets is a new feature as of HDF 4.1r2 / IDL 5.2.1. Attempts to read HDF SD datasets not created with HDF 4.1r2 (IDL 5.1) or greater will give unpredictable results. Attempts to read HDF compressed SD datasets with IDL versions prior to IDL 5.1, or other HDF readers that use an HDF version prior to HDF 4.1r2, will fail.

---

## Version History

5.2.1	Introduced
-------	------------

# HDF\_SD\_SETEXTFILE

The `HDF_SD_SETEXTFILE` procedure moves data values from a dataset into an external file. Only the data is moved—all other information remains in the original file. This routine can only be used with HDF version 3.3 (and later) files, not on older HDF files or NetCDF files. Data can only be moved once, and the user must keep track of the external file(s). The `OFFSET` keyword allows writing to an arbitrary location in the external file.

As shown in the example, when adding data to an external file SD, you *must* first use `HDF_SD_ENDACCESS` to sync the file, then reacquire the SDS ID with `HDF_SD_SELECT` before using `HDF_SD_SETEXTFILE`.

## Syntax

```
HDF_SD_SETEXTFILE, SDdataset_id, Filename [, OFFSET=bytes]
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by `HDF_SD_SELECT`.

### Filename

The name of the external file to be written.

## Keywords

### OFFSET

Set this keyword to a number of bytes from the beginning of the external file at which data writing should begin. Exercise extreme caution when using this keyword with existing files.

## Examples

```
; Create an HDF file:
SDinterface_id = HDF_SD_START('ext_main.hdf', /CREATE)
; Add an SD:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'float_findgen',
[3,5], /FLOAT)
; Put some data into the SD:
```

```

HDF_SD_ADDDATA, SDdataset_id, FINDGEN(3,5)
; Call HDF_SD_ENDACCESS to sync the file:
HDF_SD_ENDACCESS,SDdataset_id
; Reacquire the SDdataset_id:
SDdataset_id = HDF_SD_SELECT(SDinterface_id, 0)
; Move data to an external file named findgen.hdf:
HDF_SD_SETTEXTFILE, SDdataset_id, 'findgen.hdf'
; Retrieve data from the external file into the variable fout:
HDF_SD_GETDATA, SDdataset_id, fout
; Print the contents of fout:
PRINT, fout
; Sync and close the files:
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id

```

### IDL Output

```

0.00000 1.00000 2.00000
3.00000 4.00000 5.00000
6.00000 7.00000 8.00000
9.00000 10.0000 11.0000
12.0000 13.0000 14.0000

```

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_SD\\_END](#), [HDF\\_SD\\_ENDACCESS](#), [HDF\\_SD\\_SELECT](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_SETINFO

The HDF\_SD\_SETINFO procedure sets information about an SD dataset.

## Warning

Setting a label, unit, format, or coordinate system string that has more than 256 characters can have unpredictable results.

## Syntax

```
HDF_SD_SETINFO, SDdataset_id [, CALDATA=structure] [, COORDSYS=string]
  [, FILL=value] [, FORMAT=string] [, LABEL=string] [, RANGE=[max, min]]
  [, UNIT=string]
```

## Arguments

### SDdataset\_id

An SD dataset ID as returned by HDF\_SD\_SELECT or HDF\_SD\_CREATE.

## Keywords

### CALDATA

Set this keyword to a structure that contains the calibration data. This structure must contain five tags as shown below. The first four tags are of double-precision floating-point type. The fifth tag should be a long integer that specifies the HDF number type. The structure should have the following form:

```
CALDATA={ Cal: 0.0D $           ;Calibration Factor
          Cal_Err: 0.0D $      ;Calibration Error
          Offset: 0.0D $       ;Uncalibrated Offset
          Offset_Err: 0.0D $   ;Uncalibrated Offset Error
          Num_Type: 0L }       ;Number Type of Uncalibrated Data
```

The relationship between HDF and IDL number types is illustrated by the following table:

HDF Number Type	IDL Data Type
0L	UNDEFINED
3L	STRING
21L	BYTE
22L	INTEGER
24L	LONG INTEGER
5L	FLOATING-POINT
6L	DOUBLE-PRECISION

*Table 4-10: HDF Number Types vs. IDL Data Types*

The relationship between the calibrated data (CD) and the uncalibrated data (UD) is given by the equation:

$$CD = Cal * (UD - Offset)$$

Cal and Offset are the values of the Cal and Offset structure fields described above.

## COORDSYS

Set this keyword to a string to be used as the SD dataset coordinate system.

## FILL

Set this keyword to the fill value of the SD dataset.

## FORMAT

Set this keyword to a string to be used as the SD dataset format.

## LABEL

Set this keyword to a string to be used as the SD dataset label.

## RANGE

Set this keyword to a two dimensional array that contains the minimum and maximum values of the SD dataset.



## UNIT

Set this keyword to a string to be used as the SD dataset units.

## Examples

```

; Open an HDF file:
SDinterface_id = HDF_SD_START('demo.hdf', /RDWR)
; Define a new dataset for the file:
SDdataset_id = HDF_SD_CREATE(SDinterface_id, 'variable1', [10,
20], /DOUBLE)
; Create a calibration data structure:
CAL={Cal:1.0D, Cal_Err:0.1D, Offset:2.5D, Offset_Err:0.1D, $
      Num_Type:6L}
; Set information about the dataset:
HDF_SD_SETINFO, SDdataset_id, LABEL='label1', unit='unit1', $
      format='format1', coordsys='coord1', FILL=999.991, $
      RANGE=[99.99,-78], caldata=CAL
; Retrieve the information:
HDF_SD_GETINFO, SDdataset_id, LABEL=l, UNIT=u, FORMAT=f, $
      COORDSYS=c, FILL=fill, RANGE=r, CALDATA=cd, $
      NDIMS=ndims, DIMS=dims, TYPE=ty
; Print information about the returned variables:
HELP, l, u, f, c, fill, r, cd, ndims, dims, ty
; Print the range:
PRINT, r
; Print the calibration data:
PRINT, cd
; Print the dimensions:
PRINT, dims
; Close the SD interface:
HDF_SD_ENDACCESS, SDdataset_id
HDF_SD_END, SDinterface_id

```

## IDL Output

```

L STRING = 'label1'
U STRING = 'unit1'
F STRING = 'format1'
C STRING = 'coord1'
FILL DOUBLE = 999.99103
R DOUBLE = Array(2)
CD STRUCT = -> < Anonymous > Array(1)
NDIMS LONG = 2
DIMS LONG = Array(2)
TY STRING = 'DOUBLE'

-78.000000 99.989998

```

```
{ 1.0000000 0.10000000 2.5000000 0.10000000 6}  
10 20
```

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_SD\\_END](#), [HDF\\_SD\\_ENDACCESS](#), [HDF\\_SD\\_GETINFO](#), [HDF\\_SD\\_START](#)

# HDF\_SD\_START

The `HDF_SD_START` function opens or creates an HDF file and initializes the SD interface.

Note that every file opened with `HDF_SD_START` should eventually be closed with a call to `HDF_SD_END`.

## Syntax

```
Result = HDF_SD_START( Filename [, /READ | , /RDWR] [, /CREATE] )
```

## Return Value

The returned value of this function is the SD ID of the HDF file. If no keywords are present, the file is opened in read-only mode.

## Arguments

### Filename

A scalar string containing the name of the file to be opened or created. `HDF_SD_START` can open the following file types: XDR-based NetCDF files, “old-style” DFSD files, or “new-style” SD files. New files are created as “new-style” SD files.

## Keywords

### READ

Set this keyword to open the SD interface in read-only mode. If no keywords are specified, this is the default behavior.

### RDWR

Set this keyword to open the SD interface in read and write mode.

### CREATE

Set this keyword to create a new SD file.

## Examples

```
; Open a new HDF file. The file is ready to be accessed:
SDinterface_id = HDF_SD_START('test.hdf', /CREATE)
; When finished with the file, close it with a call to HDF_SD_END:
HDF_SD_END, SDinterface_id
```

For a more complicated example, see the documentation for [HDF\\_SD\\_ATTRSET](#).

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_CLOSE](#), [HDF\\_OPEN](#), [HDF\\_SD\\_ATTRFIND](#), [HDF\\_SD\\_ATTRINFO](#),  
[HDF\\_SD\\_ATTRSET](#), [HDF\\_SD\\_CREATE](#), [HDF\\_SD\\_END](#), [HDF\\_SD\\_FILEINFO](#),  
[HDF\\_SD\\_NAMETOINDEX](#), [HDF\\_SD\\_REFTOINDEX](#), [HDF\\_SD\\_SELECT](#),  
[HDF\\_SD\\_SETTEXTFILE](#)

# HDF\_UNPACKDATA

This procedure unpacks an array of byte data into a number of IDL variables. It is useful in deconstructing the output of multi-field HDF Vdata reading routines, such as those found in HDF-EOS, into a set of IDL variables. The packed data is assumed to be an array of bytes that is organized as a number of records. Each record consists of one or more data fields. A record is defined using the `HDF_TYPE` and `HDF_ORDER` keywords. These define the record layout in terms of HDF data types. The procedure walks through the input array and copies the values into output IDL arrays. There must be as many entries in the `HDF_TYPE` and `HDF_ORDER` keywords as there are data arguments.

## Syntax

```
HDF_UNPACKDATA, packeddata, data1 [, data2 [, data3 [, data4 [, data5 [, data6
  [, data7 [, data8]]]]]] [, HDF_ORDER=array] [, HDF_TYPE=array]
  [, NREC=records]
```

## Arguments

### packeddata

A BYTE array of packed data.

### data1...data8

These arguments return IDL arrays of the types specified by `HDF_TYPE` with values for each record in the packed data. If `HDF_ORDER` is greater than one, the returned array will be 2D and the leading dimension will be of length `HDF_ORDER`. The one exception is string types, which will be returned as a 1D array of IDL strings. The fixed-length string field is returned as an IDL string up to the first zero value (if present). The trailing dimension will be equal to the minimum of the `NREC` keyword value or the number of complete records that fit in the `packeddata` array.

## Keywords

### HDF\_ORDER

Set this keyword to an array with the same length as the number of data fields. The values in the array are equal to the number of elements in the return argument for each record. In the case of strings, this is the length (in characters) of the string to be

read. A value of zero is interpreted as one element. The default for this keyword is an array of ones.

## HDF\_TYPE

Set this keyword to an array with the same length as the number of data fields. The value in the array is an HDF data type for each return argument. The returned IDL variables will have these types. The default for this keyword is an array of the value 5 (an HDF 32-bit float). See “[IDL and HDF Data Types](#)” on page 317 for valid values.

## NREC

Set this keyword to the number of records to read from packeddata. The default is to read as many complete records as exist in the packeddata array.

## Examples

```
a = INDGEN(5)
b = FINDGEN(5)
c = ['This', 'is', 'a', 'string', 'array.']
HELP, a, b, c
hdftype = [ 22, 5, 4] ; HDF INT16, FLOAT32 and CHAR
order = [ 0, 0, 6] ; 2 + 4 + 6 = 12 bytes/record
data = HDF_PACKDATA( a, b, c, HDF_TYPE=hdftype, HDF_ORDER=order)
HELP, data ; a [12, 5] array (5 - 12byte records)
HDF_UNPACKDATA, data, d, e, f, HDF_TYPE=hdftype, HDF_ORDER=order
HELP, d, e, f ; recover the original arrays
```

## Version History

5.2	Introduced
-----	------------

## See Also

[HDF\\_PACKDATA](#), [HDF\\_VD\\_READ](#), [EOS\\_PT\\_READLEVEL](#)

# HDF\_VD\_ATTACH

The HDF\_VD\_ATTACH function accesses a VData with the given Id in an HDF file.

## Syntax

```
Result = HDF_VD_ATTACH( FileHandle, VData_id [, /READ] [, /WRITE] )
```

## Return Value

If successful, a handle for that VData is returned, otherwise 0 is returned.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### VData\_id

The VData reference number, usually obtained by HDF\_VD\_GETID or HDF\_VD\_LONE. Set this argument to -1 to create a new VData.

## Keywords

### READ

Set this keyword to open the VData for reading. This is the default.

### WRITE

Set this keyword to open the VData for writing. If VData\_id is set equal to -1, the file is opened for writing whether or not this keyword is set.

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_VD\\_DETACH](#)



# HDF\_VD\_ATTRFIND

The HDF\_VD\_ATTRFIND function returns an attribute's index number given the name of an attribute associated with the specified VData or VData/field pair.

## Syntax

*Result* = HDF\_VD\_ATTRFIND(*VData*, *FieldID*, *Name*)

## Return Value

Returns the specified attribute's index number or -1 if the attribute cannot be located.

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### FieldID

A zero-based index specifying the field, or a string containing the name of the field within the VData to which the attribute is attached. Setting FieldID to -1 specifies that the attribute is attached to the VData itself.

### Name

A string containing the name of the attribute whose index is to be returned.

## Keywords

None

## Examples

For an example using this routine, see the documentation for [HDF\\_VD\\_ATTRSET](#).

## Version History

---

5.5	Introduced
-----	------------

---

## See Also

[HDF\\_VD\\_ATTRINFO](#), [HDF\\_VD\\_ATTRSET](#), [HDF\\_VD\\_ISATTR](#),  
[HDF\\_VD\\_NATTRS](#)

# HDF\_VD\_ATTRINFO

The `HDF_VD_ATTRINFO` procedure reads or retrieves information about a `VData` attribute or a `VData` field attribute from the currently attached HDF `VData` structure. If the attribute is not present, an error message is printed.

## Syntax

```
HDF_VD_ATTRINFO, VData, FieldID, AttrID [, COUNT=variable]  
  [, DATA=variable] [, HDF_TYPE=variable] [, NAME=variable ]  
  [, TYPE=variable]
```

## Arguments

### **VData**

The `VData` handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### **FieldID**

A zero-based index specifying the field, or a string containing the name of the field within the `VData` whose attribute is to be read. Setting `FieldID` to -1 specifies that the attribute to be read is attached to the `VData` itself.

### **AttrID**

A zero-based integer index specifying the attribute to be read, or a string containing the name of that attribute.

## Keywords

### **COUNT**

Set this keyword to a named variable in which the number of data values (order of the attribute) is returned.

### **DATA**

Set this keyword to a named variable in which the attribute data is returned.

## HDF\_TYPE

Set this keyword to a named variable in which the HDF data type of the attribute is returned as a scalar string. See “[IDL and HDF Data Types](#)” on page 317 for valid values.

## NAME

Set this keyword to a named variable in which the name of the attribute is returned.

## TYPE

Set this keyword to a named variable in which the IDL type of the attribute is returned as a scalar string.

## Examples

For an example using this routine, see the documentation for `HDF_VD_ATTRSET`.

## Version History

5.5	Introduced
-----	------------

## See Also

[HDF\\_VD\\_ATTRFIND](#), [HDF\\_VD\\_ATTRSET](#), [HDF\\_VD\\_ISATTR](#),  
[HDF\\_VD\\_NATTRS](#)

# HDF\_VD\_ATTRSET

The `HDF_VD_ATTRSET` procedure writes a VData attribute or a VData field attribute to the currently attached HDF VData structure. If no data type keyword is specified, the data type of the attribute value is used.

## Syntax

```
HDF_VD_ATTRSET, VData, FieldID, Attr_Name, Values [, Count] [, /BYTE]
  [, /DFNT_CHAR8] [, /DFNT_FLOAT32] [, /DFNT_FLOAT64] [, /DFNT_INT8]
  [, /DFNT_INT16] [, /DFNT_INT32] [, /DFNT_UCHAR8] [, /DFNT_UINT8]
  [, /DFNT_UINT16] [, /DFNT_UINT32] [, /DOUBLE] [, /FLOAT] [, /INT]
  [, /LONG] [, /SHORT] [, /STRING] [, /UINT ] [, /ULONG ]
```

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### Note

---

The VData structure must have been attached in write mode in order for attributes to be correctly associated with a VData or one of its fields. If the VData is not write accessible, HDF does not return an error; instead, the attribute information is written to the file but is not associated with the VData.

---

### FieldID

A zero-based index specifying the field, or a string containing the name of the field within the VData whose attribute is to be set. If FieldID is set to -1, the attribute will be attached to the VData itself.

### Attr\_Name

A string containing the name of the attribute to be written.

### Values

The attribute value(s) to be written.

**Note**

---

Attributes to be written as characters may not be a multi-dimensional array (e.g. if being converted from byte values) or an array of IDL strings.

---

**Count**

An optional integer argument specifying how many values are to be written. Count must be less than or equal to the number of elements in the Values argument. If not specified, the actual number of values present will be written.

**Keywords****BYTE**

Set this keyword to indicate that the attribute is composed of bytes. Data will be stored with the HDF DFNT\_UINT8 data type. Setting this keyword is the same as setting the DFNT\_UINT8 keyword.

**DFNT\_CHAR8**

Set this keyword to create an attribute of HDF type DFNT\_CHAR8. Setting this keyword is the same as setting the STRING keyword.

**DFNT\_FLOAT32**

Set this keyword to create an attribute of HDF type DFNT\_FLOAT32. Setting this keyword is the same as setting the FLOAT keyword.

**DFNT\_FLOAT64**

Set this keyword to create an attribute of HDF type DFNT\_FLOAT64. Setting this keyword is the same as setting the DOUBLE keyword.

**DFNT\_INT8**

Set this keyword to create an attribute of HDF type DFNT\_INT8.

**DFNT\_INT16**

Set this keyword to create an attribute of HDF type DFNT\_INT16. Setting this keyword is the same as setting either the INT keyword or the SHORT keyword.

## **DFNT\_INT32**

Set this keyword to create an attribute of HDF type DFNT\_INT32. Setting this keyword is the same as setting the LONG keyword.

## **DFNT\_UCHAR8**

Set this keyword to create an attribute of HDF type DFNT\_UCHAR8.

## **DFNT\_UINT8**

Set this keyword to create an attribute of HDF type DFNT\_UINT8. Setting this keyword is the same as setting the BYTE keyword.

## **DFNT\_UINT16**

Set this keyword to create an attribute of HDF type DFNT\_UINT16.

## **DFNT\_UINT32**

Set this keyword to create an attribute of HDF type DFNT\_UINT32.

## **DOUBLE**

Set this keyword to indicate that the attribute is composed of double-precision floating-point values. Data will be stored with the HDF type DFNT\_FLOAT64. Setting this keyword is the same as setting the DFNT\_FLOAT64 keyword.

## **FLOAT**

Set this keyword to indicate that the attribute is composed of single-precision floating-point values. Data will be stored with the HDF type DFNT\_FLOAT32 data type. Setting this keyword is the same as setting the DFNT\_FLOAT32 keyword.

## **INT**

Set this keyword to indicate that the attribute is composed of 16-bit integers. Data will be stored with the HDF type DFNT\_INT16 data type. Setting this keyword is the same as setting either the SHORT keyword or the DFNT\_INT16 keyword.

## **LONG**

Set this keyword to indicate that the attribute is composed of longword integers. Data will be stored with the HDF type DFNT\_INT32 data type. Setting this keyword is the same as setting the DFNT\_INT32 keyword.

## SHORT

Set this keyword to indicate that the attribute is composed of 16-bit integers. Data will be stored with the HDF type DFNT\_INT16 data type. Setting this keyword is the same as setting either the INT keyword or the DFNT\_INT16 keyword.

## STRING

Set this keyword to indicate that the attribute is composed of strings. Data will be stored with the HDF type DFNT\_CHAR8 data type. Setting this keyword is the same as setting the DFNT\_CHAR8 keyword.

## UINT

Set this keyword to indicate that the attribute is composed of unsigned 2-byte integers. Data will be stored with the HDF type DFNT\_UINT16 data type. Setting this keyword is the same as setting the DFNT\_UINT16 keyword.

## ULONG

Set this keyword to indicate that the attribute is composed of unsigned longword integers. Data will be stored with the HDF type DFNT\_UINT32 data type. Setting this keyword is the same as setting the DFNT\_UINT32 keyword.

## Examples

```

; Open an HDF file.
fid = HDF_OPEN(FILEPATH('vattnr_example.hdf'), $
    SUBDIRECTORY = ['examples', 'data']), /RDWR

; Locate and attach an existing vdata.
vdref = HDF_VD_FIND(fid, 'MetObs')
vdid = HDF_VD_ATTACH(fid, vdref, /WRITE)

; Attach two attributes to the vdata.
HDF_VD_ATTRSET, vdid, -1, 'vdata_contents', $
    'Ground station meteorological observations.'
HDF_VD_ATTRSET, vdid, -1, 'num_stations', 10

; Attach an attribute to one of the fields in the vdata.
HDF_VD_ATTRSET, vdid, 'TempDP', 'field_contents', $
    'Dew point temperature in degrees Celsius.'

; Get the number of attributes associated with the vdata.
num_vdattnr = HDF_VD_NATTRS(vdid, -1)

```



```

PRINT, 'Number of attributes attached to vdata MetObs: ', $
      num_vdattrib

; Get information for one of the vdata attributes by first finding
; the attribute's index number.
attr_index = HDF_VD_ATTRFIND(vdid, -1, 'vdata_contents')
HDF_VD_ATTRINFO, vdid, 1, attr_index, $
      NAME = attr_name, DATA = metobs_contents
HELP, attr_name, metobs_contents

; Get information for another vdata attribute using the
; attribute's name.
HDF_VD_ATTRINFO, vdid, -1, 'num_stations', DATA = num_stations, $
      HDF_TYPE = hdftype, TYPE = idltype
HELP, num_stations, hdftype, idltype
PRINT, num_stations

; Get the number of attributes attached to the vdata field
; TempDP.
num_fdattrib = HDF_VD_NATTRS(vdid, 'TempDP')
PRINT, 'Number of attributes attached to field TempDP: ', $
      num_fdattrib

; Get the information for the vdata field attribute.
HDF_VD_ATTRINFO, vdid, 'TempDP', 'field_contents', $
      COUNT = count, HDF_TYPE = hdftype, TYPE = idltype, $
      DATA = dptemp_attr
HELP, count, hdftype, idltype, dptemp_attr

; End access to the vdata.
HDF_VD_DETACH, vdid

; Attach a vdata which stores one of the attribute values.
vdid = HDF_VD_ATTACH(fid, 5)

; Get the vdata's name and check to see that it is indeed storing
; an attribute.
HDF_VD_GET, vdid, NAME = vname
isattr = HDF_VD_ISATTR(vdid)
HELP, vname, isattr

; End access to the vdata and the HDF file.
HDF_VD_DETACH, vdid
HDF_CLOSE, fid

```

## IDL Output

```

Number of attributes attached to vdata MetObs:                2
ATTR_NAME            STRING      = 'vdata_contents'

```

```

METOBS_CONTENTS STRING      = 'Ground station meteorological
observations.'
NUM_STATIONS     INT        = Array[1]
HDFTYPE          STRING     = 'DFNT_INT16'
IDLTYPE          STRING     = 'INT'
                10
Number of attributes attached to field TempDP:                1
COUNT           LONG       =                41
HDFTYPE          STRING     = 'DFNT_CHAR8'
IDLTYPE          STRING     = 'STRING'
DPTEMP_ATTR      STRING     = 'Dew point temperature in degrees
Celsius.'
VDNAME           STRING     = 'field_contents'
ISATTR           LONG       =                1

```

## Version History

5.5	Introduced
-----	------------

## See Also

[HDF\\_VD\\_ATTRFIND](#), [HDF\\_VD\\_ATTRINFO](#), [HDF\\_VD\\_ISATTR](#),  
[HDF\\_VD\\_NATTRS](#)

# HDF\_VD\_DETACH

The HDF\_VD\_DETACH procedure is called when done accessing a VData in an HDF file. This routine must be called for every VData attached for writing before closing the HDF file to insure that VSET information is properly updated.

## Syntax

HDF\_VD\_DETACH, *VData*

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

## Keywords

None

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_VD\\_ATTACH](#)

# HDF\_VD\_FDEFINE

The `HDF_VD_FDEFINE` procedure adds a new field specification for a `VData` in an HDF file. `HDF_VD_FDEFINE` can only be used for a new `VData`.

## Syntax

```
HDF_VD_FDEFINE, VData, Fieldname [, /BYTE | /DOUBLE | /FLOAT | /INT |  
    , /LONG] [, ORDER=value] [, /UINT] [, /ULONG]
```

## Arguments

### VData

The `VData` handle returned by a previous call to `HDF_VD_ATTACH`.

### Fieldname

A string containing the new field name.

## Keywords

### BYTE

Set this keyword to indicate that the field will contain 8-bit unsigned integer data.

### DOUBLE

Set this keyword to indicate that the field will contain 64-bit floating point data.

### FLOAT

Set this keyword to indicate that the field will contain 32-bit floating point data.

### INT

Set this keyword to indicate that the field will contain 16-bit integer data.

### LONG

Set this keyword to indicate that the field will contain 32-bit integer data.

## ORDER

This keyword specifies the number of distinct components in the new field. Compound variables have an order greater than 1. The default order is 1.

## UINT

Set this keyword to indicate that the field will contain 16-bit unsigned integer data.

## ULONG

Set this keyword to indicate that the field will contain 32-bit unsigned integer data.

## Examples

```
HDF_VD_FDEFINE, vid, 'VEL', /DOUBLE, ORDER=3
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_FEXIST

The HDF\_VD\_FEXIST function determines whether the specified fields exist in the given HDF file.

## Syntax

*Result* = HDF\_VD\_FEXIST(*VData*, *Fieldnames*)

## Return Value

Returns 1 (True) if all the specified fields exist.

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### Fieldnames

A string containing a comma-separated list of fields to test. For example, 'VEL' or 'PZ,PY,PX'.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_FIND

The HDF\_VD\_FIND function returns the reference number of a VData with the specified name in an HDF file.

## Syntax

*Result* = HDF\_VD\_FIND(*FileHandle*, *Name*)

## Return Value

Returns the reference number of the named VData. A 0 is returned if an error occurs or a VData of the given name does not exist.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### Name

A string containing the name of the VData to be found.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_GET

The HDF\_VD\_GET procedure is a general VData inquiry routine. Set the various keywords to named variables to return information about a VData in an HDF file.

## Syntax

```
HDF_VD_GET, VData [, CLASS=variable] [, COUNT=variable]  
  [, FIELDS=variable] [, INTERLACE=variable] [, NAME=variable]  
  [, NFIELDS=variable] [, REF=variable] [, SIZE=variable] [, TAG=variable]
```

## Arguments

### VData

A VData handle returned by [HDF\\_VD\\_ATTACH](#).

## Keywords

### CLASS

Set this keyword to a named variable in which the class name of the VData is returned as a string.

### COUNT

Set this keyword to a named variable in which a long, containing the number of records in the VData, is returned.

### FIELDS

Set this keyword to a named variable in which a comma-separated string of fields in the VData is returned (e.g., 'PX,PY,PZ')

The maximum number of fields is 256. Each field can be up to 128 characters in length. The returned fields may or may not contain buffering whitespace depending on how the HDF file was created.

### INTERLACE

Set this keyword to a named variable in which a string, containing either 'FULL\_INTERLACE' or 'NO\_INTERLACE', is returned.



**NAME**

Set this keyword to a named variable in which a string, containing the name of the VData, is returned.

**NFIELDS**

Set this keyword to a named variable in which a long, containing the number of fields in the VDATA, is returned. For example, the VData containing the fields “PX,PY,PZ”, has an NFIELDS of 3.

**REF**

Set this keyword to a named variable in which the reference number of the VData is returned.

**SIZE**

Set this keyword to a named variable in which a long, containing the local size of a record of VData, is returned.

**TAG**

Set this keyword to a named variable in which the tag number of the VData is returned.

**Examples**

```
HDF_VD_GET, vdat, CLASS=c, COUNT=co, FIELDS=f, NAME=n, SIZE=s
```

**Version History**

4.0	Introduced
-----	------------

**See Also**

[HDF\\_VD\\_GETINFO](#), [HDF\\_VG\\_GETINFO](#)

# HDF\_VD\_GETID

The HDF\_VD\_GETID function returns the VData reference number for the next VData in an HDF file after the specified *VData\_id*.

Set *VData\_id* to -1 to return the first VData ID in the file.

## Syntax

*Result* = HDF\_VD\_GETID(*FileHandle*, *VData\_id*)

## Return Value

Returns the next VData reference number.

## Arguments

### FileHandle

The HDF file handle returned by a previous call to HDF\_OPEN.

### VData\_id

The VData reference number, generally obtained by HDF\_VD\_GETID or HDF\_VD\_LONE. Set this argument to -1 to return the first VData in the file.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_GETINFO

The `HDF_VD_GETINFO` procedure is a general VData inquiry routine. Set the various keywords to named variables to return information about each field of a VData in a HDF file.

## Syntax

```
HDF_VD_GETINFO, VData, Index [, NAME=variable] [, ORDER=variable]
[, SIZE=variable] [, TYPE=variable]
```

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### Index

A zero-based index specifying which field or the name of the field within the VData to inquire about. For example:

```
HDF_VD_GETINFO, Vdat, 'VEL', ORDER=order
```

## Keywords

### NAME

Set this keyword to a named variable in which the name of the field is returned as a string.

### ORDER

Set this keyword to a named variable in which the order of the field is returned.

### SIZE

Set this keyword to a named variable in which the size of a data value for the specified field in the VData is returned.

### TYPE

Set this keyword to a named variable in which the type of the field is returned. One of the following strings is returned: 'BYTE', 'INT', 'LONG', 'FLOAT', 'DOUBLE'.

## Examples

```
HDF_VD_GET, Vdat, NFIELDS=n
FOR index=0,n-1 DO BEGIN
  HDF_VD_GETINFO, Vdat, index, NAME=n, TYPE=t, ORDER=o
  PRINT, index, ':', n, 'TYPE=', t, 'ORDER=', o
ENDFOR
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_INSERT

The `HDF_VD_INSERT` procedure adds a `VData` or `VGroup` to the contents of a `VGroup` in an HDF file.

## Syntax

```
HDF_VD_INSERT, VGroup, VData [, POSITION=variable]
```

## Arguments

### VGroup

The `VGroup` handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### VData

The `VData` (or `VGroup`) handle returned by [HDF\\_VD\\_ATTACH](#) ([HDF\\_VG\\_ATTACH](#)).

## Keywords

### POSITION

Set this keyword to return the entry position of the element (`VData` or `VGroup`, respectively) within the existing `VGroup` to which you are adding.

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_ISATTR

The `HDF_VD_ISATTR` function determines whether or not a `VData` is storing an attribute. HDF stores attributes as `VData`s, so this routine provides a means to test whether or not a particular `VData` contains an attribute.

## Syntax

*Result* = `HDF_VD_ISATTR(VData)`

## Return Value

Returns `TRUE` (1) if the `VData` is storing an attribute, `FALSE` (0) otherwise.

## Arguments

### **VData**

The `VData` handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

## Keywords

None

## Examples

For an example using this routine, see the documentation for `HDF_VD_ATTRSET`.

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_VD\\_ATTRFIND](#), [HDF\\_VD\\_ATTRINFO](#), [HDF\\_VD\\_ATTRSET](#),  
[HDF\\_VD\\_NATTRS](#)

# HDF\_VD\_ISVD

The HDF\_VD\_ISVD function determines if the object associated with *Id* is a VData in an HDF file.

## Syntax

```
Result = HDF_VD_ISVD(VGroup, Id)
```

## Return Value

Returns True (1) if the object is VData, or False (0) otherwise.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Id

The VGroup reference number obtained by a previous call to [HDF\\_VG\\_GETNEXT](#).

## Keywords

None

## Examples

```
Vid = HDF_VG_GETNEXT(Vgrp, -1)  
PRINT, HDF_VD_ISVD(VGrp, Vid)
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_ISVG

The `HDF_VD_ISVG` function determines if the object associated with *Id* is a VGroup in an HDF file.

## Syntax

*Result* = `HDF_VD_ISVG(VGroup, Id)`

## Return Value

Returns True (1) if the object is a VGroup, or False (0) otherwise.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### Id

The VGroup reference number obtained by a previous call to `HDF_VG_GETNEXT`.

## Keywords

None

## Examples

```
Vid = HDF_VG_GETNEXT(Vgrp, -1)
PRINT, HDF_VD_ISVG(VGrp, Vid)
```

## Version History

4.0	Introduced
-----	------------



# HDF\_VD\_LONE

The HDF\_VD\_LONE function returns an array containing all VDatas in an HDF file that are not contained in another VData.

## Syntax

```
Result = HDF_VD_LONE( FileHandle [, MAXSIZE=value] )
```

## Return Value

Returns any lone VDatas within an array. If there are no lone VDatas, HDF\_VD\_LONE returns -1.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

## Keywords

### MAXSIZE

The maximum number of groups to be returned (the default is to return all known lone VDatas). For example, to return only the first 12 groups:

```
X = HDF_VD_LONE(fid, MAX=12)
```

## Examples

```
X = HDF_VD_LONE(fid)
IF N_ELEMENTS(X) EQ 0 THEN $
PRINT, 'No Lone VDatas' ELSE PRINT, 'Lone VDatas:', X
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_NATTRS

The HDF\_VD\_NATTRS function returns the number of attributes associated with the specified VData or VData/field pair.

## Syntax

*Result* = HDF\_VD\_NATTRS( *VData*, *FieldID* )

## Return Value

Returns the number of attributes if successful. Otherwise, -1 is returned.

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### FieldID

A zero-based index specifying the field, or a string containing the name of the field, within the VData whose attributes are to be counted. Setting Index to -1 specifies that attributes attached to the VData itself are to be counted.

## Keywords

None

## Examples

For an example using this routine, see the documentation for [HDF\\_VD\\_ATTRSET](#).

## Version History

5.5	Introduced
-----	------------

## See Also

[HDF\\_VD\\_ATTRFIND](#), [HDF\\_VD\\_ATTRINFO](#), [HDF\\_VD\\_ATTRSET](#),  
[HDF\\_VD\\_ISATTR](#)

# HDF\_VD\_READ

The `HDF_VD_READ` function reads data from a `VData` in an HDF file.

The default is to use `FULL_INTERLACE` and to read all fields in all records. The user can override the defaults with keywords. If multiple fields with different data types are read, all of the data is read into a byte array. The data must then be explicitly converted back into the correct type(s) using various IDL type conversion routines. For example:

```
nread = HDF_VD_READ(vdat, x, NREC=1, FIELDS="FLT,LNG")
floatvalue = FLOAT(x, 0)
longvalue = LONG(x, 4)
```

## Syntax

```
Result = HDF_VD_READ( VData, Data [, FIELDS=string] [, /FULL_INTERLACE
|, /NO_INTERLACE] [, NRECORDS=records] )
```

## Return Value

This function returns the number of records successfully read from the `VData`.

## Arguments

### **VData**

The `VData` handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### **Data**

A named variable in which the data is returned.

## Keywords

### **FIELDS**

A string containing a comma-separated list of fields to be read. Normally `HDF_VD_READ` will read all fields in the `VData`.

### **FULL\_INTERLACE**

Set this keyword to use full interlace when reading (the default).

## NO\_INTERLACE

Set this keyword to use no interlace when reading.

## NRECORDS

The number of records to read. By default, HDF\_VD\_READ reads all records from a VData.

## Examples

Typical read:

```
NREC = HDF_VD_READ(Vdat, X)
```

Read one field:

```
NREC = HDF_VD_READ(Vdat, X, FIELDS='VEL')
```

Read a record:

```
NREC = HDF_VD_READ(Vdat, X, NRECORDS=1)
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_SEEK

The `HDF_VD_SEEK` procedure moves the read pointer within the specified `VData` in an HDF file to a specific record number. Note that the record number is zero-based.

## Syntax

`HDF_VD_SEEK, VData, Record`

## Arguments

### VData

A `VData` handle returned by [HDF\\_VD\\_ATTACH](#).

### Record

The zero-based record number to seek.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VD\_SETINFO

The `HDF_VD_SETINFO` procedure specifies general information about a `VData` in an HDF file. Keywords can be used to establish the name, class, and interlace for the specified `VData`.

## Syntax

```
HDF_VD_SETINFO, VData [, CLASS=string] [, /FULL_INTERLACE | ,  
/NO_INTERLACE] [, NAME=string]
```

## Arguments

### VData

The `VData` handle returned by a previous call to `HDF_VD_ATTACH`.

## Keywords

### CLASS

A string that sets the class name for the `VData`.

### FULL\_INTERLACE

Set this keyword to store data in the file with full interlace (i.e., sequentially by record).

### NAME

A string that sets the name of the `VData`.

### NO\_INTERLACE

Set this keyword to store data in the file with no interlace (i.e., sequentially by field).

## Examples

```
HDF_VD_SETINFO, Vdat, NAME='My Favorite Data', /FULL
```

## Version History

4.0	Introduced
-----	------------



# HDF\_VD\_WRITE

The `HDF_VD_WRITE` procedure stores data in a `VData` in an HDF file.

There are many restrictions on writing data to a `VData`. When writing multiple fields of varying types, only limited error checking is possible. When writing a series of fields all with the same type, data is converted to that type before writing. For example:

```
Vdat = HDF_VD_ATTACH(Fid, -1, /WRITE)
; Create a 10 integer vector:
Data = INDGEN(10)
; Data converted to FLOAT before write:
HDF_VD_WRITE, Vdat, 'PX', Data
```

It is possible to write less data than exists in the `Data` argument by using the `NRECORDS` keyword. For example, the following command writes 5 records, instead of the 10 implied by the size of the data (`VEL` is assumed to be of type `FLOAT`, `order=3`):

```
HDF_VD_WRITE, Vdat, 'VEL', FINDGEN(3,10),NREC=5
```

`VEL` now contains [ [ 0.0, 1.0, 2.0 ], ..., [ 12.0, 13.0, 14.0 ] ]

`HDF_VD_WRITE` will not allow a user to specify more records than exist. For example, the following command fails:

```
HDF_VD_WRITE, Vdat, 'VEL', [1,2,3], NREC=1000
```

## Known Issues

HDF `vdatas` can only be appended or overwritten if they are defined at creation with a file interlacing mode of `FULL_INTERLACE`. Records in a fully interlaced `vdata` are written record-by-record which allows them to be appended or overwritten. For further information, consult the “Writing to Multi-Field `Vdatas`” section in the *HDF User's Guide* published by the National Center for Supercomputing (available at <http://hdf.ncsa.uiuc.edu/doc.html>).

## Restrictions

It is not possible to write IDL structures directly to a `VData` (because of possible internal padding depending upon fields/machine architecture, etc.). The user must put the data into a byte array before using `HDF_VD_WRITE`.

When writing a series of fields all with the same type, the low order dimension of *Data* must match the sum of the orders of the fields. For example:

```
HDF_VD_WRITE, vdat, 'PX,PY', FLTARR(3,10)
```

fails. PX and PY are both order 1 (total 2) and the array's low order dimension is 3.

## Syntax

```
HDF_VD_WRITE, VData, Fields, Data  
[, /FULL_INTERLACE | , /NO_INTERLACE] [, NRECORDS=records]
```

## Arguments

### VData

The VData handle returned by a previous call to [HDF\\_VD\\_ATTACH](#).

### Fields

A string containing a comma-separated list of the fields to be written.

### Data

The data to be written to the specified VData.

## Keywords

### FULL\_INTERLACE

Set this keyword to use full interlace when writing (the default).

### NO\_INTERLACE

Set this keyword to use no interlace when writing.

### NRECORDS

The number of records to written. By default, `HDF_VD_WRITE` writes all records from a VData.

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_ADDTR

The HDF\_VG\_ADDTR procedure adds a tag and reference to the specified VGroup in an HDF file.

## Syntax

HDF\_VG\_ADDTR, *VGroup*, *Tag*, *Ref*

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Tag

The tag to be written.

### Reference

The reference number to be written.

## Keywords

None

## Examples

See "[HDF\\_SD\\_IDTOREF](#)" on page 498 for an example using this function.

## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_VG\\_GETTR](#), [HDF\\_VG\\_GETTRS](#), [HDF\\_VG\\_INQTR](#), [HDF\\_VG\\_INSERT](#)

# HDF\_VG\_ATTACH

The HDF\_VG\_ATTACH function attaches (opens) a VGroup in an HDF file for reading or writing.

If VGroup\_id is set to -1, a new VGroup is created. If neither the READ nor WRITE keywords are set, the VGroup is opened for reading.

## Syntax

```
Result = HDF_VG_ATTACH( FileHandle, VGroup_id [, /READ] [, /WRITE] )
```

## Return Value

If successful, a handle for the specified group is returned. If it fails, 0 is returned.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### VGroup\_id

The VGroup reference number, generally obtained by HDF\_VG\_GETID or HDF\_VG\_LONE.

## Keywords

### READ

Set this keyword to open the VGroup for reading.

### WRITE

Set this keyword to open the VGroup for writing.

## Examples

See “[HDF\\_SD\\_IDTOREF](#)” on page 498 for an example using this function.

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_VG\\_DETACH](#)

# HDF\_VG\_DETACH

The HDF\_VG\_DETACH procedure should be called when you are finished accessing a VGroup in an HDF file. This routine must be called for every VGroup attached for writing before closing the HDF file in order to insure that VSET information is properly updated.

## Syntax

HDF\_VG\_DETACH, *VGroup*

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

## Keywords

None

## Examples

See “[HDF\\_SD\\_IDTOREF](#)” on page 498 for an example using this function.

## Version History

---

4.0	Introduced
-----	------------

---

## See Also

[HDF\\_VG\\_ATTACH](#)

# HDF\_VG\_GETID

The HDF\_VG\_GETID function returns the VGroup ID for the next VGroup after the specified VGroup\_id in an HDF file. Use a VGroup\_id of -1 to get the first VGroup in the file.

## Syntax

*Result* = HDF\_VG\_GETID(*FileHandle*, *VGroup\_id*)

## Return Value

Returns the next VGroup ID.

## Arguments

### FileHandle

The HDF file handle returned from a previous call to HDF\_OPEN.

### VGroup\_id

The VGroup reference number, generally obtained by HDF\_VG\_GETID or HDF\_VG\_LONE.

## Keywords

None

## Examples

See “[HDF\\_SD\\_IDTOREF](#)” on page 498 for an example using this function.

## Version History

4.0	Introduced
-----	------------



# HDF\_VG\_GETINFO

The HDF\_VG\_GETINFO procedure is a general VGroup inquiry routine. Set the various keywords to named variables to return information about different aspects of a VGroup in an HDF file.

## Syntax

```
HDF_VG_GETINFO, VGroup [, CLASS=variable] [, NAME=variable]  
[, NENTRIES=variable] [, REF=variable] [, TAG=variable]
```

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

## Keywords

### CLASS

Set this keyword to a named variable in which the class of the VGroup is returned as a string.

### NAME

Set this keyword to a named variable in which the name of the VGroup is returned as a string.

### NENTRIES

Set this keyword to a named variable in which the number of objects inside the VGroup is returned as a long integer.

### REF

Set this keyword to a named variable in which the reference number of the specified Vgroup is returned.

### TAG

Set this keyword to a named variable in which the tag number of the specified Vgroup is returned.

## Examples

```
HDF_VG_GETINFO, Vgrp, CLASS=c, NAME=nm, NENTRIES=n  
PRINT, c, nm, n
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_GETNEXT

The HDF\_VG\_GETNEXT function returns the reference number of the next object inside a VGroup in an HDF file. If Id is -1, the first item in the VGroup is returned, otherwise Id should be set to a reference number previously returned by HDF\_VG\_GETNEXT.

## Syntax

*Result* = HDF\_VG\_GETNEXT(*VGroup*, *Id*)

## Return Value

Returns the reference number of the next object or returns -1 if there was an error or there are no more objects after the one specified by Id.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Id

A VGroup or VData reference number obtained by a previous call to HDF\_VG\_GETNEXT. Alternatively, this value can be set to -1 to return the first item in the VGroup.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_GETTR

The HDF\_VG\_GETTR procedure returns the tag/reference pair at the specified position within a VGroup in an HDF file.

## Syntax

HDF\_VG\_GETTR, *VGroup*, *Index*, *Tags*, *Refs*

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Index

The position within *VGroup*.

### Tags

A named variable in which the tag numbers are returned.

### Refs

A named variable in which the reference numbers are returned.

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_GETTRS

The HDF\_VG\_GETTRS procedure returns the tag/reference pairs of the HDF file objects belonging to the specified VGroup.

## Syntax

```
HDF_VG_GETTRS, VGroup, Tags, Refs [, MAXSIZE=value]
```

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Tags

A named variable in which the tag numbers are returned.

### Refs

A named variable in which the reference numbers are returned.

## Keywords

### MAXSIZE

The maximum number of tags and references to be returned. The default is to return all tags and references in VGroup.

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_INQTR

The HDF\_VG\_INQTR function returns true if the specified tag and reference pair is linked to the specified VGroup in an HDF file.

## Syntax

*Result* = HDF\_VG\_INQTR(*VGroup*, *Tag*, *Ref*)

## Return Value

Returns true if the link exists.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Tag

The tag number.

### Ref

The reference number.

## Keywords

None

## Examples

See “[HDF\\_SD\\_IDTOREF](#)” on page 498 for an example using this function.

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_INSERT

The `HDF_VG_INSERT` procedure adds a `VData` or `VGroup` to the contents of a `VGroup` in an HDF file.

## Syntax

```
HDF_VG_INSERT, VGroup, VData [, POSITION=variable]
```

## Arguments

### VGroup

The `VGroup` handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### VData

The `VData` (or `VGroup`) handle returned by [HDF\\_VD\\_ATTACH](#) ([HDF\\_VG\\_ATTACH](#)).

## Keywords

### POSITION

Set this keyword to return the current position of the element (`VData` or `VGroup`, respectively) within the existing data group.

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_ISVD

The HDF\_VG\_ISVD function returns true if the object associated with *Id* is a VData in an HDF file.

## Syntax

```
Result = HDF_VG_ISVD(VGroup, Id)
```

## Return Value

Returns true if the specified object is a VData.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Id

The VGroup or VData reference number obtained by a previous call to [HDF\\_VG\\_GETNEXT](#).

## Keywords

None

## Examples

```
Vid = HDF_VG_GETNEXT(Vgrp, -1)  
PRINT, HDF_VG_ISVD(VGrp, Vid)
```

## Version History

4.0	Introduced
-----	------------



# HDF\_VG\_ISVG

The `HDF_VG_ISVG` function returns true if the object associated the `Id` is a `VGroup` in an HDF file.

## Syntax

```
Result = HDF_VG_ISVG(VGroup, Id)
```

## Return Value

Returns true if the specified object is a `VGroup`.

## Arguments

### VGroup

The `VGroup` handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

### Id

The `VGroup` or `VData` reference number obtained by a previous call to `HDF_VG_GETNEXT`.

Keywords

## Examples

```
Vid = HDF_VG_GETNEXT(Vgrp, -1)
PRINT, HDF_VG_ISVG(VGrp, Vid)
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_LONE

The HDF\_VG\_LONE function returns an array containing the IDs of all VGroups in an HDF file that are not contained in another VGroup.

## Syntax

```
Result = HDF_VG_LONE( FileHandle [, MAXSIZE=value] )
```

## Return Value

Returns the IDs of lone VGroups or returns -1 if there are no lone VGroups,.

## Arguments

### FileHandle

The HDF file handle returned by a previous call to HDF\_OPEN.

## Keywords

### MAXSIZE

The maximum number of groups to return (the default is to return all lone VGroups). For example, to return no more than 12 VGroups, use the command:

```
X = HDF_VG_LONE(fid, MAX=12)
```

## Examples

```
X=HDF_VG_LONE(fid)
IF X(0) EQ-1 THEN $
    PRINT, "No Lone VGroups" ELSE PRINT, "Lone VGroups:", X
```

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_NUMBER

The HDF\_VG\_NUMBER function returns the number of HDF file objects in the specified VGroup.

## Syntax

*Result* = HDF\_VG\_NUMBER(*VGroup*)

## Return Value

Returns the number of objects.

## Arguments

### VGroup

The VGroup handle returned by a previous call to [HDF\\_VG\\_ATTACH](#).

## Keywords

None

## Version History

4.0	Introduced
-----	------------

# HDF\_VG\_SETINFO

The HDF\_VG\_SETINFO procedure sets the name and class of a VGroup.

## Syntax

```
HDF_VG_SETINFO, VGroup [, CLASS=string] [, NAME=string]
```

## Arguments

### VGroup

The VGroup handle as returned by HDF\_VG\_ATTACH.

## Keywords

### CLASS

A string containing the class name for the VGroup.

### NAME

A string containing the name for the VGroup.

## Examples

```
fid = HDF_OPEN('demo.hdf',/RDWR) ; Open an HDF file:
vgid = HDF_VG_ATTACH(fid, -1, /WRITE) ; Add a new VGroup:
; Set the name and class for the VGroup:
HDF_VG_SETINFO, vgid, NAME='My Name', CLASS='My VGroup Class'
; Retrieve the name and class information from the file:
HDF_VG_GETINFO, vgid, NAME=outname, CLASS=outclass
; Print information about the returned variables:
HELP, outname, outclass
; End VGroup access:
HDF_VG_DETACH, vgid
; Close the HDF file:
HDF_CLOSE, fid
```

### IDL Output

```
OUTNAME STRING = 'My Name'
OUTCLASS STRING = 'My VGroup Class'
```


## Version History

4.0	Introduced
-----	------------

## See Also

[HDF\\_VG\\_GETINFO](#)





# Chapter 5

# HDF-EOS

The following topics are covered in this appendix:

---

Overview of the HDF-EOS .....	576	HDF-EOS Programming Model .....	578
Feature Routines .....	577	Alphabetical Listing of EOS Routines ...	580

# Overview of the HDF-EOS

HDF-EOS (Hierarchical Data Format-Earth Observing System) is an extension of NCSA (National Center for Supercomputing Applications) HDF and uses HDF calls as an underlying basis. This API contains functionality for creating, accessing and manipulating Grid, Point and Swath structures. IDL's HDF-EOS routines all begin with the prefix "EOS\_". This version of IDL supports HDF-EOS 2.8.

**Note**

---

On the AIX platform, the HDF-EOS library supports version 2.4.

---

HDF-EOS is a product of NASA, information may be found at:

<http://hdfeos.gsfc.nasa.gov>



# Feature Routines

HDF-EOS is an extension of NCSA (National Center for Supercomputing Applications) HDF and uses HDF calls as an underlying basis. This API contains functionality for creating, accessing and manipulating Grid, Point and Swath structures.

The Grid interface is designed to support data that has been stored in a rectilinear array based on a well-defined and explicitly supported projection.

Tips on writing a grid:

- Setting a compression method affects all subsequently defined fields
- Setting a tiling scheme affects all subsequently defined fields

The Point interface is designed to support data that has associated geolocation information, but is not organized in any well-defined spatial or temporal way.

Tips on writing a point:

- Every level in a point data set must be linked into the hierarchy
- Before two levels can be linked, a link field must exist

The Swath interface is tailored to support time-oriented data such as satellite swaths (which consist of a time-oriented series of scanlines), or profilers (which consist of a time-oriented series of profiles).

Tips on writing a swath:

- Define dimensions before using them to define fields of maps
- Setting a compression method affects all subsequently defined fields
- If a dimension map is not defined, a one-to-one mapping is assumed during subsetting.

# HDF-EOS Programming Model

## Writing

- open file
- create object
- define structure
- detach object
- attach object
- write data
- detach object
- close file

## Reading

- open file
- attach object
- inquire object
- read data
- detach object
- close file

---

**Note**

When writing an HDF-EOS object, be sure to detach the object before attaching it for the first time. This will initialize the library for the new object. The object will not be written correctly if the above model is not followed.

---

## Note on Array Ordering

In versions prior to version 5.5, IDL was inconsistent in its handling of array ordering between IDL and C-language routines in the HDF-EOS library. Beginning with IDL 5.5, all data arrays (either input or output) use standard IDL array ordering. Dimension size vectors and dimension name lists are also now in IDL order rather than in C-language order.

Programs written using versions of the IDL HDF-EOS routines prior to IDL version 5.5 may have been created to intentionally compensate for the previous behavior. When used with IDL 5.5 and later versions of the IDL HDF-EOS routines, these programs may generate incorrect results.

Affected routines include:

<a href="#">EOS_SW_DEFDATAFIELD</a>	<a href="#">EOS_GD_DEFFIELD</a>
<a href="#">EOS_SW_DEFGEOFIELD</a>	<a href="#">EOS_GD_DEFTILE</a>
<a href="#">EOS_SW_EXTRACTPERIOD</a>	<a href="#">EOS_GD_READFIELD</a>
<a href="#">EOS_SW_EXTRACTREGION</a>	<a href="#">EOS_GD_READTILE</a>
<a href="#">EOS_SW_PERIODINFO</a>	<a href="#">EOS_GD_REGIONINFO</a>
<a href="#">EOS_SW_READFIELD</a>	<a href="#">EOS_GD_TILEINFO</a>
<a href="#">EOS_SW_REGIONINFO</a>	<a href="#">EOS_GD_WRITEFIELD</a>
<a href="#">EOS_SW_WRITEDATAMETA</a>	<a href="#">EOS_GD_WRITEFIELDMETA</a>
<a href="#">EOS_SW_WRITEFIELD</a>	<a href="#">EOS_GD_WRITETILE</a>
<a href="#">EOS_SW_WRITEGEOMETA</a>	

---

### Note

For the [EOS\\_GD\\_READFIELD](#), [EOS\\_SW\\_READFIELD](#), [EOS\\_GD\\_WRITEFIELD](#), and [EOS\\_SW\\_WRITEFIELD](#) routines, the `START`, `STRIDE`, and `EDGE` keywords should also be specified in the IDL dimension order.

---

### Note

[EOS\\_GD\\_INQDIMS](#) and [EOS\\_SW\\_INQDIMS](#) return dimension size and name information without consideration of order.

---

# Alphabetical Listing of EOS Routines

EOS\_EH\_CONVANG  
EOS\_EH\_GETVERSION  
EOS\_EH\_IDINFO  
EOS\_EXISTS  
EOS\_GD\_ATTACH  
EOS\_GD\_ATTRINFO  
EOS\_GD\_BLKSSOMOFFSET  
EOS\_GD\_CLOSE  
EOS\_GD\_COMPINFO  
EOS\_GD\_CREATE  
EOS\_GD\_DEFBOXREGION  
EOS\_GD\_DEFCOMP  
EOS\_GD\_DEFDIM  
EOS\_GD\_DEFFIELD  
EOS\_GD\_DEFORIGIN  
EOS\_GD\_DEFPIXREG  
EOS\_GD\_DEFPROJ  
EOS\_GD\_DEFTILE  
EOS\_GD\_DEFVRTREGION  
EOS\_GD\_DETACH  
EOS\_GD\_DIMINFO  
EOS\_GD\_DUPREGION  
EOS\_GD\_EXTRACTREGION  
EOS\_GD\_FIELDINFO  
EOS\_GD\_GETFILLVALUE  
EOS\_GD\_GETPIXELS

EOS\_GD\_GETPIXVALUES  
EOS\_GD\_GRIDINFO  
EOS\_GD\_INQATTRS  
EOS\_GD\_INQDIMS  
EOS\_GD\_INQFIELDS  
EOS\_GD\_INQGRID  
EOS\_GD\_INTERPOLATE  
EOS\_GD\_NENTRIES  
EOS\_GD\_OPEN  
EOS\_GD\_ORIGININFO  
EOS\_GD\_PIXREGINFO  
EOS\_GD\_PROJINFO  
EOS\_GD\_QUERY  
EOS\_GD\_READATTR  
EOS\_GD\_READFIELD  
EOS\_GD\_READTILE  
EOS\_GD\_REGIONINFO  
EOS\_GD\_SETFILLVALUE  
EOS\_GD\_SETTILECACHE  
EOS\_GD\_TILEINFO  
EOS\_GD\_WRITEATTR  
EOS\_GD\_WRITEFIELD  
EOS\_GD\_WRITEFIELDMETA  
EOS\_GD\_WRITETILE  
EOS\_PT\_ATTACH  
EOS\_PT\_ATTRINFO  
EOS\_PT\_BCKLINKINFO  
EOS\_PT\_CLOSE

EOS\_PT\_CREATE  
EOS\_PT\_DEFBOXREGION  
EOS\_PT\_DEFLEVEL  
EOS\_PT\_DEFLINKAGE  
EOS\_PT\_DEFTIMEPERIOD  
EOS\_PT\_DEFVRTREGION  
EOS\_PT\_DETACH  
EOS\_PT\_EXTRACTPERIOD  
EOS\_PT\_EXTRACTREGION  
EOS\_PT\_FWDLINKINFO  
EOS\_PT\_GETLEVELNAME  
EOS\_PT\_GETRECNUMS  
EOS\_PT\_INQATTRS  
EOS\_PT\_INQPOINT  
EOS\_PT\_LEVELINDX  
EOS\_PT\_LEVELINFO  
EOS\_PT\_NFIELDS  
EOS\_PT\_NLEVELS  
EOS\_PT\_NRECS  
EOS\_PT\_OPEN  
EOS\_PT\_PERIODINFO  
EOS\_PT\_PERIODRECS  
EOS\_PT\_QUERY  
EOS\_PT\_READATTR  
EOS\_PT\_READLEVEL  
EOS\_PT\_REGIONINFO  
EOS\_PT\_REGIONRECS  
EOS\_PT\_SIZEOF

EOS\_PT\_UPDATELEVEL  
EOS\_PT\_WRITEATTR  
EOS\_PT\_WRITELEVEL  
EOS\_QUERY  
EOS\_SW\_ATTACH  
EOS\_SW\_ATTRINFO  
EOS\_SW\_CLOSE  
EOS\_SW\_COMPINFO  
EOS\_SW\_DEFBOXREGION  
EOS\_SW\_DEFBOXREGION  
EOS\_SW\_DEFCOMP  
EOS\_SW\_DEFDATAFIELD  
EOS\_SW\_DEFDIM  
EOS\_SW\_DEFDIMMAP  
EOS\_SW\_DEFGEOFIELD  
EOS\_SW\_DEFIDXMAP  
EOS\_SW\_DEFTIMEPERIOD  
EOS\_SW\_DEFVRTREGION  
EOS\_SW\_DETACH  
EOS\_SW\_DIMINFO  
EOS\_SW\_DUPREGION  
EOS\_SW\_EXTRACTPERIOD  
EOS\_SW\_EXTRACTREGION  
EOS\_SW\_FIELDINFO  
EOS\_SW\_GETFILLVALUE  
EOS\_SW\_IDXMAPINFO  
EOS\_SW\_INQATTRS  
EOS\_SW\_INQDATAFIELDS

EOS\_SW\_INQDIMS  
EOS\_SW\_INQGEOFIELDS  
EOS\_SW\_INQIDXMAPS  
EOS\_SW\_INQMAPS  
EOS\_SW\_INQSWATH  
EOS\_SW\_MAPINFO  
EOS\_SW\_NENTRIES  
EOS\_SW\_OPEN  
EOS\_SW\_PERIODINFO  
EOS\_SW\_QUERY  
EOS\_SW\_READATTR  
EOS\_SW\_READFIELD  
EOS\_SW\_REGIONINFO  
EOS\_SW\_SETFILLVALUE  
EOS\_SW\_WRITEATTR  
EOS\_SW\_WRITEDATAMETA  
EOS\_SW\_WRITEFIELD  
EOS\_SW\_WRITEGEOMETA



# EOS\_EH\_CONVANG

This function converts angles between three units: decimal degrees, radians, and packed degrees-minutes-seconds. In the degrees-minutes-seconds unit, an angle is expressed as an integral number of degrees and minutes and a float point value of seconds packed as a single double as follows: DDDMMMSS.SS.

## Syntax

*Result* = EOS\_EH\_CONVANG(*inAngle*, *code*)

## Return Value

Returns angle in desired units.

## Arguments

### **inAngle**

Input angle (float).

### **code**

Conversion code (long). Allowable values are:

- 0 = Radians to Degrees
- 1 = Degrees to Radians
- 2 = DMS to Degrees
- 3 = Degrees to DMS
- 4 = Radians to DMS
- 5 = DMS to Radians

## Keywords

None

## Examples

To convert 27.5 degrees to packed format:

```
inAng = 27.5  
outAng = EOS_EH_CONVANG(inAng, 3)
```

outAng will contain the value 27030000.00.

## Version History

5.2	Introduced
-----	------------

# EOS\_EH\_GETVERSION

The EOS\_EH\_GETVERSION function is used to retrieve the HDF-EOS version string of an HDF-EOS file, which is returned in the *version* argument. This designates the version of HDF-EOS that was used to create the file. This string is of the form “HDFEOS\_Vmaj.min” where maj is the major version and min is the minor version.

## Syntax

*Result* = EOS\_EH\_GETVERSION(*fid*, *version*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **fid**

File id (long) returned by EOS\_SW\_OPEN, EOS\_GD\_OPEN, or EOS\_PT\_OPEN.

### **version**

HDF-EOS version (string).

## Keywords

None

## Examples

To get the HDF-EOS version (assumed to be 2.3) used to create the HDF-EOS file:

```
fid = EOS_SW_OPEN("Swathfile.hdf", /READ)
status = EOS_EH_GETVERSION(fid, version)
```

*version* will contain the string “HDFEOS\_V2.3”.

## Version History

5.2	Introduced
-----	------------

# EOS\_EH\_IDINFO

This function returns the HDF file IDs corresponding to the HDF-EOS file ID returned by EOS\_SW\_OPEN, EOS\_GD\_OPEN, or EOS\_PT\_OPEN. These IDs can then be used to create or access native HDF structures such as SDS arrays, Vdatas, or HDF attributes within an HDF-EOS file.

## Syntax

```
Result = EOS_EH_IDINFO(fid, HDFfid, sdInterfaceID)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **fid**

File ID (long) returned by EOS\_SW\_OPEN, EOS\_GD\_OPEN, or EOS\_PT\_OPEN.

### **HDFfid**

A named variable that will contain the HDF file ID (long) returned by Hopen.

### **sdInterfaceID**

A named variable that will contain the SD interface ID (long) returned by SDstart.

## Keywords

None

## Examples

To create a vdata within an existing HDF-EOS file:

```
fid = EOS_SW_OPEN("SwathFile.hdf", /RDWR)  
status = EOS_EH_IDINFO(fid, hdfid, sdid)
```

## Version History

# EOS\_EXISTS

The EOS\_EXISTS function determines whether the current HDF-EOS extensions are supported on the current platform.

## Syntax

*Result* = EOS\_EXISTS()

## Return Value

Returns success (1) if the HDF-EOS extensions are supported, and fail (0) if not.

## Arguments

None

## Keywords

None

## Examples

```
IF (~ HDF_EOS_EXISTS) THEN PRINT, 'HDF-EOS not available.'
```

## Version History

5.2.1	Introduced
-------	------------

# EOS\_GD\_ATTACH

This function attaches to the grid using the gridname parameter as the identifier.

## Syntax

```
Result = EOS_GD_ATTACH(fid, gridname)
```

## Return Value

Returns the grid handle (gridID) if successful and FAIL(-1) otherwise.

## Arguments

### fid

Grid file id (long) returned by EOS\_GD\_OPEN.

### gridname

Name of grid (string) to be attached.

## Keywords

None

## Examples

In this example, we attach to the previously created grid, "ExampleGrid", within the HDF file, GridFile.hdf, referred to by the handle, fid:

```
gridID = EOS_GD_ATTACH(fid, "ExampleGrid")
```

The grid can then be referenced by subsequent routines using the handle, gridID.

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_GD\\_DETACH](#)



# EOS\_GD\_ATTRINFO

This function returns number type and number of elements (count) of a grid attribute.

## Syntax

```
Result = EOS_GD_ATTRINFO(gridID, attrname, numbertype, count)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### attrname

Attribute name (string).

### numbertype

A named variable that will contain the number type (long) of an attribute.

### count

A named variable that will contain the number of total bytes in an attribute (long).

## Keywords

None

## Examples

In this example, we return information about the ScalarFloat attribute:

```
status = EOS_GD_ATTRINFO(pointID, "ScalarFloat", nt, count)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_BLKSOFFSET

This function writes block SOM offset values. This is a special function for SOM MISR data.

## Syntax

*Result* = EOS\_GD\_BLKSOFFSET(*gridID*, *offset*, *code*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### gridID

The grid ID (long) as returned from [EOS\\_GD\\_ATTACH](#).

### offset

A scalar or array of offset values. The offset must be initialized to the correct data type and number of elements for the values to be written correctly.

### code

The type of action performed (read (r), write (w)). This value must be set to either the string r or w. If the string value is not recognized, the *code* defaults to r.

## Keywords

None

## Version History

5.3	Introduced
-----	------------

# EOS\_GD\_CLOSE

This function closes the HDF grid file.

## Syntax

```
Result = EOS_GD_CLOSE(fid)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

**fid**

Grid file id (long) returned by EOS\_GD\_OPEN.

## Keywords

None

## Examples

```
status = EOS_GD_CLOSE(fid)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_COMPINFO

This function returns the compression code and compression parameters for a given field.

## Syntax

```
Result = EOS_GD_COMPINFO(gridID, fieldname, compcode, compparm)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **fieldname**

Fieldname (string).

### **compcode**

A named variable that will contain the HDF compression code (long).

### **compparm**

A named variable that will contain the compression parameters (long array).

## Keywords

None

## Examples

To retrieve the compression information about the Opacity field defined in the EOS\_GD\_DEFCOMP section:

```
status = EOS_GD_COMPINFO(gridID, "Opacity", compcode,  
compparm)
```

## Version History

---

5.2	Introduced
-----	------------

---

## See Also

[EOS\\_GD\\_DEFCOMP](#)

# EOS\_GD\_CREATE

This function creates a grid within the file. The grid is created as a Vgroup within the HDF file with the name `gridname` and class `GRID`. This function establishes the resolution of the grid, (i.e., the number of rows and columns), and its location within the complete global projection through the `upleftpt` and `lowrightpt` arrays. These arrays should be in meters for all GCTP projections other than the Geographic Projection, which should be in packed degree format (q.v. below). For GCTP projection information, see the *HDF-EOS User's Guide, Volume 2: Reference Guide* provided by NASA.

## Syntax

*Result* = EOS\_GD\_CREATE(*fid*, *gridname*, *xdimsize*, *ydimsize*, *upleftpt*, *lowrightpt*)

## Return Value

Returns the grid handle (`gridID`) and `FAIL(-1)` otherwise.

## Arguments

### **fid**

Grid file id (long) returned by `EOS_GD_OPEN`.

### **gridname**

Name of grid (string) to be created.

### **xdimsize**

Number of columns (long) in grid.

### **ydimsize**

Number of rows (long) in grid.

### **upleftpt**

Location (double, 2 element array) of upper left corner of the upper left pixel.

## lowrightpt

Location (double, 2 element array) of lower right corner of the lower right pixel.

## Keywords

None

## Examples

In this example, we create a UTM grid bounded by 54 E to 60 E longitude and 20 N to 30 N latitude. We divide it into 120 bins along the x-axis and 200 bins along the y-axis.

```
uplft[0]=10584.50041d
uplft[1]=3322395.95445d
lowrgt[0]=813931.10959d
lowrgt[1]=214162.53278d
xdim=120
ydim=200
gridID = EOS_GD_CREATE(fid, "UTMGrid", xdim, ydim, uplft, lowrgt)
```

The grid structure is then referenced by subsequent routines using the handle, gridID.

The xdim and ydim values are referenced in the field definition routines by the reserved dimensions: XDim and YDim.

For the Polar Stereographic, Goode Homolosine and Lambert Azimuthal projections, we have established default values in the case of an entire hemisphere for the first projection, the entire globe for the second and the entire polar or equatorial projection for the third.

In the case of the Geographic projection (linear scale in both longitude latitude), the upleftpt and lowrightpt arrays contain the longitude and latitude of these points in packed degree format (DDDMMMSS.SS).

- upleftpt- Array that contains the X-Y coordinates of the upper left corner of the upper left pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The upper left X coordinate value should be the lowest X value of the grid. The upper left Y coordinate value should be the highest Y value of the grid.
- lowrightpt - Array that contains the X-Y coordinates of the lower right corner of the lower right pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The lower right X coordinate



value should be the highest X value of the grid. The lower right Y coordinate value should be the lowest Y value of the grid.

If the projection is geographic (i.e., projcode=0) then the X-Y coordinates should be specified in degrees/minutes/seconds (DDMMSS.SS) format. The first element of the array holds the longitude and the second element holds the latitude. Latitudes are from -90 to +90 and longitudes are from -180 to +180 (west is negative).

For all other projection types the X-Y coordinates should be in meters in double precision. These coordinates have to be computed using the GCTP software with the same projection parameters that have been specified in the projparm array. For UTM projections use the same zone code and its sign (positive or negative) while computing both upper left and lower right corner X-Y coordinates irrespective of the hemisphere.

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFBOXREGION

This function defines a longitude-latitude box region for a grid. It returns a grid region ID which is used by the EOS\_GD\_EXTRACTREGION function to read all the entries of a data field within the region.

## Syntax

*Result* = EOS\_GD\_DEFBOXREGION(*gridID*, *cornerlon*, *cornerlat*)

## Return Value

Returns the grid region ID if successful and FAIL (-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### cornerlon

Longitude (double, 2 element array) in decimal degrees of box corners.

### cornerlat

Latitude (double, 2 element array) in decimal degrees of box corners.

## Keywords

None

## Examples

In this example, we define the region to be the first quadrant of the Northern hemisphere:

```
cornerlon[0] = 0.d
cornerlat[0] = 90.d
cornerlon[1] = 90.d
cornerlat[1] = 0.d
regionID = EOS_GD_DEFBOXREGION(EOS_GD_id, cornerlon, cornerlat)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFCOMP

This function sets the HDF field compression for subsequent grid field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported are: run length encoding (1), skipping Huffman (3), deflate (gzip) (4) and no compression (0, the default). Deflate compression requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression.

Compressed fields are written using the standard EOS\_GD\_WRITEFIELD function, however, the entire field must be written in a single call. If this is not possible, the user should consider tiling. See [EOS\\_GD\\_DEFTILE](#) for further information. Any portion of a compressed field can then be accessed with the EOS\_GD\_READFIELD function. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of compression schemes and parameters.

## Syntax

*Result* = EOS\_GD\_DEFCOMP(*gridID*, *compcode* [, *compparm* ] )

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### compcode

HDF compression code (long).

Allowable values are:

- 0 = None
- 1 = Run Length Encoding (RLE)
- 3 = Skipping Huffman
- 4 = Deflate (gzip)

## compparm

Compression parameters array. Compparm is an array argument whose value(s) depend on the compression scheme selected.

## Keywords

None

## Examples

Suppose we wish to compress the Pressure field using run length encoding, the Opacity field using deflate compression, the Spectra field with skipping Huffman compression, and use no compression for the Temperature field:

```
status = EOS_GD_DEFCOMP(gridID, 1)
status = EOS_GD_DEFFIELD(gridID, "Pressure", "YDim,XDim", 5)
compparm[0] = 5
status = EOS_GD_DEFCOMP(gridID, 4, compparm)
status = EOS_GD_DEFFIELD(gridID, "Opacity", "YDim,XDim", 5)
status = EOS_GD_DEFCOMP(gridID, 3)
status = EOS_GD_DEFFIELD(gridID, "Spectra", "Bands,YDim,XDim", 5)
status = EOS_GD_DEFCOMP(gridID, 0)
status = EOS_GD_DEFFIELD(gridID, "Temperature", "YDim,XDim", 5,$
/MERGE)
```

Note that the MERGE keyword will be ignored in the Temperature field definition.

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFDIM

This function defines dimensions that are used by the field definition routines (described subsequently) to establish the size of the field.

## Syntax

```
Result = EOS_GD_DEFDIM(gridID, dimname, dim)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### dimname

Name of dimension to be defined (string).

### dim

The size of the dimension (long).

## Keywords

None

## Examples

In this example, we define a dimension, Band, with size 15:

```
status = EOS_GD_DEFDIM(gridID, "Band", 15)
```

To specify an unlimited dimension that can be used to define an appendable array, the dimension value should be set to zero:

```
status = EOS_GD_DEFDIM(gridID, "Unlim", 0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFFIELD

This function defines data fields to be stored in the grid. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, numbertype. If the MERGE keyword is not set, the API will not attempt to merge it with other fields. Fields using the unlimited dimension will not be merged. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF-EOS fields directly using HDF.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_DEFFIELD(*gridID*, *fieldname*, *dimlist*, *numbertype* [, /MERGE])

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Name of field (string) to be defined.

### dimlist

The list of data dimensions (string) defining the field.

### numbertype

The HDF data type (long) of the data stored in the field



## Keywords

### MERGE

If set, automerger will occur.

## Examples

In this example, we define a grid field, Temperature with dimensions XDim and YDim (as established by the EOS\_GD\_CREATE routine) containing 4-byte floating point numbers and a field, Spectra, with dimensions XDim, YDim, and Bands:

```
status = EOS_GD_DEFFIELD(gridID, "Temperature", &
    "YDim,XDim", 5, /MERGE)
status = EOS_GD_DEFFIELD(gridID, "Spectra", "Bands,YDim,XDim", 5)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFORIGIN

This function defines the origin of the grid data. This allows the user to select any corner of the grid as the origin.

## Syntax

```
Result = EOS_GD_DEFORIGIN(gridID, origincode)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### origincode

Location of the origin (long) of the grid data. The allowable values are:

- 0 = Upper left
- 1 = Upper right
- 2 = Lower left
- 3 = Lower right

## Keywords

None

## Examples

In this Example we define the origin of the grid to be the Lower Right corner:

```
status = EOS_GD_DEFORIGIN(gridID, 3)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFPIXREG

This function defines whether the pixel center or pixel corner (as defined by the EOS\_GD\_DEFORIGIN function) is used when requesting the location (longitude and latitude) of a given pixel.

## Syntax

*Result* = EOS\_GD\_DEFPIXREG(*gridID*, *pixreg*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### pixreg

Pixel registration (long). The allowable values are:

- 0 = Center
- 1 = Corner

## Keywords

None

## Examples

In this example, we define the pixel registration to be the corner of the pixel cell:

```
status = EOS_GD_DEFPIXREG(gridID, 1)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFPROJ

This function defines the GCTP projection and projection parameters of the grid. For GCTP projection information, see the *HDF-EOS User's Guide, Volume 2: Reference Guide* provided by NASA.

## Syntax

*Result* = EOS\_GD\_DEFPROJ(*gridID*, *projcode*, *zonecode*, *spherecode*, *projparm*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### projcode

GCTP projection code (long).

### zonecode

GCTP zone code used by UTM projection (long).

### spherecode

GCTP spheroid code (long).

### projparm

GCTP projection parameter array.

## Keywords

None

## Examples

### Example 1

In this example, we define a Universal Transverse Mercator (UTM) grid bounded by 54 E - 60 E longitude and 20 N - 30 N latitude - UTM zonecode 40, using default spheroid (Clarke 1866), spherecode = 0:

```
spherecode = 0
zonecode = 40
status = EOS_GD_DEFPROJ(gridID, 1, zonecode, spherecode, 0)
```

### Example 2

In this example, we define a Polar Stereographic projection of the Northern Hemisphere (True scale at 90 N, 0 Longitude below pole) using the International 1967 spheroid:

```
spherecode = 3
projparm = lonarr (13)
;Set Long below pole & true scale in DDDMMMSS.SSS form
projparm[5] = 90000000.00
status = EOS_GD_DEFPROJ(gridID, 6, 0, spherecode, projparm)
```

### Example 3

Finally, we define a Geographic projection. In this case, neither the zone code, sphere code, or the projection parameters are used:

```
status = EOS_GD_DEFPROJ(gridID, 0, 0, 0, 0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DEFTILE

This function defines the tiling dimensions for fields defined following this function call, analogous to the procedure for setting the field compression scheme using EOS\_GD\_DEFCOMP. The number of tile dimensions and subsequent field dimensions must be the same and the tile dimensions must be integral divisors of the corresponding field dimensions. A tile dimension set to 0 will be equivalent to 1.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_DEFTILE( *gridID*, *tilecode* [, *tilerank*, *tiledims*] )

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **tilecode**

Tile code (long): 0 = notile, 1 = tile

### **tilerank**

The number of tile dimensions (long) (optional).

### **tiledims**

Tile dimensions (long) (optional).

## Keywords

None

## Examples

We will define four fields in a grid, two 2-D fields of the same size with the same tiling, a three-dimensional field with a different tiling scheme, and a fourth with no tiling. We assume that XDim is 200 and YDim is 300.

```

tiledims[0] = 100
tiledims[1] = 200
status = EOS_GD_DEFTILE(gridID, 1, 2, tiledims)
status = EOS_GD_DEFFIELD(gridID, "Pressure", "YDim,XDim", 22)
status = EOS_GD_DEFFIELD(gridID, "Temperature", "YDim,XDim", 5)
tiledims[0] = 1
tiledims[1] = 150
tiledims[2] = 100
status = EOS_GD_DEFTILE(gridID, 1, 3, tiledims)
status = EOS_GD_DEFFIELD(gridID, "Spectra", "Bands,YDim,XDim", 5)
status = EOS_GD_DEFTILE(gridID, 0, 0)
status = EOS_GD_DEFFIELD(gridID, "Communities", "YDim,XDim", 24,
/MERGE)

```

## Version History

5.2	Introduced
-----	------------



# EOS\_GD\_DEFVRTREGION

This function subsets on a monotonic field or contiguous elements of a dimension. Whereas the EOS\_GD\_DEFBOXREGION function subsets along the XDim and YDim dimensions, this function allows the user to subset along any other dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range (case 2). In the second case, the field must be one-dimensional and the values must be monotonic (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this routine, the second option is restricted to fields with number type: 22, 24, 5, 6)

This function may be called after EOS\_GD\_DEFBOXREGION to provide both geographic and “vertical” subsetting. In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the input id to (-1).

This function may be called up to eight times with the same region ID. In this way a region can be subsetted along a number of dimensions.

The EOS\_GD\_REGIONINFO and EOS\_GD\_EXTRACTREGION functions work as before, however the field to be subsetted, (the field specified in the call to EOS\_GD\_REGIONINFO and EOS\_GD\_EXTRACTREGION) must contain the dimension used explicitly in the call to EOS\_GD\_DEFVRTREGION (case 1) or the dimension of the one-dimensional field (case 2).

## Syntax

*Result* = EOS\_GD\_DEFVRTREGION(*gridID*, *regionID*, *vertObj*, *range*)

## Return Value

Returns the grid region ID if successful and FAIL (-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### regionID

Region or period id (long) from previous subset call or -1 to start a new region.

## vertObj

Dimension or field to subset (string).

## range

Minimum and maximum range for subset (double) 2 element array.

## Keywords

None

## Examples

Suppose we have a field called Pressure of dimension Height whose values increase from 100 to 1000. If we desire all the elements with values between 500 and 800, we make the call:

```
range[0] = 500.d
range[1] = 800.d
regionID = EOS_GD_DEFVRTREGION(gridID, -1, "Pressure", range)
```

The routine determines the elements in the Height dimension which correspond to the values of the Pressure field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the Height dimension, the call would be:

```
range[0] = 2.d
range[1] = 5.d
regionID = EOS_GD_DEFVRTREGION(gridID, -1, "DIM:Height", range)
```

The "DIM:" prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field.

If a previous subset region or period was defined with id, subsetID, that we wish to refine further with the vertical subsetting defined above we make the call:

```
regionID = EOS_GD_DEFVRTREGION(gridID, subsetID, "Pressure", $
    range)
```

The return value, regionID, is set equal to subsetID. That is, the subset region is modified rather than a new one created.

In this example, any field to be subsetted must contain the Height dimension.

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DETACH

This function detaches from the grid interface. This routine should be run before exiting from the grid file for every grid opened by EOS\_GD\_CREATE or EOS\_GD\_ATTACH.

## Syntax

```
Result = EOS_GD_DETACH(gridID)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

## Keywords

None

## Examples

In this example, we detach a grid structure:

```
status = EOS_GD_DETACH(gridID)
```

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_GD\\_ATTACH](#)

# EOS\_GD\_DIMINFO

This function retrieves the size of the specified dimension.

## Syntax

```
Result = EOS_GD_DIMINFO(gridID, dimname)
```

## Return Value

Size of dimension. If FAIL(-1), could signify an improper grid id or dimension name.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### dimname

Dimension name (string)

## Keywords

None

## Examples

In this example, we retrieve information about the dimension, "Bands":

```
dimsize = EOS_GD_DIMINFO(gridID, "Bands")
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_DUPREGION

This function copies the information stored in a current region or period to a new region or period and generates a new id. It is useful when the user wishes to further subset a region (period) in multiple ways.

## Syntax

*Result* = EOS\_GD\_DUPREGION(*regionID*)

## Return Value

Returns new region or period ID or FAIL (-1) if the region cannot be duplicated.

## Arguments

### regionID

Region or period id (long) returned by EOS\_GD\_DEFBOXREGION or EOS\_GD\_DEFVRTREGION.

## Keywords

None

## Examples

In this example, we first subset a grid with EOS\_GD\_DEFBOXREGION, duplicate the region creating a new region ID, regionID2, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = EOS_GD_DEFBOXREGION(gridID, cornerlon, cornerlat)
regionID2 = EOS_GD_DUPREGION(regionID)
regionID = EOS_GD_DEFVRTREGION(gridID, regionID, "Pressure", $
    rangePres)
regionID2 = EOS_GD_DEFVRTREGION(gridID, regionID2, $
    "Temperature", rangeTemp)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_EXTRACTREGION

This function reads data into the data buffer from a subsetted region as defined by EOS\_GD\_DEFBOXREGION.

## Syntax

*Result* = EOS\_GD\_EXTRACTREGION(*gridID*, *regionID*, *fieldname*, *buffer*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### regionID

Region or period id (long) returned by EOS\_GD\_DEFBOXREGION.

### fieldname

Field to subset (string).

### buffer

A named variable that will contain the data Buffer.

## Keywords

None

## Examples

In this example, we extract data from the “Temperature” field from the region defined in EOS\_GD\_DEFBOXREGION. The size of the subsetted region for the field is given by the EOS\_GD\_REGIONINFO routine.

```
status = EOS_GD_EXTRACTREGION(EOS_GD_id, regionID, $
    "Temperature", datbuf32)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_FIELDINFO

This function retrieves information on a specific data field.

## Syntax

*Result* = EOS\_GD\_FIELDINFO(*gridID*, *fieldname*, *rank*, *dims*, *numbertype*, *dimlist*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) if the specified field does not exist.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Fieldname (string).

### rank

A named variable that will contain the pointer to rank (long) of the field.

### dims

A named variable that will contain an array (long) of the dimension sizes of the field.

### numbertype

A named variable that will contain the HDF data type (long) of the field.

### dimlist

A named variable that will contain the dimension list (string).

## Keywords

None

## Examples

In this example, we retrieve information about the Spectra data fields:

```
status = EOS_GD_FIELDINFO(gridID, "Spectra", rank, dims,$
    numbertype, dimlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_GETFILLVALUE

This function retrieves the fill value for the specified field.

## Syntax

```
Result = EOS_GD_GETFILLVALUE(gridID, fieldname, fillvalue)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Fieldname (string).

### fillvalue

A named variable that will contain the fill value.

## Keywords

None

## Examples

In this example, we get the fill value for the “Temperature” field:

```
status = EOS_GD_GETFILLVALUE(gridID, "Temperature", tempfill)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_GETPIXELS

This function returns the pixel rows and columns for specified longitude/latitude pairs. This function converts longitude/latitude pairs into (0-based) pixel rows and columns. The origin is the upper left-hand corner of the grid. This routine is the pixel subsetting equivalent of EOS\_GD\_DEFBOXREGION.

## Syntax

*Result* = EOS\_GD\_GETPIXELS(*gridID*, *nLonLat*, *lonVal*, *latVal*, *pixRow*, *pixCol*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### nLonLat

Number of longitude/latitude pairs (long).

### lonVal

Longitude values in degrees (double, 1D array).

### latVal

Latitude values in degrees (double, 1D array).

### pixRow

A named variable that will contain the pixel Rows (long array).

### pixCol

A named variable that will contain the pixel Columns (long array).

## Keywords

None

## Examples

This example converts two pairs of longitude/latitude values to rows and columns. The rows and columns of the two pairs will be returned in the rowArr and colArr arrays:

```
lonArr[0] = 134.2d
latArr[0] = -20.8d
lonArr[1] = 15.8d
latArr[1] = 84.6d
status = EOS_GD_GETPIXELS(gridID, 2, lonArr, latArr, rowArr, $
    colArr)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_GETPIXVALUES

This function reads data from a data field for the specified pixels. It is the pixel subsetting equivalent of EOS\_GD\_EXTRACTREGION. All entries along the non-geographic dimensions (i.e., NOT XDim and YDim) are returned.

## Syntax

```
Result = EOS_GD_GETPIXVALUES(gridID, nPixels, pixCol, pixRow, fieldname,  
buffer)
```

## Return Value

Returns size of data buffer if successful and FAIL(-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#)

### **nPixels**

Number of pixels (long).

### **pixCol**

Pixel Columns (long array).

### **pixRow**

Pixel Rows (long array).

### **fieldname**

Field (string) from which to extract data values.

### **buffer**

A named variable that will contain data values.

## Keywords

None

## Examples

To read values from the Spectra field with dimensions, Bands, YDim, and XDim:

```
bufsiz = EOS_GD_GETPIXVALUES(gridID, 2, rowArr, colArr, $  
    "Spectra", buffer)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_GD\_GRIDINFO

This function returns the number of rows, columns and the location, in meters, of the upper left and lower right corners of the grid image.

## Syntax

*Result* = EOS\_GD\_GRIDINFO(*gridID*, *xdimsize*, *ydimsize*, *upleft*, *lowright*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **xdimsize**

A named variable that will contain the number of columns in grid (long).

### **ydimsize**

A named variable that will contain the number of rows in grid (long).

### **upleft**

A named variable that will contain the location (double, 2 element array; in meters) of upper left corner.

### **lowright**

A named variable that will contain the location (double, 2 element array; in meters) of lower right corner.

## Keywords

None

## Examples

In this example, we retrieve information from a previously created grid with a call to `EOS_GD_ATTACH`:

```
status = EOS_GD_GRIDINFO(gridID, xdimsize, ydimsize, $
    upleft, lowrgt)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_INQATTRS

This function retrieves information about attributes defined in a grid. The attribute list is returned as a string with each attribute name separated by commas.

**Note**

See [STRSPLIT](#) to separate the attribute list.

---

## Syntax

```
Result = EOS_GD_INQATTRS( gridID, attrlist [, LENGTH=variable] )
```

## Return Value

Number of attributes found or (-1) if failure.

## Arguments

**gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

**attrlist**

A named variable that will contain the attribute list (string) with entries separated by commas.

## Keywords

**LENGTH**

Set this keyword to a named variable that will contain the length of the attribute list as a long integer.

## Examples

In this example, we retrieve information about the attributes defined in a grid structure:

```
nattr = EOS_GD_INQATTRS(gridID, attrlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_INQDIMS

This function retrieves information about dimensions defined in a grid. The dimension list is returned as a string with each dimension name separated by commas.

**Note**

See [STRSPLIT](#) to separate the dimension list.

---

## Syntax

```
Result = EOS_GD_INQDIMS(gridID, dimname, dims)
```

## Return Value

Number of dimension entries found. If FAIL(-1), could signify an improper grid id.

## Arguments

**gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

**dimname**

A named variable that will contain the dimension list (string) with entries separated by commas.

**dims**

A named variable that will contain an array (long) of the size of each dimension.

## Keywords

None

## Examples

To retrieve information about the dimensions, use the following statement:

```
ndim = EOS_GD_INQDIMS(gridID, dimname, dims)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_INQFIELDS

This function retrieves information about the data fields defined in grid. The field list is returned as a string with each data field separated by commas. The rank and numbertype arrays will have an entry for each field.

**Note**

See [STRSPLIT](#) to separate the field list.

---

## Syntax

*Result* = EOS\_GD\_INQFIELDS(*gridID*, *fieldlist*, *rank*, *numbertype*)

## Return Value

Number of data fields found. If FAIL(-1), could signify an improper grid id.

## Arguments

**gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

**fieldlist**

A named variable that will contain the listing of data fields (string) with entries separated by commas.

**rank**

A named variable that will contain the array (long) containing the rank of each data field.

**numbertype**

A named variable that will contain the array (long) containing the numbertype of each data field.

## Keywords

None

## Examples

To retrieve information about the data fields, use the following statement:

```
nfld = EOS_GD_INQFIELDS(gridID, fieldlist, rank, numbertype)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_GD\_INQGRID

This function retrieves number and names of grids defined in HDF-EOS file. The grid list is returned as a string with each grid name separated by commas.

**Note**

See [STRSPLIT](#) to separate the grid list.

---

## Syntax

```
Result = EOS_GD_INQGRID(filename, gridlist [, LENGTH=variable])
```

## Return Value

Number of grids found or (-1) if failure.

## Arguments

**filename**

HDF-EOS filename (string).

**gridlist**

A named variable that will contain the grid list (string) with entries separated by commas.

## Keywords

**LENGTH**

Set this keyword to a named variable that will contain the length of the grid list as a long integer.

## Examples

In this example, we retrieve information about the grids defined in an HDF-EOS file, HDFEOS.hdf:

```
ngrid = EOS_GD_INQGRID("HDFEOS.hdf", gridlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_INTERPOLATE

This function performs bilinear interpolation on a grid field. It assumes that the pixel data values are uniformly spaced which is strictly true only for an infinitesimally small region of the globe but is a good approximation for a sufficiently small region. The default position of the pixel value is pixel center, however if the pixel registration has been set to 1 (with the `EOS_GD_DEFPIXREG` function) then the value is located at one of the four corners specified by the `EOS_GD_DEFORIGIN` routine.

All entries along the non-geographic dimensions (i.e., NOT XDim and YDim) are interpolated and all interpolated values are returned as `FLOAT64`. The reference for the interpolation algorithm is Numerical Recipes in C (2nd ed). (Note for the current version of this routine, the number type of the field to be interpolated is restricted to 22, 24, 5, 6.)

## Syntax

```
Result = EOS_GD_INTERPOLATE(gridID, Interp, lonVal, latVal, fieldname,  
                             interpVal)
```

## Return Value

Returns size in bytes of interpolated data values if successful and `FAIL(-1)` otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#)

### **nInterp**

Number of interpolation points (long).

### **lonVal**

Longitude of interpolation points (double array).

### **latVal**

Latitude of interpolation points (double array).

**fieldname**

The field (string) from which to interpolate data values.

**interpVal**

A named variable that will contain the (double) interpolated data values.

**Keywords**

None

**Examples**

To interpolate the Spectra field at two geographic data points:

```
lonVal[0] = 134.2d
latVal[0] = -20.8d
lonVal[1] = 15.8d
latVal[1] = 84.6d
bufsiz = EOS_GD_INTERPOLATE(gridID, 2, lonVal, latVal, $
    "Spectra", interpVal)
```

**Version History**

5.2	Introduced
-----	------------

# EOS\_GD\_NENTRIES

This function returns the number of entries and descriptive string buffer size for a specified entity.

## Syntax

```
Result = EOS_GD_NENTRIES( gridID, entrycode [, LENGTH=variable] )
```

## Return Value

Number of entries or FAIL(-1) which could signify an improper grid id or entry code.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### entrycode

Entrycode (long). Allowable values are:

- 0 = Dimensions
- 4 = Datafields

## Keywords

### LENGTH

Set this keyword to a named variable that will contain the length of the string returned by the corresponding inquiry routine as a long integer.

## Examples

In this example, we determine the number of data field entries:

```
ndims = EOS_GD_NENTRIES(gridID, 4)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_OPEN

This function creates a new file or opens an existing one.

## Syntax

```
Result = EOS_GD_OPEN(filename, access [, /CREATE] [, /RDWR | , /READ])
```

## Return Value

Returns the grid file id handle (fid) if successful and FAIL(-1) otherwise.

## Arguments

### filename

Complete path and filename (string) for the file to be opened.

## Keywords

### CREATE

If file exists, delete it, then open a new file for read/write.

### RDWR

Open for read/write. If file does not exist, create it.

### READ

Open for read only. If file does not exist, error. This is the default.

## Examples

In this example, we create a new grid file named, GridFile.hdf. It returns the file handle, fid.

```
fid = EOS_GD_OPEN("GridFile.hdf", /CREATE)
```

## Version History

---

5.2	Introduced
-----	------------

---

## See Also

[EOS\\_GD\\_CLOSE](#)



# EOS\_GD\_ORIGININFO

This function retrieves the origin code.

## Syntax

*Result* = EOS\_GD\_ORIGININFO(*gridID*, *origincode*)

## Return Value

Returns 0 if successful, and -1 otherwise. A return value of -1 could signify an improper grid id or entry code.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### origincode

A named variable that will contain the origin code (long). See [EOS\\_GD\\_DEFORIGIN](#) for a list of origin codes and their meanings.

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_PIXREGINFO

This function retrieves the pixel registration code.

## Syntax

*Result* = EOS\_GD\_PIXREGINFO(*gridID*, *pixregcode*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### pixregcode

A named variable that will contain the pixel registration code (long).

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_PROJINFO

This function retrieves the GCTP projection code, zone code, spheroid code and the projection parameters of the grid. For GCTP projection information, see the *HDF-EOS User's Guide, Volume 2: Reference Guide* provided by NASA.

## Syntax

```
Result = EOS_GD_PROJINFO(gridID, projcode, zonecode, spherecode, projparm)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### projcode

A named variable that will contain the GCTP projection code (long).

### zonecode

A named variable that will contain the GCTP zone code used by UTM projection (long).

### spherecode

A named variable that will contain the GCTP spheroid code (long).

### projparm

A named variable that will contain the GCTP projection parameter array (double).

## Keywords

None

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_QUERY

The EOS\_GD\_QUERY function returns information about a specified grid.

## Syntax

*Result* = EOS\_GD\_QUERY( *Filename*, *GridName*, [*Info*]

## Return Value

This function returns an integer value of 1 if the file is an HDF file with EOS GRID extensions, and 0 otherwise.

## Arguments

### Filename

A string containing the name of the file to query.

### GridName

A string containing the name of the grid to query.

### Info

Returns an anonymous structure containing information about the specified grid. The returned structure contains the following fields:

Field	IDL Data Type	Description
ATTRIBUTES	String array	Array of attribute names
DIMENSION_NAMES	String array	Names of dimensions
DIMENSION_SIZES	Long array	Sizes of dimensions
FIELD_NAMES	String array	Names of fields
FIELD_RANKS	Long array	Ranks (dimensions) of fields
FIELD_TYPES	Long array	IDL types of fields
GCTP_PROJECTION	Long	GCTP projection code

Table 5-1: Fields of the Info Structure

Field	IDL Data Type	Description
GCTP_PROJECTION_PARM	Double array	GCTP projection parameters
GCTP_SPHEROID	Long	GCTP spheroid code
GCTP_ZONE	Long	GCTP zone code (for UTM projection)
IMAGE_LOWRIGHT	Double[2]	Location of lower right corner (meters)
IMAGE_UPLEFT	Double[2]	Location of upper left corner (meters)
IMAGE_X_DIM	Long	Number of columns in grid image
IMAGE_Y_DIM	Long	Number of rows in grid image
NUM_ATTRIBUTES	Long	Number of attributes
NUM_DIMS	Long	Number of dimensions
NUM_IDX_MAPS	Long	Number of indexed dimension mapping entries
NUM_MAPS	Long	Number of dimension mapping entries
NUM_FIELDS	Long	Number of fields
NUM_GEO_FIELDS	Long	Number of geolocation field entries
ORIGIN_CODE	Long	Origin code
PIX_REG_CODE	Long	Pixel registration code

Table 5-1: Fields of the Info Structure (Continued)

## Version History

5.3	Introduced
-----	------------

# EOS\_GD\_READATTR

This function reads attributes from the grid.

## Syntax

```
Result = EOS_GD_READATTR(gridID, attrname, datbuf)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

A named variable that will contain the attribute values.

## Keywords

None

## Examples

In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = EOS_GD_READATTR(gridID, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_READFIELD

This function reads data from the grid field. The values within start, stride, and edge arrays refer to the grid field (input) dimensions. The default values for start and stride are 0 and 1 respectively. The default value for edge is  $(\text{dim} - \text{start}) / \text{stride}$  where dim refers to the size of the dimension.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See “[Note on Array Ordering](#)” on page 579 for details.

---

## Syntax

```
Result = EOS_GD_READFIELD( gridID, fieldname, buffer [, EDGE=array]  
[, START=array] [, STRIDE=array] )
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Name of field (string) to read.

### buffer

A named variable that will contain the data read from the field.

## Keywords

### EDGE

Array (long) specifying the number of values to read along each dimension.



## START

Array (long) specifying the starting location within each dimension.

## STRIDE

Set this keyword to an array of integers specifying the number of values to step along each dimension. The default is [1, 1, ...] indicating that every value should be included. Specifying a stride of 0 is equivalent to 1.

## Examples

In this example, we read data from the 10th row (0-based) of the Temperature field:

```
start=[10,1]
edge=[1,120]
status = EOS_GD_READFIELD(gridID, "Temperature", row, $
    START = start, EDGE = edge)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_READTILE

This function reads a single tile of data from a field. If the data is to be read tile by tile, this routine is more efficient than EOS\_GD\_READFIELD. In all other cases, the later routine should be used. EOS\_GD\_READTILE does not work on non-tiled fields. Note that the coordinates are in terms of tiles, not data elements.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See “[Note on Array Ordering](#)” on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_READTILE(*gridID*, *fieldname*, *tilecoords*, *buffer*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **fieldname**

Fieldname (string).

### **tilecoords**

Array (long) of tile coordinates.

### **buffer**

A named variable that will contain the tile.

## Keywords

None

## Examples

In this example, we read one tile from the Temperature field (see EOS\_GD\_DEFTILE example) located at the second column of the first row of tiles:

```
tilecoords[0] = 0
tilecoords[1] = 1
status = EOS_GD_READTILE(gridid, "Temperature", $
    tilecoords, buffer)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_REGIONINFO

This function returns information about a subsetted region for a particular field. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields. The `upleftpt` and `lowrightpt` arrays can be used when creating a new grid from the subsetted region.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_REGIONINFO(*gridID*, *regionID*, *fieldname*, *ntype*, *rank*, *dims*, *size*, *upleftpt*, *lowrightpt*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **regionID**

Region or period id (long) returned by [EOS\\_GD\\_DEFBOXREGION](#).

### **fieldname**

Field to subset (string).

### **ntype**

A named variable that will contain the HDF data type of field (long).

**rank**

A named variable that will contain the rank of field (long).

**dims**

A named variable that will contain the dimensions of subset region (long).

**size**

A named variable that will contain the size in bytes of subset region (long).

**upleftpt**

A named variable that will contain the upper left point of subset region (double array).

**lowrightpt**

A named variable that will contain the lower right point of subset region (double array).

**Keywords**

None

**Examples**

In this example, we retrieve information about the region defined in EOS\_GD\_DEFBOXREGION for the “Temperature” field:

```
status = EOS_GD_REGIONINFO(EOS_GD_id, regionID, $
    "Temperature", ntype,$ rank, dims, size, upleft,$ lowright)
```

**Version History**

5.2	Introduced
-----	------------

# EOS\_GD\_SETFILLVALUE

This function sets the fill value for the specified field. The fill value is placed in all elements of the field which have not been explicitly defined.

## Syntax

*Result* = EOS\_GD\_SETFILLVALUE(*gridID*, *fieldname*, *fillvalue*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Fieldname (string).

### fillvalue

The fill value to be used.

## Keywords

None

## Examples

In this example, we set a fill value for the “Temperature” field:

```
tempfill = -999.0
status = EOS_GD_SETFILLVALUE(gridID, "Temperature", tempfill)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_SETTILECACHE

This function sets tile cache parameters.

## Syntax

*Result* = EOS\_GD\_SETTILECACHE(*gridID*, *fieldname*, *maxcache*, *cachecode*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Fieldname (string).

### maxcache

Maximum number of tiles (long) to cache in memory.

### cachecode

Currently must be set to 0 (long).

## Keywords

None

## Examples

In this example, we set maxcache to 10 tiles. The particular subsetting envisioned for the Spectra field (defined in the EOS\_GD\_DEFTILE example) would never cross more than 10 tiles along the field's fastest varying dimension, i.e., XDim.

```
status = EOS_GD_SETTILECACHE(gridID, "Spectra", 10, 0)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_TILEINFO

This function returns the tiling code, tiling rank, and tiling dimensions for a given field.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_TILEINFO(*gridID*, *fieldname*, *tilecode*, *tilerank*, *tiledims*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **gridID**

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### **fieldname**

Fieldname (string).

### **tilecode**

A named variable that will contain the tile code (long): 0 No Tile, 1 Tile.

### **tilerank**

A named variable that will contain the number of tile dimensions (long).

### **tiledims**

A named variable that will contain the tile dimensions (long).

## Keywords

None

## Examples

To retrieve the tiling information about the Pressure field defined in the EOS\_GD\_DEFTILE section:

```
status = EOS_GD_COMPINFO(gridID, "Pressure", tilecode, $
    tilerank, tiledims)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_WRITEATTR

This function writes/updates attributes in the grid. If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated.

## Syntax

```
Result = EOS_GD_WRITEATTR( gridID, attrname, datbuf [, COUNT=value]  
                        [, HDF_TYPE=value] )
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

Attribute values. If HDF\_TYPE is specified, the IDL variable is first converted to the type specified by the keyword before being written.

## Keywords

### COUNT

Number of values to store in attribute (long).

### HDF\_TYPE

HDF data type of attribute (long). See [“IDL and HDF Data Types”](#) on page 317 for valid values.

## Examples

In this example, we write a single precision (32 bit) floating point number with the name “ScalarFloat” and the value 3.14:

```
f32 = 3.14
status = EOS_GD_WRITEATTR(gridid, "ScalarFloat", f32)
```

We can update this value by simply calling the function again with the new value:

```
f32 = 3.14159
status = EOS_GD_WRITEATTR(gridid, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_WRITEFIELD

This function writes data to the grid field. The values within start, stride, and edge arrays refer to the grid field (output) dimensions. The input data in the data buffer is read from contiguously. The default values for start and stride are 0 and 1 respectively. The default value for edge is  $(\text{dim} - \text{start}) / \text{stride}$  where dim refers to the size of the dimension. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_GD_WRITEFIELD( gridID, fieldname, data [, EDGE=array]  
                             [, START=array] [, STRIDE=array] )
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Name of field (string) to write.

### data

Values (long) to be written to the field.

## Keywords

### EDGE

Array (long) specifying the number of values to write along each dimension.

### START

Array (long) specifying the starting location within each dimension (0-based).

### STRIDE

Set this keyword to an array of integers specifying the number of values to step along each dimension. The default is [1, 1, ...] indicating that every value should be included. Specifying a stride of 0 is equivalent to 1.

## Examples

In this example, we write data to the Temperature field:

```

; Define elements of temperature array:
temperature = indegen (200, 120)
status = EOS_GD_WRITEFIELD(gridID, "Temperature", temperature)

; Update Row 10 (0-based) in this field:
start=[0,10], edge=[2000,1]

; Define elements of newrow array:
status = EOS_GD_WRITEFIELD(gridID, "Temperature", $
    START=start, EDGE=edge, newrow)

```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_WRITEFIELDMETA

This function writes the field metadata for a grid field not defined by the Grid API.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_WRITEFIELDMETA(*gridID*, *fieldname*, *dimlist*, *numbertype*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise

## Arguments

### gridID

Grid id (long) returned by [EOS\\_GD\\_CREATE](#) or [EOS\\_GD\\_ATTACH](#).

### fieldname

Name of field (string) that metadata information is to be written.

### dimlist

Dimension list of field (long).

### numbertype

Number type of data in field (long).

## Keywords

None



## Examples

```
status = EOS_GD_writefieldmeta(gridID, "ExternField", $
    "Ydim,Xdim", 5)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_GD\_WRITETILE

This function writes a single tile of data to a field. If the data to be written to a field can be arranged tile by tile, this routine is more efficient than EOS\_GD\_WRITEFIELD. In all other cases, the EOS\_GD\_WRITEFIELD routine should be used. EOS\_GD\_WRITETILE does not work on non-tiled fields. Note that the are coordinates in terms of tiles, not data elements.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_GD\_WRITETILE(*gridID*, *fieldname*, *tilecoords*, *data*)

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### gridID

Grid id (long) returned by EOS\_GD\_CREATE or EOS\_GD\_ATTACH.

### fieldname

Fieldname (string).

### tilecoords

Array of tile coordinates (long).

### data

Data to be written to tile.

## Keywords

None

## Examples

In this example, we write one tile to the Temperature field (see the EOS\_GD\_DEFTILE example) at the second column of the first row of tiles:

```
tilecoords[0] = 0
tilecoords[1] = 1
status=EOS_GD_WRITETILE(gridID, "Temperature", tilecoords, data)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_ATTACH

This function attaches to the point using the pointname parameter as the identifier.

## Syntax

*Result* = EOS\_PT\_ATTACH(*fid*, *pointname*)

## Return Value

Returns the point handle (pointID) if successful and FAIL (-1) otherwise. Typical reasons for failure are an improper point file id or point name.

## Arguments

### fid

Point file id (long) returned by EOS\_PT\_OPEN.

### pointname

Name of point (string) to be attached.

## Keywords

None

## Examples

In this example, we attach to the previously created point, "ExamplePoint", within the HDF file, PointFile.hdf, referred to by the handle, fid:

```
pointID = EOS_PT_ATTACH(fid, "ExamplePoint")
```

The point can then be referenced by subsequent routines using the handle, pointID.

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_PT\\_DETACH](#)

# EOS\_PT\_ATTRINFO

This function returns number type and number of elements (count) of a point attribute.

## Syntax

```
Result = EOS_PT_ATTRINFO(pointID, attrname, numbertype, count)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### attrname

Attribute name (string).

### numbertype

A named variable that will contain the HDF type of the attribute value (long).

### count

A named variable that will contain the number of total bytes in attribute (long).

## Keywords

None

## Examples

In this example, we return information about the ScalarFloat attribute:

```
status = EOS_PT_ATTRINFO(pointID, "ScalarFloat", nt, count)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_BCKLINKINFO

This function returns the linkfield to the previous level.

## Syntax

```
Result = EOS_PT_BCKLINKINFO(pointID, level, linkfield)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Point level (0-based long).

### linkfield

A named variable that will contain the link field (string).

## Keywords

None

## Examples

In this example, we return the linkfield connecting the Observations level to the previous Desc-Loc level. (These levels are defined in the EOS\_PT\_DEFLEVEL routine.)

```
status = EOS_PT_BCKLINKINFO(pointID2, 1, linkfield)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_CLOSE

This function closes the HDF point file.

## Syntax

```
Result = EOS_PT_CLOSE(fid)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

**fid**

Point file id (long) returned by EOS\_PT\_OPEN.

## Keywords

None

## Examples

```
status = EOS_PT_CLOSE(fid)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_CREATE

This function creates a new point structure. The point is created as a Vgroup within the HDF file with the name *pointname* and class POINT.

## Syntax

```
Result = EOS_PT_CREATE(fid, pointname)
```

## Return Value

Returns the point handle (pointID) if successful and FAIL (-1) otherwise.

## Arguments

### fid

Point file id (long) returned by EOS\_PT\_OPEN.

### pointname

Name of point (string) to be created.

## Keywords

None

## Examples

In this example, we create a new point structure, ExamplePoint, in the previously created file, PointFile.hdf:

```
pointID = EOS_PT_CREATE(fid, "ExamplePoint")
```

The point structure is then referenced by subsequent routines using the handle, pointID.

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_DEFBOXREGION

This function defines an area of interest for a point. It returns a point region ID which is used by the EOS\_PT\_EXTRACTREGION routine to read the fields from a level for those records within the area of interest. The point structure must have a level with both a Longitude and Latitude (or Colatitude) field defined.

## Syntax

*Result* = EOS\_PT\_DEFBOXREGION(*pointID*, *cornerlon*, *cornerlat*)

## Return Value

Returns the point regionID if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### cornerlon

Longitude (double) in decimal degrees of box corners (2 element, 1-D array).

### cornerlat

Latitude (double) in decimal degrees of box corners (2 element, 1-D array).

## Keywords

None

## Examples

In this example, we define an area of interest with (opposite) corners at -145 degrees longitude, -15 degrees latitude and -135 degrees longitude, -8 degrees latitude:

```
cornerlon = dblarr (2)
cornerlat = dblarr (2)
cornerlon[0] = -145.
cornerlat[0] = -15.
cornerlon[1] = -135.
```

```
cornerlat[1] = -8.  
regionID = EOS_PT_DEFBOXREGION(pointID, cornerlon, cornerlat)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_DEFLEVEL

This function defines a level within the point. A simple point consists of a single level. A point where there is common data for a number of records can be more efficiently stored with multiple levels. The order in which the levels are defined determines the (0-based) level index.

## Syntax

*Result* = EOS\_PT\_DEFLEVEL(*pointID*, *levelname*, *fieldlist*, *fieldtype*, *fieldorder*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### levelname

Name of level (string) to be defined.

### fieldlist

List of fields (string) in level.

### fieldtype

Array (long) containing HDF data type of each field within level.

### fieldorder

Array (long) containing order of each field within level.

### Note

---

An order of 0 is considered the same as an order of 1.

---

## Keywords

None

## Examples

### Example 1 — Simple Point:

In this example, we define a simple single level point, with levelname, Sensor. The levelname should not contain any slashes (“/”). It consists of six fields, ID, Time, Longitude, Latitude, Temperature, and Mode defined in the field list. The fieldtype and fieldorder parameters are arrays consisting of the HDF number type codes and field orders, respectively. The Temperature is an array field of dimension 4 and the Mode field a character string of size 4. All other fields are scalars. Note that the order for numerical scalar variables can be either 0 or 1.

```
fieldtype = [22, 22, 5, 5, 5, 4]
fieldorder = [0,0,0,0,4,4]
fldlist = "ID,Time,Longitude,Latitude,Temperature,Mode"
status = EOS_PT_DEFLEVEL(pointID, "Sensor", fldlist, fieldtype,$
fieldorder)
```

### Example 2 — Multi-Level Point:

In this example, we define a two-level point that describes data from a network of fixed buoys. The first level contains information about each buoy and includes the name (label) of the buoy, its (fixed) longitude and latitude, its deployment date, and an ID that is used to *link* it to the following level. (The link field is defined in the EOS\_PT\_DEFLINKAGE routine described later.) The entries within the ID field must be unique. The second level contains the actual measurements from the buoys (rainfall and temperature values) plus the observation time and the ID which relates a given measurement to a particular buoy entry in the previous level. There can be many records in this level with the same ID since there can be multiple measurements from a single buoy. It is advantageous, although not mandatory, to store all records for a particular buoy (ID) contiguously.

Level 0

```
fieldtype0 = [4, 6, 6, 5, 4]
fieldorder0 = [8,0,0,0,1]
fldlist0 = "Label,Longitude,Latitude,DeployDate,ID"
status = EOS_PT_deflevel(pointID2, "Desc-Loc", $
fldlist0, fieldtype0, fieldorder0)
```

### Level 1

```
fieldtype1 = [6, 5, 5, 4]
fieldorder1 = [0,0,0,1]
fldlist1 = "Time,Rainfall,Temperature,ID"
status = EOS_PT_DEFLEVEL(pointID2, "Observations", $
    fldlist1, fieldtype1, fieldorder1)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_PT\_DEFLINKAGE

This function defines the linkfield between two levels. This field must be defined in both levels.

## Syntax

*Result* = EOS\_PT\_DEFLINKAGE(*pointID*, *parent*, *child*, *linkfield*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### parent

Name (string) of parent level.

### child

Name (string) of child level.

### linkfield

Name (string) of common linkfield.

## Keywords

None

## Examples

In this example, we define the ID field as the link between the two levels defined previously in the EOS\_PT\_DEFLEVEL function:

```
status = EOS_PT_DEFLINKAGE(pointID2, "Desc-Loc", $
    "Observations", "ID")
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_DEFTIMEPERIOD

This function defines a time period for a point. It returns a point period ID which is used by the EOS\_PT\_EXTRACTPERIOD function to read the fields from a level for those records within the time period. The point structure must have a level with the Time field defined.

## Syntax

*Result* = EOS\_PT\_DEFTIMEPERIOD(*pointID*, *starttime*, *stoptime*)

## Return Value

Returns the point periodID if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### starttime

Start time (double) of period.

### stoptime

Stop time (double) of period.

## Keywords

None

## Examples

In this example, we define a time period with a start time of 35208757.6 and a stop time of 35984639.2:

```
starttime = 35208757.6d
stoptime = 35984639.2d
periodID = EOS_PT_DEFTIMEPERIOD(pointID, starttime, stoptime)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_DEFVRTREGION

This function allows the user to select those records within a point whose field values are within a given range. (For the current version of this routine, the field must have one of the following HDF data types: 22, 24, 5, 6) This function may be called after EOS\_PT\_DEFBOXREGION or EOS\_PT\_DEFTIMEPERIOD to provide both geographic or time and vertical subsetting. In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called stand-alone by setting the input id to (-1).

This function may be called up to eight times with the same region ID. In this way a region can be subsetted along a number of dimensions.

The EOS\_PT\_REGIONINFO and EOS\_PT\_EXTRACTREGION functions work as before, however, because there is no mapping performed between geolocation dimensions and data dimensions for the field to be subsetted, (the field specified in the call to EOS\_PT\_REGIONINFO and EOS\_PT\_EXTRACTREGION) must contain the dimension used explicitly in the call to EOS\_PT\_DEFVRTREGION (case 1) or the dimension of the one-dimensional field (case 2).

## Syntax

*Result* = EOS\_PT\_DEFVRTREGION(*pointID*, *regionID*, *vertObj*, *range*)

## Return Value

Returns the point region ID if successful and FAIL (-1) otherwise.

## Arguments

### **pointID**

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### **regionID**

Region or period id (long) returned from a previous subset call.

### **vertObj**

String name of a dimension or field by which to subset.

## range

Minimum and maximum range for the subset (double, 2 element, 1-D array).

## Keywords

None

## Examples

Suppose we wish to find those records within a point whose Rainfall values fall between 1 and 2. We wish to search all the records within the point, so we set the input region ID to (-1):

```

range = [1.,2.]
regionID = EOS_PT_DEFVRTREGION(pointID, -1, "Rainfall", range)

; Now we subset further using the Temperature field:
range = [22.,24.]
regionID = EOS_PT_DEFVRTREGION(pointID, regionID, $
    "Temperature", range)

```

The subsetted region referred to by regionID will now contain those records whose Rainfall field are between 1 and 2 and whose Temperature field are between 22 and 24.

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_DETACH

This function detaches from a point data set. This function should be run before exiting from the point file for every point opened by EOS\_PT\_CREATE or EOS\_PT\_ATTACH.

## Syntax

*Result* = EOS\_PT\_DETACH(*pointID*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#)

## Keywords

None

## Examples

```
status = EOS_PT_DETACH(pointID)
```

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_PT\\_ATTACH](#)

# EOS\_PT\_EXTRACTPERIOD

This function reads data from the designated level fields into the data buffer from the subsetted time period.

## Syntax

*Result* = EOS\_PT\_EXTRACTPERIOD(*pointID*, *periodID*, *level*, *fieldlist*, *buffer*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long).

### periodID

Period id (long) returned by EOS\_PT\_DEFTIMEPERIOD.

### level

Point level (0-based long).

### fieldlist

List of fields (string) to extract.

### buffer

A named variable that will contain the data buffer. This buffer is in packed format. Use HDF\_UNPACKDATA to convert it into variables.

## Keywords

None



## Examples

In this example, we read data within the subsetted time period defined by EOS\_PT\_DEFTIMEPERIOD from the Time field:

```
periodID = EOS_PT_DEFTIMEPERIOD(pointID, 35208757.6d, $
    35984639.2d)
IF (periodID NE -1) THEN BEGIN
    status = EOS_PT_EXTRACTPERIOD(pointID, periodID, 1, $
        "Time", buffer)
    HDF_UNPACKDATA, buffer, dataTime, HDF_TYPE=[6]
ENDIF
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_EXTRACTREGION

This function reads data from the designated level fields into the data buffer from the subsetted area of interest.

## Syntax

*Result* = EOS\_PT\_EXTRACTREGION(*pointID*, *regionID*, *level*, *fieldlist*, *buffer*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **pointID**

Point id (long).

### **regionID**

Period id (long) returned by EOS\_PT\_DEFBOXREGION.

### **level**

Point level (0-based long).

### **fieldlist**

List of fields (string) to extract.

### **buffer**

A named variable that will contain the data buffer.

## Keywords

None

## Examples

In this example, we read data within the subsetted area of interest defined by EOS\_PT\_DEFBOXREGION from the Longitude and Latitude fields:

```
regionID = EOS_PT_DEFBOXREGION(pointID, [-145.,-135.], [-15.,-8.])
IF (regionID NE -1) THEN BEGIN
    status = EOS_PT_EXTRACTREGION(pointID, regionID, 0, $
        "Longitude,Latitude", buffer)
    HDF_UNPACKDATA, buffer, dataLong,dataLat,HDF_TYPE=[6,6]
ENDIF
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_FWDLINKINFO

This function returns the linkfield to the given level.

## Syntax

```
Result = EOS_PT_FWDLINKINFO(pointID, level, linkfield)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Point level (0-based long).

### linkfield

A named variable that will contain the link field (string).

## Keywords

None

## Examples

In this example, we return the linkfield connecting the Desc-Loc level to the following Observations level. (These levels are defined in the `EOS_PT_DEFLEVEL` function.):

```
status = EOS_PT_FWDLINKINFO(pointID2, 1, linkfield)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_GETLEVELNAME

This function returns the name of a level given the level number (0-based).

## Syntax

```
Result = EOS_PT_GETLEVELNAME( pointID, level, levelname  
[, LENGTH=variable] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Point level (0-based long).

### levelname

A named variable that will contain the level name (string).

## Keywords

### LENGTH

Set this keyword to a named variable that will contain the string length of the level name.

## Examples

In this example, we return the level name of the 0th level of the second point defined in the EOS\_PT\_DEFLEVEL section:

```
status = EOS_PT_GETLEVELNAME(pointID2, 0, levelname)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_GETRECNUMS

This function returns the record numbers in one level that are connected to a given set of records in a different level. The two levels need not be adjacent. The records in one level are related to those in another through the link field. These in turn are related to the next. In this way, each record in any level is related to others in all the levels of the point structure.

## Syntax

*Result* = EOS\_PT\_GETRECNUMS( *pointID*, *inlevel*, *outlevel*, *inNrec*, *inRecs*,  
*outNrec*, *outRecs*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### inlevel

Level number (long) of input records (0-based).

### outlevel

Level number (long) of output records (0-based).

### inNrec

Number of records (long) in the inRecs array.

### inRecs

Array (long) containing the input record numbers.

### outNrec

A named variable that will contain the number of records (long) in the outRecs array.



## outRecs

A named variable that will contain the array (long) of output record numbers.

## Keywords

None

## Examples

In this example, we get the record numbers in the second level that are related to the first record in the first level:

```
nrec = 1
recs[0] = 0
inLevel = 0
outLevel = 1
status = EOS_PT_GETRECNUMS(pointID2, inLevel, outLevel, $
    nrec, recs, outNrec, outRecs)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_INQATTRS

This function retrieves information about the attributes defined in a point structure. The attribute list is returned as a string with each attribute name separated by a comma.

---

**Note**

See [STRSPLIT](#) to separate the attribute list.

---

## Syntax

```
Result = EOS_PT_INQATTRS( pointID, attrlist [, LENGTH=variable] )
```

## Return Value

Number of attributes found or (-1) if failure.

## Arguments

### pointID

Point id (long).

### attrlist

A named variable that will contain the attribute list (string) entries separated by commas.

## Keywords

### LENGTH

Set this keyword to a named variable that will contain the length of the attribute list, as a long integer.

## Examples

```
nattr = EOS_PT_INQATTRS(pointID, attrlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_INQPOINT

This function retrieves the number and names of points defined in an HDF-EOS file. The point list is returned as a string with each point name separated by a comma.

---

**Note**

See [STRSPLIT](#) to separate the attribute list.

---

## Syntax

*Result* = EOS\_PT\_INQPOINT(*filename*, *pointlist* [, [LENGTH=variable](#)])

## Return Value

Returns number of points found or (-1) if failure.

## Arguments

### filename

HDF-EOS filename (string).

### pointlist

A named variable that will contain the point list (string) entries separated by commas.

## Keywords

### LENGTH

Set this keyword to a named variable that will contain the length of the point list as a long integer.

## Examples

In this example, we retrieve information about the points defined in an HDF-EOS file, HDFEOS.hdf:

```
npoint = EOS_PT_INQPOINT("HDFEOS.hdf", pointlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_LEVELINDX

This function returns the level index for a given level specified by name.

## Syntax

```
Result = EOS_PT_LEVELINDX( pointID, levelname)
```

## Return Value

Returns the level index if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### levelname

Level Name (string).

## Keywords

None

## Examples

In this example, we return the level index of the Observations level in the multilevel point structure defined in EOS\_PT\_DEFLEVEL:

```
levindx = EOS_PT_LEVELINDEX(pointID2, "Observations")
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_LEVELINFO

This function returns information about the fields in a given level. Typical reasons for failure are an improper point id or level number.

## Syntax

*Result* = EOS\_PT\_LEVELINFO(*pointID*, *level*, *fieldlist*, *fldtype*, *fldorder*)

## Return Value

Returns number of fields if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Point level (0-based long).

### fieldlist

A named variable that will contain field names (string) in level.

### fldtype

A named variable that will contain the number HDF data type (long) of each field.

### fldorder

A named variable that will contain the order (long) of each field.

## Keywords

None

## Examples

In this example, we return information about the Desc-Loc (1st) level defined previously:

```
nflds = EOS_PT_LEVELINFO(pointID2, 0, fldlist, fldtype, fldorder)
```

The last variable is useful only when information on an entire point is requested.

## Version History

5.2	Introduced
-----	------------



# EOS\_PT\_NFIELDS

This function returns the number of fields in a level.

## Syntax

```
Result = EOS_PT_NFIELDS( pointID, level [, LENGTH=bytes] )
```

## Return Value

Returns number of fields if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Level number (0-based long).

## Keywords

### LENGTH

Size (long) in bytes of fieldlist for level.

## Examples

In this example, we retrieve the number of fields in the 2nd point defined previously:

```
nflds=EOS_PT_NFIELDS(pointID2,0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_NLEVELS

This function returns the number of levels in a point.

## Syntax

*Result* = EOS\_PT\_NLEVELS(*pointID*)

## Return Value

Returns number of levels if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

## Keywords

None

## Examples

In this example, we retrieve the number of levels in the 2nd point defined previously:

```
nlevels = EOS_PT_NLEVELS(pointID2)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_NRECS

This function returns the number of records in a given level.

## Syntax

```
Result = EOS_PT_NRECS(pointID, level)
```

## Return Value

Returns number of records in a given level if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Level number (0-based long).

## Keywords

None

## Examples

In this example, we retrieve the number of records in the first level of the 2nd point defined previously:

```
nrecs = EOS_PT_NRECS(pointID2, 0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_OPEN

This function creates a new file or opens an existing one.

## Syntax

```
Result = EOS_PT_OPEN(fieldname [, /CREATE] [, /RDWR | , /READ] )
```

## Return Value

Returns the point file id handle (fid) if successful and FAIL (-1) otherwise.

## Arguments

### fieldname

Complete path and filename (string) for the file to be opened.

## Keywords

### CREATE

If file exists, delete it, then open a new file for read/write.

### RDWR

Open for read/write. If file does not exist, create it.

### READ

Open for read only. If file does not exist then error.

## Examples

In this example, we create a new point file named, PointFile.hdf. It returns the file handle, fid.

```
fid = EOS_PT_OPEN("PointFile.hdf", /CREATE)
```

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_PT\\_CLOSE](#)

# EOS\_PT\_PERIODINFO

This function returns information about a subsetted time period for a particular fieldlist.

## Syntax

*Result* = EOS\_PT\_PERIODINFO(*pointID*, *periodID*, *level*, *fieldlist*, *size*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long).

### periodID

Period id (long) returned by EOS\_PT\_DEFTIMEPERIOD.

### level

Point level (0-based long).

### fieldlist

List of fields (string) to extract.

### size

A named variable that will contain the size in bytes (long) of subset period.

## Keywords

None

## Examples

In this example, we get the size of the subsetted time period defined in EOS\_PT\_DEFTIMEPERIOD for the Time field:

```
status = EOS_PT_PERIODINTO(pointID, periodID, 0, "Time", size)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_PERIODRECS

This function returns the record numbers within a subsetted time period for a particular level.

## Syntax

*Result* = EOS\_PT\_PERIODRECS(*pointID*, *periodID*, *level*, *nrec*, *recs*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **pointID**

Point id (long).

### **periodID**

Period id (long) returned by EOS\_PT\_DEFTIMEPERIOD.

### **level**

Point level (0-based long).

### **nrec**

A named variable that will contain the number of records (long) within time period in level.

### **recs**

A named variable that will contain the record numbers (long) of subsetted records in level.

## Keywords

None



## Examples

In this example, we get the number of records and record numbers within the subsetting area of interest defined in EOS\_PT\_DEFTIMEPERIOD for the 0th level:

```
status = EOS_PT_PERIODRECS(pointID, periodID, 0, nrec, recs)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_QUERY

The EOS\_PT\_QUERY function returns information about a specified point.

## Syntax

*Result* = EOS\_PT\_QUERY( *Filename*, *PointName*, [*Info*] )

## Return Value

This function returns an integer value of 1 if the file is an HDF file with EOS POINT extensions, and 0 otherwise.

## Arguments

### Filename

A string containing the name of the file to query.

### PointName

A string containing the name of the point to query.

### Info

Returns an anonymous structure containing information about the specified point. The returned structure contains the following fields:

Field	IDL Data Type	Description
ATTRIBUTES	String array	Array of attribute names
NUM_ATTRIBUTES	Long	Number of attributes
NUM_LEVELS	Long	Number of levels

*Table 5-2: Fields of the Info Structure*

## Keywords

None

## Version History

5.3	Introduced
-----	------------

# EOS\_PT\_READATTR

This function reads attributes.

## Syntax

```
Result = EOS_PT_READATTR(pointID, attrname, datbuf)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

A named variable that will contain the buffer allocated to hold attribute values.

## Keywords

None

## Examples

In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = EOS_PT_READATTR(pointID, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_READLEVEL

This function reads data from the specified fields and records of a single level in a point.

## Syntax

*Result* = EOS\_PT\_READLEVEL(*pointID*, *level*, *fieldlist*, *nrec*, *recs*, *buffer*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Level to read (0-based long).

### fieldlist

List of fields (string) to read.

### nrec

Number of records (long) to read.

### recs

Record number of records to read (0-based long).

### buffer

A named variable that will contain the buffer to store data. This buffer is in packed format. Use [HDF\\_UNPACKDATA](#) to convert it into IDL variables.

## Keywords

None

## Examples

In this example, we read records 0, 2, and 3 from the Temperature and Mode fields in the first level of the point referred to by point ID, pointID. Temperature is a 32-bit float field and Mode is a 4 character field (HDF types 5 and 4 respectively):

```

recs = [ 0, 2, 3 ]
status = EOS_PT_READLEVEL( pointID, 0, "Temperature,Mode", $
    3, recs, buffer)
IF (status EQ 0) THEN BEGIN
    HDF_UNPACKDATA, buffer, dataTemperature, dataMode, $
        HDF_TYPE=[5,4], HDF_ORDER = [4,4]
ENDIF

```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_REGIONINFO

This function returns information about a subsetted area of interest for a particular fieldlist.

## Syntax

*Result* = EOS\_PT\_REGIONINFO(*pointID*, *regionID*, *level*, *fieldlist*, *size*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **pointID**

Point id (long).

### **regionID**

Region id (long) returned by EOS\_PT\_DEFBOXREGION.

### **level**

Point level (0-based long).

### **fieldlist**

List of fields (string) to extract.

### **size**

A named variable that will contain the size in bytes (long) of subset period.

## Keywords

None

## Examples

In this example, we get the size of the subsetted area of interest defined in EOS\_PT\_DEFBOXREGION from the Longitude and Latitude fields:

```
status = EOS_PT_REGIONINFO(pointID, regionID, 0, "Longitude, $  
Latitude", size)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_PT\_REGIONRECS

This function returns the record numbers within a subsetted geographic region for a particular level.

## Syntax

*Result* = EOS\_PT\_REGIONRECS(*pointID*, *regionID*, *level*, *nrec*, *recs*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **pointID**

Point id (long).

### **regionID**

Region id (long) returned by EOS\_PT\_DEFBOXREGION.

### **level**

Point level (0-based long).

### **nrec**

A named variable that will contain the number of records (long) within geographic region in level.

### **recs**

A named variable that will contain the record numbers (long) of subsetted records in level.

## Keywords

None

## Examples

In this example, we get the number of records and record numbers within the subsetting area of interest defined in EOS\_PT\_DEFBOXREGION for the 0th level:

```
status = EOS_PT_REGIONRECS(pointID, regionID, 0, nrec, recs)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_SIZEOF

This function returns information about specified fields in a point regardless of level.

## Syntax

```
Result = EOS_PT_SIZEOF(pointID, fieldlist, fldlevel)
```

## Return Value

Returns size in bytes of specified fields and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### fieldlist

Field names (string).

### fldlevel

A named variable that will contain the level number (long) of each field.

## Keywords

None

## Examples

In this example, we return the size in bytes of the Label and Rainfall fields in the 2nd point defined in the EOS\_PT\_DEFLEVEL function:

```
size = EOS_PT_SIZEOF(pointID2, "Label,Rainfall", fldlevel)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_UPDATELEVEL

This function updates the specified fields and records of a single level.

## Syntax

*Result* = EOS\_PT\_UPDATELEVEL(*pointID*, *level*, *field*, *list*, *nrec*, *recs*, *data*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Level to update (0-based long).

### fieldlist

List of fields (string) to update.

### nrec

Number of records (long) to update.

### recs

Record number of records to update (0-based long).

### data

Values to be written to the fields. Data values are not converted to the internal HDF type automatically. Use HDF\_PACKDATA if conversion is necessary or the data fields specify multiple types.

## Keywords

None

## Examples

In this example, we update records 0, 2, and 3 in the Temperature and Mode fields in the second level in the point referred to by the point ID pointID. Temperature is a 4 value 32-bit float field and Mode is a 4 character field (HDF types 5 and 4 respectively):

```
recs = [ 0, 2, 3]
dataTemperature = [ [20, 21, 22, 23], [30, 31, 32, 33], $
  [40, 41, 42, 43]]]
dataMode = ['P', 'I', 'A']
buffer = HDF_PACKDATA(dataTemperature, dataMode, $
  HDF_TYPE = [5, 4], HDF_ORDER = [4, 4])
status = EOS_PT_UPDATELEVEL( pointID, 1, "Temperature,Mode", $
  3, recs, buffer)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_WRITEATTR

This function writes/updates an attribute in a point. If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated.

## Syntax

```
Result = EOS_PT_WRITEATTR( pointID, attrname, datbuf [, COUNT=value]  
[, HDF_TYPE=value] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

Attribute values.

## Keywords

### COUNT

Number of values (long) to store in attribute.

### HDF\_TYPE

Number type (long) of attribute. See “[IDL and HDF Data Types](#)” on page 317 for valid values.

## Examples

In this example, we write a single precision (32 bit) floating point number with the name “ScalarFloat” and the value 3.14:

```
f32 = 3.14f
status = EOS_PT_WRITEATTR(pointid, "ScalarFloat", f32)
```

We can update this value by simply calling the function again with the new value:

```
f32 = 3.14159
status = EOS_PT_WRITEATTR(pointid, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_PT\_WRITELEVEL

This function writes (appends) full records to a level. The data in each record must be packed. Refer to the section on Vdatas in the HDF documentation. The input data buffer must be sufficient to fill the number of records designated.

## Syntax

*Result* = EOS\_PT\_WRITELEVEL(*pointID*, *level*, *nrec*, *data*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### pointID

Point id (long) returned by [EOS\\_PT\\_CREATE](#) or [EOS\\_PT\\_ATTACH](#).

### level

Level to write (0-based long).

### nrec

Number of records (long) to write.

### data

Values to be written to the field. Data values are not converted to the internal HDF type automatically. Use `HDF_PACKDATA` if conversion is necessary or the data fields specify multiple types.

## Examples

In this example, we write 5 records to the first level in the point referred to by the point id, `pointID1`:

```
status = EOS_PT_WRITELEVEL(pointID1, 0, 5, datbuf)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_QUERY

The EOS\_QUERY function returns information about the makeup of an HDF-EOS file.

## Syntax

*Result* = EOS\_QUERY( *Filename*, [*Info*] )

## Return Value

This function returns integer value of 1 if the file is an HDF file with EOS extensions, and 0 otherwise.

## Arguments

### Filename

A scalar string containing the name of the file to query.

### Info

Returns an anonymous structure containing information about the contents of the file. The returned structure contains the following fields:

Field	IDL Data Type	Description
GRID_NAMES	String array	Names of grids
NUM_GRIDS	Long	Number of grids in file
NUM_POINTS	Long	Number of points in file
NUM_SWATHS	Long	Number of swaths in file
POINT_NAMES	String array	Names of points
SWATH_NAMES	String array	Names of swaths

*Table 5-3: Fields of the Info Structure*

## Version History

5.3	Introduced
-----	------------

# EOS\_SW\_ATTACH

This function attaches to the swath using the swathname parameter as the identifier.

## Syntax

```
Result = EOS_SW_ATTACH(fid, swathname)
```

## Return Value

Returns the swath handle (swathID) if successful and FAIL (-1) otherwise.

## Arguments

### fid

Swath file id (long) returned by EOS\_SW\_OPEN.

### swathname

Name of swath (string) to be attached.

## Keywords

None

## Examples

In this example, we attach to the previously created swath, “ExampleSwath”, within the HDF file, SwathFile.hdf, referred to by the handle, fid:

```
swathID = EOS_SW_ATTACH(fid, "ExampleSwath")
```

The swath can then be referenced by subsequent routines using the handle, swathID.

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_SW\\_DETACH](#)

# EOS\_SW\_ATTRINFO

This function returns the number type and number of elements (count) of a swath attribute.

## Syntax

*Result* = EOS\_SW\_ATTRINFO(*swathID*, *attrname*, *numbertype*, *count*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### attrname

Attribute name (string).

### numbertype

A named variable that will contain the HDF data type (long) of attribute.

### count

A named variable that will contain the number of total bytes (long) in attribute.

## Keywords

None

## Examples

In this example, we return information about the ScalarFloat attribute:

```
status = EOS_SW_ATTRINFO(pointID, "ScalarFloat", nt, count)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_CLOSE

This function closes the HDF swath file.

## Syntax

*Result* = EOS\_SW\_CLOSE(*fid*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

**fid**

Swath file id (long) returned by EOS\_SW\_OPEN.

## Keywords

None

## Examples

```
status = EOS_SW_CLOSE(fid)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_SW\_COMPINFO

This function returns the compression code and compression parameters for a given field.

## Syntax

```
Result = EOS_SW_COMPINFO(swathID, fieldname, compcode, compparm)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **fieldname**

Fieldname (string).

### **compcode**

A named variable that will contain the HDF compression code (long).

### **compparm**

A named variable that will contain the compression parameters (long).

## Keywords

None

## Examples

To retrieve the compression information about the Opacity field defined in the EOS\_SW\_DEFCOMP section:

```
status = EOS_SW_COMPINFO(swathID, "Opacity", compcode, compparm)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_CREATE

This function creates a swath within the file. The swath is created as a Vgroup within the HDF file with the name *swathname* and class EOS\_SWATH.

## Syntax

```
Result = EOS_SW_CREATE(fid, swathname)
```

## Return Value

Returns the swath handle (swathID) if successful and FAIL (-1) otherwise.

## Arguments

### fid

Swath file id (long) returned by EOS\_SW\_OPEN.

### swathname

Name of swath (string) to be created.

## Keywords

None

## Examples

In this example, we create a new swath structure, “ExampleSwath”, in the previously created file, SwathFile.hdf.

```
swathID = EOS_SW_CREATE(fid, "ExampleSwath")
```

The swath structure is referenced by subsequent routines using the handle, swathID.

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFBOXREGION

This function defines a longitude-latitude box region for a swath. It returns a swath region ID that is used by the EOS\_SW\_EXTRACTREGION function to read all the entries of a data field within the region. A cross track is within a region if its midpoint is within the longitude-latitude box (0), or either of its endpoints is within the longitude-latitude box (1), or any point of the cross track is within the longitude-latitude box (2), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the region even though a particular element of the cross track might be outside the region. The swath structure must have both Longitude and Latitude (or Colatitude) fields defined.

## Syntax

*Result* = EOS\_SW\_DEFBOXREGION(*swathID*, *cornerlon*, *cornerlat*, *mode*)

## Return Value

Returns the swath region ID if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### cornerlon

Longitude in decimal degrees (double) of box corners (double, 2 element, 1-D array).

### cornerlat

Latitude in decimal degrees (double) of box corners (double, 2 element, 1-D array).

### mode

Cross Track inclusion mode (long). Allowable values are:

- 0 = Midpoint
- 1 = Endpoint
- 2 = Anypoint

## Keywords

None

## Examples

In this example, we define a region bounded by 3 degrees longitude, 5 degrees latitude and 7 degrees longitude, 12 degrees latitude. We will consider a cross track to be within the region if its midpoint is within the region:

```
cornerlon[0] = 3.d  
cornerlat[0] = 5.d  
cornerlon[1] = 7.d  
cornerlat[1] = 12.d  
regionID = EOS_SW_DEFBOXREGION(swathID, cornerlon, cornerlat, 0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFCOMP

This function sets the HDF field compression for subsequent swath field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported are: run length encoding (1), skipping Huffman (3), deflate (gzip) (4) and no compression (0, the default). Compressed fields are written using the standard EOS\_SW\_WRITEFIELD function, however, the entire field must be written in a single call. Any portion of a compressed field can then be accessed with the EOS\_SW\_READFIELD function. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of the compression schemes and parameters.

## Syntax

```
Result = EOS_SW_DEFCOMP( swathID, compcode, [, compparm] )
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### compcode

HDF compression code (long). Allowable values are:

- 0 = None
- 1 = Run Length Encoding (RLE)
- 3 = Skipping Huffman
- 4 = Deflate (gzip)

### compparm

Deflate compression (*compcode* 4) requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression.

## Keywords

None

## Examples

Suppose we wish to compress the Pressure using run length encoding, the Opacity field using deflate compression, the Spectra field with skipping Huffman compression, and use no compression for the Temperature field:

```
status = EOS_SW_DEFCOMP(swathID, 1)
status = EOS_SW_DEFDATAFIELD(swathID, "Pressure", $
    "Track,Xtrack", 5)
compparm[0] = 5
status = EOS_SW_DEFCOMP(swathID, 4, compparm)
status = EOS_SW_DEFDATAFIELD(swathID, "Opacity", $
    "Track,Xtrack", 5)
status = EOS_SW_DEFCOMP(swathID, 3)
status = EOS_SW_DEFDATAFIELD(swathID, "Spectra", $
    "Bands,Track,Xtrack", 5)
status = EOS_SW_DEFCOMP(swathID, 0)
status = EOS_SW_DEFDATAFIELD(swathID, $
    "Temperature", "Track,Xtrack", 5, /MERGE)
```

Note that the MERGE keyword will be ignored in the Temperature field definition.

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFDATAFIELD

This function defines data fields to be stored in the swath. The dimensions are entered as a string consisting of data dimensions separated by commas. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, `numbertype`. If the merge keyword is not set, the API will not attempt to merge it with other fields. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF-EOS field directly using HDF routines. To assure that the fields defined by `EOS_SW_DEFDATAFIELD` are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_SW_DEFDATAFIELD( swathID, fieldname, dimlist, numbertype  
[, /MERGE] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field (string) to be defined.

### dimlist

The list of data dimensions (string) defining the field.



## numbertype

The HDF data type (long) of the data stored in the field.

## Keywords

### MERGE

If set, automatic merging will occur. By default, fields are not merged.

## Examples

In this example, we define a three dimensional data field named Spectra with dimensions Bands, DataTrack, and DataXtrack:

```
status = EOS_SW_DEFDATAFIELD(swathID, "Spectra", $  
    "Bands,DataTrack,DataXtrack", 5, /MERGE)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFDIM

This function defines dimensions that are used by the field definition functions (described subsequently) to establish the size of the field.

## Syntax

```
Result = EOS_SW_DEFDIM(swathID, fieldname, dim)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **swathID**

Swath id (long).

### **fieldname**

Name of dimension (string) to be defined.

### **dim**

The size (long) of the dimension.

## Keywords

None

## Examples

In this example, we define a track geolocation dimension, GeoTrack, of size 2000, a cross track dimension, GeoXtrack, of size 1000 and two corresponding data dimensions with twice the resolution of the geolocation dimensions:

```
status = EOS_SW_DEFDIM(swathID, "GeoTrack", 2000)
status = EOS_SW_DEFDIM(swathID, "GeoXtrack", 1000)
status = EOS_SW_DEFDIM(swathID, "DataTrack", 4000)
status = EOS_SW_DEFDIM(swathID, "DataXtrack", 2000)
status = EOS_SW_DEFDIM(swathID, "Bands", 5)
```

To specify an unlimited dimension that can be used to define an appendable array, the dimension value should be set to zero:

```
status = EOS_SW_DEFDIM(swathID, "Unlim", 0)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFDIMMAP

This function defines monotonic mapping between the geolocation and data dimensions. Typically the geolocation and data dimensions are of different size (resolution). This function establishes the relation between the two where the offset gives the index of the data element (0-based) corresponding to the first geolocation element and the increment gives the number of data elements to skip for each geolocation element. If the geolocation dimension begins “before” the data dimension, then the offset is negative. Similarly, if the geolocation dimension has higher resolution than the data dimension, then the increment is negative. A typical reason for failure is an incorrect geolocation or data dimension name.

## Syntax

*Result* = EOS\_SW\_DEFDIMMAP(*swathID*, *geodim*, *datadim*, *offset*, *increment*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **geodim**

Geolocation dimension name (string).

### **datadim**

Data dimension name (string).

### **offset**

The offset (long) of the geolocation dimension with respect to the data dimension.

### **increment**

The increment (long) of the geolocation dimension with respect to the data dimension.

## Keywords

None

## Examples

In this example, we establish the following:

- The first element of the GeoTrack dimension corresponds to the first element of the DataTrack dimension and the data dimension has twice the resolution of the geolocation dimension.
- The first element of the GeoXtrack dimension corresponds to the second element of the DataTrack dimension and the data dimension has twice the resolution of the geolocation dimension.

```
status=EOS_SW_DEFDIMMAP(swathID, "GeoTrack", "DataTrack", 0, 2)
status=EOS_SW_DEFDIMMAP(swathID, "GeoXtrack", "DataXtrack", 1, 2)
```




Figure 5-1:

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFGEOFIELD

This function defines geolocation fields to be stored in the swath. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, `numbertype`. If the merge keyword is not set, the API will not attempt to merge it with other fields. Fields using the unlimited dimension will not be merged. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF field directly using HDF routines. To assure that the fields defined by `EOS_SW_DEFGEOFIELD` are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_SW_DEFGEOFIELD( swathID, fieldname, dimlist, numbertype  
[, /MERGE] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field (string) to be defined.

### dimlist

The list of geolocation dimensions (string) defining the field.

## numbertype

The HDF data type (long) of the data stored in the field.

## Keywords

### MERGE

If set, automatic merging will occur. By default, fields are not merged.

## Examples

In this example, we define the geolocation fields, Longitude and Latitude with dimensions GeoTrack and GeoXtrack and containing 4 byte floating point numbers. We allow these fields to be merged into a single object:

```
status = EOS_SW_DEFGEOFIELD(swathID, "Longitude", $
    "GeoTrack,GeoXtrack", 5, /MERGE
status = EOS_SW_DEFGEOFIELD(swathID, "Latitude", $
    "GeoTrack,GeoXtrack", 5, /MERGE
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFIDXMAP

If there does not exist a regular (linear) mapping between a geolocation and data dimension, then the mapping must be made explicit. Each element of the index array, whose dimension is given by the geolocation size, contains the element number (0-based) of the corresponding data dimension.

## Syntax

*Result* = EOS\_SW\_DEFIDXMAP(*swathID*, *geodim*, *datadim*, *index*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### geodim

Geolocation dimension name (string).

### datadim

Data dimension name (string).

### index

The array (long) containing the indices of the data dimension to which each geolocation element corresponds.

## Keywords

None

## Examples

In this example, we consider the (simple) case of a geolocation dimension `IdxGeo` of size 5 and a data dimension `IdxData` of size 8. In this case, the 0th element of `IdxGeo`



will correspond to the 0th element of IdxDData, the 1st element of IdxGeo to the 2nd element of IdxDData, etc.:

```
index = [0,2,3,6,7]
status = EOS_SW_DEFIDXMAP(swathID, "IdxGeo", "IdxData", index)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFTIMEPERIOD

This function defines a time period for a swath. It returns a swath period ID which is used by the EOS\_SW\_EXTRACTPERIOD function to read all the entries of a data field within the time period. A cross track is within a time period if its midpoint is within the time period box (0), or either of its endpoints is within the time period box (1), or any point of the cross track is within the time period box (2), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the time period even though a particular element of the cross track might be outside the time period. The swath structure must have the Time field defined.

## Syntax

*Result* = EOS\_SW\_DEFTIMEPERIOD(*swathID*, *starttime*, *stoptime*, *mode*)

## Return Value

Returns the swath period ID if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### starttime

Start time (double) of period.

### stoptime

Stop time (double) of period.

### mode

Cross Track inclusion mode (long). Allowable values are:

- 0 = Midpoint
- 1 = Endpoint
- 2 = Anypoint

## Keywords

None

## Examples

In this example, we define a time period with a start time of 35232487.2 and a stop time of 36609898.1. We will consider a cross track to be within the time period if either one of the time values at the endpoints of a cross track are within the time period:

```
starttime = 35232487.2d
stoptime = 36609898.1d
periodID = EOS_SW_DEFTIMEPERIOD(swathID, starttime, stoptime, 1)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DEFVRTREGION

Whereas the `EOS_SW_DEFBOXREGION` and `EOS_SW_DEFTIMEPERIOD` functions perform subsetting along the “Track” dimension, this function allows the user to subset along any dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range (case 2). In the second case, the field must be one-dimensional and the values must be monotonic (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this function, the second option is restricted to fields with one of the following HDF data types: 22, 24, 5, 6.)

This function may be called after `EOS_SW_DEFBOXREGION` or `EOS_SW_DEFTIMEPERIOD` to provide both geographic or time and “vertical” subsetting. In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This function may also be called “stand-alone” by setting the input id to (-1).

This function may be called up to eight times with the same region ID. In this way a region can be subsetted along a number of dimensions.

The `EOS_SW_REGIONINFO` and `EOS_SW_EXTRACTREGION` functions work as before, however, because there is no mapping performed between geolocation dimensions and data dimensions the field to be subsetted, (the field specified in the call to `EOS_SW_REGIONINFO` and `EOS_SW_EXTRACTREGION`) must contain the dimension used explicitly in the call to `EOS_SW_DEFVRTREGION` (case 1) or the dimension of the one-dimensional field (case 2).

## Syntax

*Result* = `EOS_SW_DEFVRTREGION`(*swathID*, *regionID*, *vertObj*, *range*)

## Return Value

Returns the swath region ID if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by `EOS_SW_CREATE` or `EOS_SW_ATTACH`.

## regionID

Region or period id (long) from previous subset call, or -1 to create a new region within the entire dataset.

## vertObj

Dimension or field (string) to subset by.

## range

Minimum and maximum range (double) for subset.

## Keywords

None

## Examples

Suppose we have a field called Pressure of dimension Height whose values increase from 100 to 1000, and we desire all the elements with values between 500 and 800:

```
range[0] = 500.d
range[1] = 800.d
regionID = EOS_SW_DEFVRTREGION(swathID, -1, "Pressure", range)
```

The function determines the elements in the Height dimension that correspond to the values of the Pressure field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the Height dimension, the call would be:

```
range[0] = 2.d
range[1] = 5.d
regionID = EOS_SW_DEFVRTREGION(swathID, -1, "DIM:Height", range)
```

The “DIM:” prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field. In this example, any field to be subsetted must contain the Height dimension.

If a previous subset region or period was defined with an id of subsetID that we wish to refine further with the vertical subsetting defined above, we make the call:

```
regionID = EOS_SW_DEFVRTREGION(swathID, subsetID, $
    "Pressure", range)
```

The return value, `regionID`, is set equal to `subsetID`. That is, the subset region is modified rather than a new one created. We can further refine the subset region with another call to the function:

```
freq[0] = 1540.3d
freq[1] = 1652.8d
regionID = EOS_SW_DEFVRTREGION(swathID, regionID, $
    "FreqRange", freq)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_DETACH

This function detaches from the swath interface. It should be run before exiting from the swath file for every swath opened by `EOS_SW_CREATE` or `EOS_SW_ATTACH`.

## Syntax

```
Result = EOS_SW_DETACH(swathID)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

## Keywords

None

## Examples

```
status = EOS_SW_DETACH(swathID)
```

## Version History

5.2	Introduced
-----	------------

## See Also

[EOS\\_SW\\_ATTACH](#)

# EOS\_SW\_DIMINFO

This function retrieves the size of the specified dimension.

## Syntax

```
Result = EOS_SW_DIMINFO(swathID, dimname)
```

## Return Value

Size of dimension or FAIL (-1) if the swath ID or dimension name are invalid.

## Arguments

### **swathID**

Swath id (long).

### **dimname**

Dimension name (string).

## Keywords

None

## Examples

In this example, we retrieve information about the dimension, “GeoTrack”:

```
dimsize = EOS_SW_DIMINFO(swathID, "GeoTrack")
```

## Version History

5.2	Introduced
-----	------------



# EOS\_SW\_DUPREGION

This function copies the information stored in a current region or period to a new region or period and generates a new id. It is useful when the user wishes to further subset a region (period) in multiple ways.

## Syntax

*Result* = EOS\_SW\_DUPREGION(*regionID*)

## Return Value

Returns new region or period ID or FAIL (-1) on error.

## Arguments

### regionID

Region or period id (long) returned by EOS\_SW\_DEFBOXREGION, EOS\_SW\_DEFTIMEPERIOD, or EOS\_SW\_DEFVRTREGION.

## Keywords

None

## Examples

In this example, we first subset a swath with EOS\_SW\_DEFBOXREGION, duplicate the region creating a new region ID, regionID2, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = EOS_SW_DEFBOXREGION(swathID, cornerlon, $
    cornerlat, 0)
regionID2 = EOS_SW_DUPREGION(regionID)
regionID = EOS_SW_DEFVRTREGION(swathID, regionID, $
    "Pressure", rangePres)
regionID2 = EOS_SW_DEFVRTREGION(swathID, regionID2, $
    "Temperature", rangeTemp)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_EXTRACTPERIOD

This function reads data into the data buffer from the subsetted time period. Only complete crosstracks are extracted. If the `external_mode` flag is set to (1) then the geolocation fields and the data field can be in different swaths. If set to (0), then these fields must be in the same swath structure.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_SW_EXTRACTPERIOD(swathID, periodID, fieldname,  
                               external_mode, buffer)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

**swathID**

Swath id (long).

**periodID**

Period id (long) returned by EOS\_SW\_DEFTIMEPERIOD.

**fieldname**

Field to subset (string).

**external\_mode**

External geolocation mode (long).

## buffer

A named variable that will contain the period data.

## Keywords

None

## Examples

In this example, we read data within the subsetted time period defined in EOS\_SW\_DEFTIMEPERIOD from the Spectra field. Both the geolocation fields and the Spectra data field are in the same swath.

```
status = EOS_SW_EXTRACTPERIOD(EOS_SW_id, periodID, 0, "Spectra", $
    datbuf)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_EXTRACTREGION

This function reads data into the data buffer from the subsetted region. Only complete crosstracks are extracted. If the `external_mode` flag is set to (1) then the geolocation fields and the data field can be in different swaths. If set to (0), then these fields must be in the same swath structure.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_SW_EXTRACTREGION(swathID, regionID, fieldname,  
                               external_mode, buffer)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **regionID**

Region id (long) returned by [EOS\\_SW\\_DEFBOXREGION](#).

### **fieldname**

Field to subset (string).

### **external\_mode**

External geolocation mode (long).

## buffer

A named variable that will contain the data buffer.

## Keywords

None

## Examples

In this example, we read data within the subsetted region defined in EOS\_SW\_DEFBOXREGION from the Spectra field. Both the geolocation fields and the Spectra data field are in the same swath.

```
status = EOS_SW_EXTRACTREGION(EOS_SW_id, regionID, 0, "Spectra", $
    datbuf)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_FIELDINFO

This function retrieves information on a specific data field.

## Syntax

```
Result = EOS_SW_FIELDINFO(swathID, fieldname, rank, dims, numbertype,  
dimlist)
```

## Return Value

Returns SUCCEED(0) if successful and FAIL(-1) if the specified field does not exist.

## Arguments

### **swathID**

Swath id (long).

### **fieldname**

Fieldname (string).

### **rank**

A named variable that will contain the rank of field (long).

### **dims**

A named variable that will contain the array of length “rank” (long) containing the dimension sizes of the field. If one of the dimensions in the field is appendable, then the current value for that dimension will be returned in the dims array.

### **numbertype**

A named variable that will contain HDF data type of the field.

### **dimlist**

A named variable that will contain the list of dimensions (string) in field.

## Keywords

None

## Examples

In this example, we retrieve information about the Spectra data fields:

```
status = EOS_SW_FIELDINFO(swathID, "Spectra", rank, dims, $
    numbertype, dimlist)
```

## Version History

5.2	Introduced
-----	------------



# EOS\_SW\_GETFILLVALUE

This function retrieves the fill value for the specified field.

## Syntax

*Result* = EOS\_SW\_GETFILLVALUE(*swathID*, *fieldname*, *fillvalue*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Fieldname (string).

### fillvalue

A named variable that will contain the fill value.

## Keywords

None

## Examples

In this example, we get the fill value for the “Temperature” field:

```
status = EOS_SW_GETFILLVALUE(swathID, "Temperature", tempfill)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_IDXMAPINFO

This function retrieves the size of the indexed array and the array of indexed elements of the specified geolocation mapping.

## Syntax

```
Result = EOS_SW_IDXMAPINFO(swathID, geodim, datadim, index)
```

## Return Value

Returns size of indexed array if successful and FAIL (-1) if the specified mapping does not exist.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **geodim**

Geolocation dimension name (string).

### **datadim**

Data dimension name (string).

### **index**

A named variable that will contain an array (long) of indices of the data dimension to which each geolocation element corresponds.

## Keywords

None

## Examples

In this example, we retrieve information about the indexed mapping between the “IdxGeo” and “IdxData” dimensions:

```
idxsz = EOS_SW_IDXMAPINFO(swathID, "IdxGeo", "IdxData", index)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQATTRS

This function retrieves information about attributes defined in swath. The attribute list is returned as a string with each attribute name separated by commas.

**Note**

See [STRSPLIT](#) to separate the attribute list.

---

## Syntax

*Result* = EOS\_SW\_INQATTRS( *swathID*, *attrlist* [, **LENGTH**=*variable*] )

## Return Value

Number of attributes found or (-1) if failure.

## Arguments

**swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

**attrlist**

A named variable that will contain the attribute list (string) with entries separated by commas.

## Keywords

**LENGTH**

Set this keyword to a named variable that will contain the length of the attribute list as a long integer.

## Examples

```
nattr = EOS_SW_INQATTRS(swathID, attrlist)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQDATAFIELDS

This function retrieves information about all of the data fields defined in swath. The field list is returned as a string with each data field separated by commas. The rank and numbertype arrays will have an entry for each field.

---

**Note**

See [STRSPLIT](#) to separate the field list.

---

## Syntax

*Result* = EOS\_SW\_INQDATAFIELDS(*swathID*, *fieldlist*, *rank*, *numbertype*)

## Return Value

Returns number of data fields found. If -1, could signify improper swath id.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **fieldlist**

A named variable that will contain the listing of data fields (string) with entries separated by commas.

### **rank**

A named variable that will contain an array (long) of rank of each data field.

### **numbertype**

A named variable that will contain an array (long) of numbertype of each data field.

## Keywords

None

## Examples

```
nflds = EOS_SW_INQDATAFIELDS(swathID, fieldlist, rank, numbertype)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQDIMS

This function retrieves information about all of the dimensions defined in swath. The dimension list is returned as a string with each dimension name separated by commas.

**Note**

See [STRSPLIT](#) to separate the dimension list.

## Syntax

*Result* = EOS\_SW\_INQDIMS(*swathID*, *dimname*, *dim*)

## Return Value

Returns number of dimension entries found. If -1, could signify an improper swath id.

## Arguments

**swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

**dimname**

A named variable that will contain the dimension list (string) with entries separated by commas.

**dims**

A named variable that will contain an array (long) of size of each dimension.

## Keywords

None

## Examples

```
ndims = EOS_SW_INQDIMS(swathID, dimname, dims)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQGEOFIELDS

This function retrieves information about all of the geolocation fields defined in swath. The field list is returned as a string with each geolocation field separated by commas. The rank and numbertype arrays will have an entry for each field.

---

**Note**

See [STRSPLIT](#) to separate the field list.

---

## Syntax

*Result* = EOS\_SW\_INQGEOFIELDS(*swathID*, *fieldlist*, *rank*, *numbertype*)

## Return Value

Returns number of geolocation fields found. If -1, could signify an improper swath id.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldlist

A named variable that will contain the listing of geolocation fields (string) with entries separated by commas.

### rank

A named variable that will contain an array (long) of the rank of each geolocation field.

### numbertype

A named variable that will contain an array (long) of the numbertype of each geolocation field.

## Keywords

None

## Examples

```
nflds = EOS_SW_INQGEOFIELDS(swathID, fieldlist, rank, numbertype)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQIDXMAPS

This function retrieves information about all of the indexed geolocation/data mappings defined in swath. The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/).

---

**Note**

See [STRSPLIT](#) to separate the mapping list.

---

## Syntax

*Result* = EOS\_SW\_INQIDXMAPS(*swathID*, *idxmap*, *idxsizes*)

## Return Value

Number of indexed mapping relations found. If -1, could signify an improper swath id.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### idxmap

A named variable that will contain the indexed Dimension mapping list (string) with entries separated by commas.

### idxsizes

A named variable that will contain an array (long) of the sizes of the corresponding index arrays.

## Keywords

None

## Examples

```
nidxmaps = EOS_SW_INQIDXMAPS(swathID, idxmap, idxsizes)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQMAPS

This function retrieves information about all of the (non-indexed) geolocation relations defined in swath. The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/).

---

**Note**

See [STRSPLIT](#) to separate the mapping list.

---

## Syntax

*Result* = EOS\_SW\_INQMAPS(*swathID*, *dimmap*, *offset*, *increment*)

## Return Value

Number of geolocation relation entries found. If -1, could signify an improper swath id.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### dimmap

A named variable that will contain the dimension mapping list (string) with entries separated by commas.

### offset

A named variable that will contain an array (long) of the offset of each geolocation relation.

### increment

A named variable that contain an array (long) of the increment of each geolocation relation.

## Keywords

None

## Examples

```
nmaps = EOS_SW_INQMAPS(swathID, dimmap, offset, increment)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_INQSWATH

This function retrieves number and names of swaths defined in the HDF-EOS file. The swath list is returned as a string with each swath name separated by commas.

---

**Note**

See [STRSPLIT](#) to separate the swath list.

---

## Syntax

*Result* = EOS\_SW\_INQSWATH(*filename*, *swathlist* [, **LENGTH** =*value*])

## Return Value

Number of swaths found or (-1) if failure.

## Arguments

**filename**

HDF-EOS filename (string).

**swathlist**

Swath list (string) with entries separated by commas.

## Keywords

**LENGTH**

String length (long) of swath list.

## Examples

In this example, we retrieve information about the swaths defined in an HDF-EOS file, HDFEOS.hdf:

```
nswath = EOS_SW_INQSWATH("HDFEOS.hdf", swathlist)
```



## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_MAPINFO

This function retrieves the offset and increment of the specified geolocation mapping.

## Syntax

*Result* = EOS\_SW\_MAPINFO(*swathID*, *geodim*, *datadim*, *offset*, *increment*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) if the specified mapping does not exist.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **geodim**

Geolocation dimension name (string).

### **datadim**

Data dimension name (string).

### **offset**

A named variable that will contain the mapping offset (long).

### **increment**

A named variable that will contain the mapping increment (long).

## Keywords

None

## Examples

In this example, we retrieve information about the mapping between the GeoTrack and DataTrack dimensions:

```
status = EOS_SW_MAPINFO(swathID, "GeoTrack", "DataTrack", $  
    offset, increment)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_NENTRIES

This function returns number of entries and descriptive string buffer size for a specified entity. This function can be called before an inquiry routine in order to determine the sizes of the output arrays and descriptive strings.

## Syntax

*Result* = EOS\_SW\_NENTRIES( *swathID*, *entrycode* [, **LENGTH**=*variable*] )

## Return Value

Number of entries or FAIL (-1) in the case of an improper swath id or entry code.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### entrycode

Entrycode (long). Allowable values are:

- 0 = Dimensions
- 1 = Dimension Mappings
- 2 = Indexed Dimension Mappings
- 3 = Geolocation Fields
- 4 = Data Fields

## Keywords

### LENGTH

Set this keyword to a named variable that will contain the length of the string that would be returned by the corresponding inquiry routine, as a long integer.

## Examples

In this example, we determine the number of dimension mapping entries.

```
nmaps = EOS_SW_NENTRIES(swathID, 2)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_OPEN

This function creates a new file or opens an existing file.

## Syntax

```
Result = EOS_SW_OPEN(filename [, /CREATE] [, /RDWR | , /READ] )
```

## Return Value

Returns the swath file id handle (fid) if successful and FAIL (-1) otherwise.

## Arguments

### filename

Complete path and filename for the file to be opened (string).

## Keywords

### CREATE

If file exists, delete it, then open a new file for read/write.

### RDWR

Open for read/write, If file does not exist, create it.

### READ

Open for read only. If file does not exist, error. This is the default.

## Examples

In this example, we create a new swath file named, SwathFile.hdf. It returns the file handle, fid:

```
fid = EOS_SW_OPEN("SwathFile.hdf", /CREATE)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_PERIODINFO

This function returns information about a subsetted time period for a particular field. Because of differences in number type and geolocation mapping, a given time period will give different values for the dimensions and size for various fields.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See “[Note on Array Ordering](#)” on page 579 for details.

---

## Syntax

*Result* = EOS\_SW\_PERIODINFO(*swathID*, *periodID*, *fieldname*, *ntype*, *rank*, *dims*, *size*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **periodID**

Period id (long) returned by EOS\_SW\_DEFTIMEPERIOD.

### **fieldname**

Field to subset (string).

### **ntype**

A named variable that will contain the number type of field (long).

### **rank**

A named variable that will contain the rank of field (long).



**dims**

A named variable that will contain the dimensions of subset period (long).

**size**

A named variable that will contain the size in bytes of subset period (long).

**Keywords**

None

**Examples**

In this example, we retrieve information about the time period defined in EOS\_SW\_DEFTIMEPERIOD for the Spectra field:

```
; Get size in bytes of time period for "Spectra" field
status = EOS_SW_PERIODINFO(EOS_SW_id, periodID, $
    "Spectra", ntype, rank, dims, size)
```

**Version History**

5.2	Introduced
-----	------------

# EOS\_SW\_QUERY

The EOS\_SW\_QUERY function returns information about a specified swath.

## Syntax

*Result*=EOS\_SW\_QUERY(*Filename*, *SwathName*, [*Info*])

## Return Value

This function returns an integer value of 1 if the file is an HDF file with EOS SWATH extensions, and 0 otherwise.

## Arguments

### Filename

A string containing the name of the file to be queried.

### SwathName

A string containing the name of the swath to be queried.

### Info

Returns an anonymous structure containing information about the specified swath. The returned structure contains the following fields:

Field	IDL data type	Description
ATTRIBUTES	String array	Array of attribute names
DIMENSION_NAMES	String array	Names of dimensions
DIMENSION_SIZES	Long array	Sizes of dimensions
FIELD_NAMES	String array	Names of fields
FIELD_RANKS	Long array	Ranks (dimensions) of fields
FIELD_TYPES	Long array	IDL types of fields

Table 5-4: Fields of the Info Structure

Field	IDL data type	Description
GEO_FIELD_NAMES	String array	Names of geolocation fields
GEO_FIELD_RANKS	Long array	Ranks (dimensions) of geolocation fields
GEO_FIELD_TYPES	Long array	IDL types of geolocation fields
IDX_MAP_NAMES	String array	Names of index maps
IDX_MAP_SIZES	Long array	Sizes of index map arrays
NUM_ATTRIBUTES	Long	Number of attributes
NUM_DIMS	Long	Number of dimensions
NUM_FIELDS	Long	Number of fields
NUM_GEO_FIELDS	Long	Number of geolocation fields
NUM_IDX_MAPS	Long	Number of indexed dimension mapping entries
NUM_MAPS	Long	Number of mapping entries
MAP_INCREMENTS	Long array	Increment of each geolocation relation
MAP_NAMES	String array	Names of maps
MAP_OFFSETS	Long array	Offset of each geolocation relation

Table 5-4: Fields of the Info Structure (Continued)

## Keywords

None

## Version History

5.3	Introduced
-----	------------

# EOS\_SW\_READATTR

This function reads attributes from a swath field.

## Syntax

```
Result = EOS_SW_READATTR(swathID, attrname, datbuf)
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

A named variable that will contain the attribute values.

## Keywords

None

## Examples

In this example, we read a single precision (32-bit) floating-point attribute with the name "ScalarFloat":

```
status = EOS_SW_READATTR(swathID, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_READFIELD

This function reads data from a swath field. The values within start, stride, and edge arrays refer to the swath field (input) dimensions. The default values for start and stride are 0 and 1 respectively if these keywords are not set. The default value for edge is  $(\text{dim} - \text{start}) / \text{stride}$  where dim refers to the IDL variable dimension.

## Note

---

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

```
Result = EOS_SW_READFIELD( swathID, fieldname, buffer [, EDGE=array]  
                        [, START=array] [, STRIDE=array] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field to read (string).

### buffer

A named variable that will contain the data read from the field.

## Keywords

### EDGE

Array (long) specifying the number of values to read along each dimension.

## START

Array (long) specifying the starting location within each dimension.

## STRIDE

Set this keyword to an array of integers specifying the number of values to step along each dimension. The default is [1, 1, ...] indicating that every value should be included. Specifying a stride of 0 is equivalent to 1.

## Examples

In this example, we read data from the 10th track (0-based) of the Longitude field:

```
start=[10,1]
edge=[1,1000]
status = EOS_SW_READFIELD(swathID, "Longitude", track, $
    START = start, EDGE = edge)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_REGIONINFO

This function returns information about a subsetted region for a particular field. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_SW\_REGIONINFO(*swathID*, *regionID*, *fieldname*, *ntype*, *rank*, *dims*, *size*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### **swathID**

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### **regionID**

Region id (long) returned by [EOS\\_SW\\_DEFBOXREGION](#).

### **fieldname**

Field to subset (string).

### **ntype**

A named variable that will contain the number type of field (long).

### **rank**

A named variable that will contain the rank of field (long).

**dims**

A named variable that will contain the dimensions of subset region (long).

**size**

A named variable that will contain the size in bytes of subset region (long).

**Keywords**

None

**Examples**

In this example, we retrieve information about the region defined in EOS\_SW\_DEFBOXREGION for the Spectra field:

```
status = EOS_SW_REGIONINFO(EOS_SW_id, regionID, "Spectra", $
    ntype, rank, dims, size)
```

**Version History**

5.2	Introduced
-----	------------



# EOS\_SW\_SETFILLVALUE

This function sets the fill value for the specified field. The fill value is placed in all elements of the field that have not been explicitly defined.

## Syntax

*Result* = EOS\_SW\_SETFILLVALUE(*swathID*, *fieldname*, *fillvalue*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or EOS\_SW\_\_ATTACH.

### fieldname

Fieldname (string).

### fillvalue

The fill value to be used.

## Keywords

None

## Examples

In this example, we set a fill value for the “Temperature” field:

```
tempfill = -999.0
status = EOS_SW_SETFILLVALUE(swathID, "Temperature", tempfill)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_WRITEATTR

This function writes/updates attributes in a swath. If the attribute does not exist, it is created. If it does exist, then the value is updated.

## Syntax

```
Result = EOS_SW_WRITEATTR( swathID, attrname, datbuf [, COUNT=value]
    [, HDF_TYPE=value] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### attrname

Attribute name (string).

### datbuf

Attribute values (long). If HDF\_TYPE is specified, the attribute values are first converted to the type specified by HDF\_TYPE before being stored.

## Keywords

### COUNT

Number of values to store in attribute (long).

### HDF\_TYPE

HDF data type of the attribute. See “[IDL and HDF Data Types](#)” on page 317 for valid values.

## Examples

In this example, we write a single precision (32 bit) floating point number with the name “ScalarFloat” and the value 3.14:

```
f32 = 3.14
status = EOS_SW_WRITEATTR(swathid, "ScalarFloat", f32)
```

We can update this value by simply calling the function again with the new value:

```
f32 = 3.14159
status = EOS_SW_WRITEATTR(swathid, "ScalarFloat", f32)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_WRITEDATAMETA

This function writes field metadata for an existing data field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the EOS\_SW\_DEFDIM function before this function is called.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_SW\_WRITEDATAMETA(*swathID*, *fieldname*, *dimlist*, *numbertype*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field (string).

### dimlist

The list of data dimensions defining the field (string).

### numbertype

The number type of the data stored in the field (long).

## Keywords

None

## Examples

In this example, we write the metadata for the “Band\_1” data field used in the swath:

```
status = EOS_SW_WRITEDATAMETA(swathID, "Band_1", $
    "GeoTrack,GeoXtrack", 5)
```

## Version History

5.2	Introduced
-----	------------

# EOS\_SW\_WRITEFIELD

This function writes data to a swath field. The values within start, stride, and edge arrays refer to the swath field (output) dimensions. The default values for start and stride are 0 and 1 respectively and are used if keywords are not set. The default value for edge is  $(\text{dim} - \text{start}) / \text{stride}$  where dim refers to the size of the dimension. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See “[Note on Array Ordering](#)” on page 579 for details.

---

## Syntax

```
Result = EOS_SW_WRITEFIELD( swathID, fieldname, data [, EDGE=array]  
    [, START=array] [, STRIDE=array] )
```

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field to write (string).

### data

Values to be written to the field.

## Keywords

### EDGE

Array (long) specifying the number of values to write along each dimension.

### START

Array (long) specifying the starting location within each dimension (0-based).

### STRIDE

Set this keyword to an array of integers specifying the number of values to step along each dimension. The default is [1, 1, ...] indicating that every value should be included. Specifying a stride of 0 is equivalent to 1.

## Examples

In this example, we write data to the Longitude field:

```

; Define elements of longitude array:
longitude = indgen(2000, 1000)
status = EOS_SW_WRITEFIELD(swathID,"Longitude", longitude)
; We now update Track 10 (0 - based) in this field:
newtrack = intarr (1,1000)
start=[10,0]
edge =[1,1000]
; Define elements of newtrack array:
status = EOS_SW_WRITEFIELD(swathID, "Longitude",newtrack, $
    START = start, EDGE = edge)

```

## Version History

5.2	Introduced
-----	------------



# EOS\_SW\_WRITEGEOMETA

This function writes field metadata for an existing geolocation field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the EOS\_SW\_DEFDIM function before this function is called.

---

**Note**

Array ordering of variables used or returned by this routine changed in IDL 5.5. Programs written for versions of this routine prior to IDL 5.5 may need to be modified to work correctly with the current version. See [“Note on Array Ordering”](#) on page 579 for details.

---

## Syntax

*Result* = EOS\_SW\_WRITEGEOMETA(*swathID*, *fieldname*, *dimlist*, *numbertype*)

## Return Value

Returns SUCCEED (0) if successful and FAIL (-1) otherwise.

## Arguments

### swathID

Swath id (long) returned by [EOS\\_SW\\_CREATE](#) or [EOS\\_SW\\_ATTACH](#).

### fieldname

Name of field (string).

### dimlist

The list of geolocation dimensions (string) defining the field.

### numbertype

The number type of the data (long) stored in the field.

## Keywords

None

## Examples

In this example, we write the metadata for the “Latitude” geolocation field used in the swath:

```
status = EOS_SW_WRITEGEOMETA(swathID, $
    "Latitude", "GeoTrack,GeoXtrack", 5)
```

## Version History

5.2	Introduced
-----	------------

## Keywords

None



## Chapter 6

# Network Common Data Format

The following topics are covered in this appendix:

---

Overview of NetCDF . . . . .	820	Type Conversion . . . . .	826
NetCDF Data Modes . . . . .	821	Specifying Attributes and Variables . . . . .	827
Attributes, Dimensions, and Variables . . . . .	822	String Data in NetCDF Files . . . . .	828
Creating NetCDF Files . . . . .	823	Alphabetical Listing of NCDF Routines . . . . .	829

# Overview of NetCDF

The network Common Data Format (netCDF) is a self-describing scientific data access interface and library developed at the Unidata Program Center in Boulder, Colorado. The netCDF interface and library use XDR (eXternal Data Representation) to make the data format machine-independent. This version of IDL supports netCDF 3.5. IDL's NetCDF routines all begin with the prefix "NCDF\_".

More information about netCDF can be found on Unidata's netCDF World Wide Web home page which can be found at:

<http://www.unidata.ucar.edu/packages/netcdf/>

Further information and the original netCDF documentation can be obtained from Unidata at the following addresses:

UCAR Unidata Program Center  
P.O. Box 3000  
Boulder, Colorado, USA 80307  
(303) 497-8644  
e-mail: [support@unidata.ucar.edu](mailto:support@unidata.ucar.edu)

## NetCDF Data Modes

There are two modes associated with accessing a netCDF file: *define* mode and *data* mode. In define mode, dimensions, variables, and new attributes can be created but variable data cannot be read or written. In data mode, data can be read or written and attributes can be changed, but new dimensions, variables, and attributes cannot be created.

IDL's `NCDF_CONTROL` routine can be used control the mode of a netCDF file. The only time it is not necessary to set the mode with `NCDF_CONTROL` is when using the `NCDF_CREATE` procedure to create a new file. `NCDF_CREATE` places the new netCDF file into define mode automatically.

# Attributes, Dimensions, and Variables

The three basic components of a netCDF file are described below.

## Attributes

Attributes can contain auxiliary information about an entire netCDF file (*global* attributes) or about a single netCDF variable. Every attribute has a name, data type, and length associated with it. It is common to repeat attribute names for each variable. For example, every variable in a netCDF file might have an attribute named “Units”. Note however, that variables cannot have multiple attributes with the same names.

## Dimensions

Dimensions are named integers that are used to specify the size (or *dimensionality*) of one or more variables. Each dimension must have a unique name, but a variable and dimension can share a name. Each netCDF file is allowed to have one boundless (or *unlimited*) dimension. Most often the unlimited dimension is used as a temporal variable, allowing data to be appended to an existing netCDF file. An example of this use is shown later.

## Variables

Variables are multidimensional arrays of values of the same data type. Each variable has a size, type, and name associated with it. Variables can also have *attributes* that describe them.

# Creating NetCDF Files

The following IDL commands should be used to create a new netCDF file:

- `NCDF_CREATE`: Call this procedure to begin creating a new file. The new file is put into *define* mode.
- `NCDF_DIMDEF`: Create dimensions for the file.
- `NCDF_VARDEF`: Define the variables to be used in the file.
- `NCDF_ATTPUT`: Optionally, use attributes to describe the data.
- `NCDF_CONTROL`, `/ENDEF`: Call `NCDF_CONTROL` and set the `ENDEF` keyword to leave *define* mode and enter *data* mode.
- `NCDF_VARPUT`: Write the appropriate data to the netCDF file.
- `NCDF_CLOSE`: Close the file.

## Reading NetCDF Files

The following commands should be used to read data from a netCDF file:

- `NCDF_OPEN`: Open an existing netCDF file.
- `NCDF_INQUIRE`: Call this function to find the format of the netCDF file.
- `NCDF_DIMINQ`: Retrieve the names and sizes of dimensions in the file.
- `NCDF_VARINQ`: Retrieve the names, types, and sizes of variables in the file.
- `NCDF_ATTNAME`: Optionally, retrieve attribute names.
- `NCDF_ATTINQ`: Optionally, retrieve the types and lengths of attributes.
- `NCDF_ATTGET`: Optionally, retrieve the attributes.
- `NCDF_VARGET`: Read the data from the variables.
- `NCDF_CLOSE`: Close the file.

If the structure of the netCDF file is already known, the inquiry routines do not need to be called—only `NCDF_OPEN`, `NCDF_ATTGET`, `NCDF_VARGET`, and `NCDF_CLOSE` would be needed.

## NetCDF Examples

### Example Code

Two example files that demonstrate the use of the netCDF routines can be found in the `examples/doc/sdf` subdirectory of the IDL distribution. The file `ncdf_cat.pro` prints a summary of basic information about a netCDF file. The file `ncdf_rdwr.pro` creates a new netCDF file and then reads the information back from that file.

### A Complete Example with Unlimited Dimensions

The following example shows how to create a netCDF file, populate it with data, read data from the file, and make a simple plot from the data. The resulting graphic is shown below.




Figure 6-1: SHOW3 result of unlimited dimensions example



```

; Create a new NetCDF file with the filename inquire.nc:
id = NCDF_CREATE('inquire.nc', /CLOBBER)
; Fill the file with default values:
NCDF_CONTROL, id, /FILL
; We'll create some time-dependent data, so here is an
; array of hours from 0 to 5:
hours = INDGEN(5)
; Create a 5 by 10 array to hold floating-point data:
data = FLTARR(5,10)
; Generate some values.
FOR i=0,9 DO $
    data(*,i) = (i+0.5) * EXP(-hours/2.) / SIN((i+1)/30.*!PI)
xid = NCDF_DIMDEF(id, 'x', 10)      ; Make dimensions.
zid = NCDF_DIMDEF(id, 'z', /UNLIMITED)
; Define variables:
hid = NCDF_VARDEF(id, 'Hour', [zid], /SHORT)
vid = NCDF_VARDEF(id, 'Temperature', [xid,zid], /FLOAT)
NCDF_ATTPUT, id, vid, 'units', 'Degrees x 100 F'
NCDF_ATTPUT, id, vid, 'long_name', 'Warp Core Temperature'
NCDF_ATTPUT, id, hid, 'long_name', 'Hours Since Shutdown'
NCDF_ATTPUT, id, /GLOBAL, 'Title', 'Really important data'
; Put file in data mode:
NCDF_CONTROL, id, /ENDEF
; Input data:
NCDF_VARPUT, id, hid, hours
FOR i=0,4 DO NCDF_VARPUT, id, vid, $
; Oops! We forgot the 6th hour! This is not a problem, however,
; as you can dynamically expand a netCDF file if the unlimited
; dimension is used.
    REFORM(data(i,*)), OFFSET=[0,i]
; Add the hour and data:
NCDF_VARPUT, id, hid, 6, OFFSET=[5]
; Add the temperature:
NCDF_VARPUT, id, vid, FINDGEN(10)*EXP(-6./2), OFFSET=[0,5]
; Read the data back out:
NCDF_VARGET, id, vid, output_data
NCDF_ATTGET, id, vid, 'long_name', ztitle
NCDF_ATTGET, id, hid, 'long_name', ytitle
NCDF_ATTGET, id, vid, 'units', subtitle
!P.CHARSIZE = 2.5
!X.TITLE = 'Location'
!Y.TITLE = STRING(ytitle) ; Convert from bytes to strings.
!Z.TITLE = STRING(ztitle) + '!C' + STRING(subtitle)
NCDF_CLOSE, id ; Close the NetCDF file.
SHOW3, output_data ; Display the data.

```

# Type Conversion

Values are converted to the appropriate type before being written to a netCDF file. For example, in the commands below, IDL converts the string “12” to a floating-point 12.0 before writing it:

```
varid=NCDF_VARDEF(fileid, 'VarName', [d0,d1,d2+d3], /FLOAT)  
NCDF_VARPUT, fileid, 'VarName', '12'
```

## Specifying Attributes and Variables

Variables and attributes can be referred to either by name or by their ID numbers in most netCDF routines. For example, given the NCDF\_VARDEF command shown below, the two NCDF\_VARPUT commands shown after it are equivalent:

```
varid = NCDF_VARDEF(fileid, 'VarName', [d0,d1,d2+d3], /FLOAT)
; Reference by variable name:
NCDF_VARPUT, fileid, 'VarName', '12'
; Reference by variable ID:
NCDF_VARPUT, fileid, varid, '12'
```

## String Data in NetCDF Files

Strings are stored as arrays of ASCII bytes in netCDF files. To read string data from netCDF files, use the `STRING` function to convert bytes back into characters. When writing an IDL string array to a variable, an extra dimension (the maximum string length) must be added to the variable definition. Both of these situations are illustrated by the following example:

```

; Make a test string:
string_in = REPLICATE('Test String',10,10)
; Make one element longer than the others:
string_in(0,0) = 'Long Test String'
HELP, string_in
; Create a new netCDF file:
ncdfid = NCDF_CREATE('string.nc', /CLOBBER)
; Define first dimension:
xid = NCDF_DIMDEF(ncdfid, 'height', 10)
; Define second dimension:
yid = NCDF_DIMDEF(ncdfid, 'width', 10)
; Find the length of the longest string and use that as the
; third dimension:
zid = NCDF_DIMDEF(ncdfid, 'length', MAX(STRLEN(string_in)))
; Define the variable with dimensions zid, yid, xid:
id = NCDF_VARDEF(ncdfid, 'strings', [zid,yid,xid], /CHAR)
; Put the file into define mode:
NCDF_CONTROL, ncdfid, /ENDEF
; Write the string variable. The array will be stored as bytes
; in the file:
NCDF_VARPUT, ncdfid, id, string_in
; Read the byte array back out:
NCDF_VARGET, ncdfid, id, byte_out
NCDF_CLOSE, ncdfid ; Close the file.
HELP, byte_out
; IDL reports that BYTE_OUT is a (16, 10, 10) BYTE array.
PRINT, STRING(byte_out(*,0,0))
; Taking the STRING of the first "row" of byte_out returns the
; first element of our original array, "Long Test String".
; Convert the entire byte array back into strings:
string_new = STRING(byte_out)
; The new string array has the same dimensions and values as
; our original string, string_in.
HELP, string_new
; This statement compares the two arrays and prints "Success!" if
; they are equal, and they are:
IF TOTAL(string_in NE string_new) EQ 0 THEN PRINT, 'Success!'

```

# Alphabetical Listing of NCDF Routines

NCDF\_ATTCOPY  
NCDF\_ATTDEL  
NCDF\_ATTGET  
NCDF\_ATTINQ  
NCDF\_ATTNAME  
NCDF\_ATTPUT  
NCDF\_ATTRENAME  
NCDF\_CLOSE  
NCDF\_CONTROL  
NCDF\_CREATE  
NCDF\_DIMDEF  
NCDF\_DIMID  
NCDF\_DIMINQ  
NCDF\_DIMRENAME  
NCDF\_EXISTS  
NCDF\_INQUIRE  
NCDF\_OPEN  
NCDF\_VARDEF  
NCDF\_VARGET  
NCDF\_VARID  
NCDF\_VARINQ  
NCDF\_VARPUT  
NCDF\_VARRENAME

# NCDF\_ATTCOPY

The `NCDF_ATTCOPY` function copies an attribute from one netCDF file to another. Note that *Incdf* and *Outcdf* can be the same netCDF ID.

## Syntax

```
Result = NCDF_ATTCOPY( Incdf [, Invar ] , Name, Outcdf [, Outvar]
    [, /IN_GLOBAL] [, /OUT_GLOBAL] )
```

## Return Value

`NCDF_ATTCOPY` returns the attribute number of the copied attribute in the new file, or -1 if the copy was not successful.

## Arguments

### Incdf

The netCDF ID, returned from a previous call to `NCDF_OPEN` or `NCDF_CREATE`.

### Invar

The netCDF variable ID to be read, returned from a previous call to `NCDF_VARDEF` or `NCDF_VARID`, or the name of the variable. If the `IN_GLOBAL` keyword is set, this argument must be omitted.

### Name

A scalar string containing the name of the attribute to be copied.

### Outcdf

The netCDF ID of a netCDF file opened for writing, returned from a previous call to `NCDF_OPEN` or `NCDF_CREATE`.

### Outvar

The netCDF variable ID to be written, returned from a previous call to `NCDF_VARDEF` or `NCDF_VARID`, or the name of the variable. If the `OUT_GLOBAL` keyword is set, this argument must be omitted.

## Keywords

### **IN\_GLOBAL**

Set this keyword to read a global attribute.

### **OUT\_GLOBAL**

Set this keyword to create a global attribute.

## Examples

See example from [“NCDF\\_ATTINQ”](#) on page 836.

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_ATTDEL

The NCDF\_ATTDEL procedure deletes an attribute from a netCDF file.

## Syntax

```
NCDF_ATTDEL, Cdfid [, Varid] , Name [, /GLOBAL]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable. If the GLOBAL keyword is used, this argument must be omitted.

### Name

A scalar string containing the name of the attribute to be deleted.

## Keywords

### GLOBAL

Set this keyword to delete a global variable.

## Examples

```
; Open file test.nc for writing:
id = NCDF_OPEN('test.nc', /WRITE)
; Delete global attribute TITLE from the file:
NCDF_ATTDEL, id, 'TITLE', /GLOBAL
NCDF_CLOSE, id ; Close the file.
```



## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTNAME](#), [NCDF\\_ATTPUT](#)

# NCDF\_ATTGET

The `NCDF_ATTGET` procedure retrieves the value of an attribute from a netCDF file.

## Syntax

```
NCDF_ATTGET, Cdfid [, Varid] , Name, Value [, /GLOBAL]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to `NCDF_OPEN` or `NCDF_CREATE`.

### Varid

The netCDF variable ID, returned from a previous call to `NCDF_VARDEF` or `NCDF_VARID`, or the name of the variable. If the `GLOBAL` keyword is used, this argument must be omitted.

### Name

A scalar string containing the attribute name.

### Value

A named variable in which the attribute's value is returned. `NCDF_ATTGET` sets *Value*'s size and data type appropriately.

## Keywords

### GLOBAL

Set this keyword to retrieve the value of a global attribute.

## Examples

For an example using this routine, see the documentation for [NCDF\\_ATTINQ](#).

## Version History

---

Pre 4.0	Introduced
---------	------------

---

## See Also

[NCDF\\_ATTINQ](#), [NCDF\\_ATTNAME](#), [NCDF\\_ATTPUT](#)

# NCDF\_ATTINQ

The NCDF\_ATTINQ function returns a structure that contains information about a netCDF attribute. This structure, described below, has the form:

```
{ DATATYPE:'', LENGTH:0L }
```

## Syntax

*Result* = NCDF\_ATTINQ( *Cdfid* [, *Varid*] , *Name* [, /GLOBAL])

## Return Value

The structure returned by this function contains the following tags:

Tag	Description
DataType	A string describing the data type of the variable. The string will be one of the following: BYTE, CHAR, INT, LONG, FLOAT, or DOUBLE.
Length	The number of values stored in the attribute. If the attribute is a string, the number of values indicates one more character than the string length to include the terminating null character. This is the NetCDF convention, as demonstrated in the following example.

Table 6-1: NCDF\_ATTINQ Structure Tags

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable. If the GLOBAL keyword is set, this argument must be omitted.

## Name

A scalar string containing the name of the attribute for which information is to be returned.

## Keywords

### GLOBAL

Set this keyword to inquire about a global variable. If this keyword is set, the *Varid* argument must be omitted.

## Examples

```

id = NCDF_CREATE('test.nc', /CLOBBER ; Open a new netCDF file.
id2 = NCDF_CREATE('test2.nc', /CLOBBER ; Open a second file.
; Create two global attributes TITLE and DATE:
NCDF_ATTPUT, id, /GLOBAL, 'TITLE', 'MY TITLE'
NCDF_ATTPUT, id, /GLOBAL, 'DAY', 'July 1,1996'
; Suppose we wanted to use DATE instead of DAY. We could use
; ATTRENAME to rename the attribute:
NCDF_ATTRENAME, id, 'DAY', 'DATE', /GLOBAL
; Next, copy both attributes into a duplicate file:
result = NCDF_ATTCOPY(id, 'TITLE', id2, /IN_GLOBAL, /OUT_GLOBAL)
result2 = NCDF_ATTCOPY(id, 'DATE', id2, /IN_GLOBAL, /OUT_GLOBAL)
; Put the file into data mode:
NCDF_CONTROL, id, /ENDEF
; Get the second attribute's name:
name = NCDF_ATTNAME(id, /GLOBAL, 1)
; Retrieve the date:
NCDF_ATTGET, id, /GLOBAL, name, date
; Get info about the attribute:
result = NCDF_ATTINQ(id, /GLOBAL, name)
HELP, name, date, result, /STRUCTURE
PRINT, date
PRINT, STRING(date)
NCDF_DELETE, id ; Close the netCDF files.
NCDF_DELETE, id2

```

### IDL Output

```

NAME                STRING      = 'DATE'
DATE                BYTE        = Array(12)
** Structure <400dac30>, 2 tags, length=12, refs=1:
  DATATYPE          STRING      'BYTE'
  LENGTH            LONG        12

```

Note the length includes the NCDF standard NULL terminator

```
74 117 108 121 32 49 44 49 57 57 54 0
```

July 1, 1996

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTDEL](#), [NCDF\\_ATTGET](#), [NCDF\\_ATTNAME](#), [NCDF\\_ATTPUT](#)

# NCDF\_ATTNAME

The NCDF\_ATTNAME function returns the name of an attribute in a netCDF file given its ID.

## Syntax

```
Result = NCDF_ATTNAME( Cdfid [, Varid] , Attnum [, /GLOBAL])
```

## Return Value

Returns the specified attribute's name or the NULL string ("") if there is no such attribute.

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable. If the GLOBAL keyword is set, this argument must be omitted.

### Attnum

An expression containing the number of the desired attribute. The attributes for each variable are numbered from 0 to the number-of-attributes minus 1. Note that the number of attributes can be found using NCDF\_VARINQ or NCDF\_INQUIRE (to find the number of global variables).

## Keywords

### GLOBAL

Set this keyword to return the name of one of the global attributes.

## Version History

---

Pre 4.0	Introduced
---------	------------

---

## See Also

[NCDF\\_ATTINQ](#)



# NCDF\_ATTPUT

The NCDF\_ATTPUT procedure creates an attribute in a netCDF file. If the attribute is new, or if the space required to store the attribute is greater than before, the netCDF file must be in *define* mode.

## Syntax

```
NCDF_ATTPUT, Cdfid [, Varid] , Name , Value [, /GLOBAL] [, LENGTH=value]
           [, /BYTE | , /CHAR | , /DOUBLE | , /FLOAT | , /LONG | , /SHORT]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable. If the GLOBAL keyword is set, this argument must be omitted.

### Name

A scalar string containing the attribute name.

### Warning

---

The *Name* string may contain only alphanumeric characters and the `-`, `_`, and `.` characters.

---

### Value

An expression containing the data to be written. Although this procedure checks that there are a sufficient number of bytes of data, the data type is not checked or altered.

## Keywords

### GLOBAL

Set this keyword to create a global attribute.

## LENGTH

Use this keyword to override the default length (the whole value). Set this keyword to a value less than or equal to the number of elements in *Value*. For example:

```
ATTR_ID = NCDF_ATTPUT(CDFID, VARID, 'Attr1', $
    INDGEN(10), LENGTH=5
```

writes Attr1 as [0,1,2,3,4].

The following keywords specify a non-default data type for the variable. By default, NCDF\_ATTPUT chooses one based upon the type of data. If a data type flag is specified, the data supplied in *Value* is converted to that data type before being written to the file. Only one of these keywords can be used in a single call to NCDF\_ATTPUT.

## BYTE

Set this keyword to indicate that the data is composed of bytes.

## CHAR

Set this keyword to indicate that the data is composed of bytes (assumed to be ASCII).

## DOUBLE

Set this keyword to indicate that the data is composed of 8-byte floating point numbers (doubles).

## FLOAT

Set this keyword to indicate that the data is composed of 4-byte floating point numbers (floats).

## LONG

Set this keyword to indicate that the data is composed of 4-byte integers (longs).

## SHORT

Set this keyword to indicate that the data is composed of 2-byte integers.

## Examples

```
NCDF_ATTPUT, cdfid, /GLOBAL, "Title", "My Favorite Data File"
NCDF_ATTPUT, cdfid, "data", "scale_factor", 12.5D
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTINQ](#)

# NCDF\_ATTRENAME

The NCDF\_ATTRENAME procedure renames an attribute in a netCDF file.

## Syntax

```
NCDF_ATTRENAME, Cdfid [, Varid] Oldname, Newname [, /GLOBAL]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable. If the GLOBAL keyword is set, this argument must be omitted.

### OldName

A scalar string containing the attribute's current name.

### NewName

A scalar string containing the attribute's new name.

## Keywords

### GLOBAL

Set this keyword to rename a global attribute.

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTINQ](#)

# NCDF\_CLOSE

The NCDF\_CLOSE procedure closes an open netCDF file. If a writable netCDF file is not closed before exiting IDL, the disk copy of the netCDF file may not reflect recent data changes or new definitions.

## Syntax

NCDF\_CLOSE, *Cdfid*

## Arguments

### Cdfid

The netCDF ID of the file to be closed, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

## Keywords

None

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTINQ](#)

# NCDF\_CONTROL

The NCDF\_CONTROL procedure performs miscellaneous netCDF operations.

Different options are controlled by keywords. Only one keyword can be specified in any call to NCDF\_CONTROL, unless the OLDFILL keyword is specified.

## Syntax

```
NCDF_CONTROL, Cdfid [, /ABORT] [, /ENDEF] [, /FILL | , /NOFILL]  
[, /NOVERBOSE | , /VERBOSE] [, OLDFILL=variable] [, /REDEF] [, /SYNC]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

## Keywords

### ABORT

Set this keyword to close a netCDF file that is not in define mode. If the file is being created and is still in define mode, the file is deleted. If define mode was entered by a call to NCDF\_CONTROL with the REDEF keyword, the netCDF file is restored to its state before definition mode was entered, and the file is closed.

### ENDEF

Set this keyword to take an open netCDF file out of define mode (and into data mode).

## FILL

Set this keyword so that data in the netCDF file is pre-filled with default fill values. The default values (which cannot be changed) are:

Data Type	Fill Value
BYTE	0
CHAR	0
SHORT	-32767
LONG	-2147483647
FLOAT	9.96921E+36
DOUBLE	9.96921E+36

Table 6-2: Default Fill Values for netCDF Files

## NOFILL

Set this keyword so that data in the netCDF file is not pre-filled. This option saves time when it is certain that variable values will be written before a read is attempted.

## NOVERBOSE

Set this keyword to suppress the printing of netCDF error messages. *Cdfid* is required but not used.

## OLDFILL

This keyword specifies a named variable in which the previous fill value is returned. This keyword can only be used in combination with the FILL or NOFILL keywords. For example:

```
NCDF_CONTROL, id, FILL=1, OLDFILL=previous_fill
```

## REDEF

Set this keyword to put an open netCDF file into define mode.



## SYNC

Set this keyword to update the disk copy of a netCDF file that is open for writing. The netCDF file must be in data mode. A netCDF file in define mode will be updated only when `NCDF_CONTROL` is called with the `ENDEF` keyword.

## VERBOSE

Set this keyword to cause netCDF error messages to be printed. *Cdfid* is required but not used. For example:

```
NCDF_CONTROL, 0, /VERBOSE
```

is a valid command even if 0 is not a valid NetCDF file ID.

## Examples

See the examples under [NCDF\\_ATTINQ](#) and [NCDF\\_VARPUT](#).

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_CLOSE](#), [NCDF\\_CREATE](#), [NCDF\\_OPEN](#)

# NCDF\_CREATE

The NCDF\_CREATE function creates a new netCDF file.

## Syntax

```
Result = NCDF_CREATE( Filename [, /CLOBBER | , /NOCLOBBER] )
```

## Return Value

If successful, the netCDF ID for the file is returned. The newly-created netCDF file is automatically placed into define mode. If you do not have write permission to create the specified Filename, NCDF\_CREATE returns an error message instead of a netCDF file ID.

## Arguments

### Filename

A scalar string containing the name of the file to be created

## Keywords

### CLOBBER

Set this keyword to erase the existing file (if the file already exists) before creating the new version.

### NOCLOBBER

Set this keyword to create a new netCDF file only if the specified file does not already exist. This is the default.

## Examples

```
; Open a new NetCDF File and destroy test.nc if it already exists:  
id = NCDF_CREATE('test.nc', /CLOBBER)  
  
id2 = NCDF_CREATE('test.nc', /NOCLOBBER)
```

This attempt to create a new version of the file `test.nc` produces the following error because the `NOCLOBBER` keyword was set:

```
nccreate: filename "test.nc": File exists
% NCDF_CREATE: Operation failed
% Execution halted at $MAIN$ (NCDF_CREATE).
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_CLOSE](#), [NCDF\\_CONTROL](#), [NCDF\\_OPEN](#)

# NCDF\_DIMDEF

The NCDF\_DIMDEF function defines a dimension in a netCDF file given its name and size.

## Syntax

```
Result = NCDF_DIMDEF( Cdfid, DimName, Size [, /UNLIMITED] )
```

## Return Value

If successful, the dimension ID is returned.

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### DimName

A scalar string containing the name of the dimension being defined.

### Size

The size of the dimension. *Size* can be any scalar expression. If the UNLIMITED keyword is used, the *Size* parameter should be omitted.

## Keywords

### UNLIMITED

Set this keyword to create a dimension of unlimited size. Note that only one dimension in a netCDF file can be unlimited.

## Examples

See [NCDF\\_VARPUT](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_DIMID

The NCDF\_DIMID function returns the ID of a netCDF dimension, given the name of the dimension.

## Syntax

```
Result = NCDF_DIMID( Cdfid, DimName )
```

## Return Value

Return the dimension ID or -1 if the dimension does not exist.

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### DimName

A scalar string containing the dimension name.

## Keywords

None

## Examples

See [NCDF\\_VARPUT](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_DIMINQ

The NCDF\_DIMINQ procedure retrieves the name and size of a dimension in a netCDF file, given its ID. The size for the unlimited dimension, if any, is the maximum value used so far in writing data for that dimension.

## Syntax

NCDF\_DIMINQ, *Cdfid*, *Dimid*, *Name*, *Size*

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Dimid

The netCDF dimension ID, returned from a previous call to NCDF\_DIMID or NCDF\_DIMDEF, or an indexed number from 0 to NDIMS-1 that indexes the desired dimension. The first dimension has a DIMID of 0, the second dimension has a DIMID of 1, and so on.

### Name

A named variable in which the dimension name is returned (a scalar string).

### Size

A named variable in which the size of the dimension is returned (a scalar longword integer)

## Keywords

None

## Examples

See [NCDF\\_VARPUT](#).

## Version History

Pre 4.0	Introduced
---------	------------



# NCDF\_DIMRENAME

The NCDF\_DIMRENAME procedure renames an existing dimension in a netCDF file which has been opened for writing. If the new name is longer than the old name, the netCDF file must be in define mode. You cannot rename one dimension to have the same name as another dimension.

## Syntax

NCDF\_DIMRENAME, *Cdfid*, *Dimid*, *NewName*

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Dimid

The netCDF dimension ID, returned from a previous call to NCDF\_DIMID or NCDF\_DIMDEF, or the name of the dimension.

### NewName

A scalar string containing the new name for the dimension.

## Keywords

None

## Examples

See [NCDF\\_VARPUT](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_EXISTS

The NCDF\_EXISTS function returns true if the Network Common Data Format (netCDF) scientific data format library is supported on the current IDL platform.

This routine is written in the IDL language. Its source code can be found in the file `ncdf_exists.pro` in the `lib` subdirectory of the IDL distribution.

## Syntax

*Result* = NCDF\_EXISTS()

## Return Value

Returns true if the library is supported.

## Arguments

None

## Keywords

None

## Examples

The following IDL command prints an error message if the NetCDF library is not available:

```
IF NCDF_EXISTS() EQ 0 THEN PRINT, 'NCDF not supported.'
```

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_INQUIRE

The NCDF\_INQUIRE function returns a structure that contains information about an open netCDF file. This structure of the form:

```
{ NDIMS:0L, NVAR:0L, NGATTR:0L, RECDIM:0L }
```

The structure tags are described below.

## Syntax

```
Result = NCDF_INQUIRE(Cdfid)
```

## Return Value

The returned structure contains the following tags:

Tag	Description
Ndims	The number of dimensions defined for this netCDF file.
Nvars	The number of variables defined for this netCDF file.
Ngatts	The number of global attributes defined for this netCDF file.
RecDim	The ID of the unlimited dimension, if there is one, for this netCDF file. If there is no unlimited dimension, RecDim is set to -1.

Table 6-3: NCDF\_INQUIRE Structure Tags

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

## Keywords

None

## Examples

See [NCDF\\_VARDEF](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_OPEN

The NCDF\_OPEN function opens an existing netCDF file.

## Syntax

```
Result = NCDF_OPEN( Filename [, /NOWRITE | , /WRITE] )
```

## Return Value

If successful, the netCDF ID for the file is returned.

## Arguments

### Filename

A scalar string containing the name of the file to be opened.

## Keywords

### NOWRITE

Set this keyword to open an existing netCDF file as read only. This is the default.

### WRITE

Set this keyword to open an existing netCDF file for both writing and reading.

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_ATTINQ](#)

# NCDF\_VARDEF

The `NCDF_VARDEF` function adds a new variable to an open netCDF file in define mode.

## Syntax

```
Result = NCDF_VARDEF( Cdfid, Name [, Dim] [, /BYTE | /CHAR | /DOUBLE | /FLOAT | /LONG | /SHORT ] )
```

## Return Value

If successful, the variable ID is returned. If a new variable cannot be defined, `NCDF_VARDEF` returns -1.

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to `NCDF_OPEN` or `NCDF_CREATE`.

### Name

A scalar string containing the variable name.

### Dim

An optional vector containing the dimension IDs corresponding to the variable dimensions. If the ID of the unlimited dimension is included, it must be the rightmost element in the array. If *Dim* is omitted, the variable is assumed to be a scalar.

## Keywords

The following keywords specify the data type for the variable. Only one of these keywords can be used. If no data type keyword is specified, `FLOAT` is used by default.

### BYTE

Set this keyword to indicate that the data is composed of bytes.

## CHAR

Set this keyword to indicate that the data is composed of bytes (assumed to be ASCII).

## DOUBLE

Set this keyword to indicate that the data is composed of double-precision floating-point numbers.

## FLOAT

Set this keyword to indicate that the data is composed of floating-point numbers.

## LONG

Set this keyword to indicate that the data is composed of longword integers.

## SHORT

Set this keyword to indicate that the data is composed of 2-byte integers.

## Examples

```

id = NCDF_CREATE('test.nc', /CLOBBER) ; Create the netCDF file.
NCDF_ATTPUT, id, 'TITLE', 'Incredibly Important Data', /GLOBAL
NCDF_ATTPUT, id, 'GALAXY', 'Milky Way', /GLOBAL
NCDF_ATTPUT, id, 'PLANET', 'Earth', /GLOBAL
xid = NCDF_DIMDEF(id, 'x', 100) ; Define the X dimension.
yid = NCDF_DIMDEF(id, 'y', 200) ; Define the Y dimension.
zid = NCDF_DIMDEF(id, 'z', /UNLIMITED) ; Define the Z dimension.
vid0 = NCDF_VARDEF(id, 'image0', [yid, xid], /FLOAT)
vid1 = NCDF_VARDEF(id, 'image1', [yid, xid], /FLOAT)
; Rename image0 to dist_image:
dist_id = NCDF_VARID(id, 'image0')
NCDF_VARRENAME, id, vid0, 'dist_image'
NCDF_ATTPUT, id, vid, 'TITLE', 'DIST_IMAGE'
NCDF_CONTROL, id, /ENDEF ; Put the file into data mode.
image = CONGRID(DIST(200), 200, 100)
NCDF_VARPUT, id, vid, image
INQ_VID = NCDF_VARINQ(id, 'dist_image')
HELP, INQ_VID, /STRUCTURE
file_inq = NCDF_INQUIRE(id)
HELP, file_inq, /STRUCTURE
NCDF_CLOSE, id ; Close the NetCDF file.

```

## IDL Output

```

** Structure <400ec678>, 5 tags, length=32, refs=1:
  NAME           STRING      'dist_image'
  DATATYPE       STRING      'FLOAT'
  NDIMS          LONG         2
  NATTS          LONG         1
  DIM            LONG         Array(2)
** Structure <400ebdf8>, 4 tags, length=16, refs=1:
  NDIMS          LONG         3
  NVAR           LONG         2
  NGATTS        LONG         3
  RECDIM        LONG         2

```

## Version History

Pre 4.0	Introduced
---------	------------



# NCDF\_VARGET

The NCDF\_VARGET procedure retrieves a hyperslab of values from a netCDF variable. The netCDF file must be in *data* mode to use this procedure.

## Syntax

```
NCDF_VARGET, Cdfid, Varid, Value [, COUNT=vector] [, OFFSET=vector]  
[, STRIDE=vector]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable.

### Value

A named variable in which the values are returned. NCDF\_VARGET sets *Value*'s size and data type as appropriate.

## Keywords

### COUNT

An optional vector containing the counts to be used in reading *Value*. COUNT is a 1-based vector with an element for each dimension of the data to be written. The default matches the size of the variable so that all data is written out.

### OFFSET

An optional vector containing the starting position for the read. The default start position is [0, 0, ...].

## STRIDE

An optional vector containing the strides, or sampling intervals, between accessed values of the netCDF variable. The default stride vector is that for a contiguous read, [1, 1, ...].

## Examples

Suppose that a 230 by 230 image is saved in the netCDF file `dave.nc`. The following commands extract both the full image and a 70x70 sub-image starting at [80,20] sampling every other X pixel and every third Y pixel:

```

; A variable that contains the offset for the sub-image:
offset = [80, 20]
; The dimensions of the sub-image:
count = [70, 70]
; Create a variable to be used as a value for the STRIDE keyword.
; Every other X element and every third Y element will be sampled:
stride = [2, 3]
; Open the NetCDF file:
id = NCDF_OPEN('dave.nc')
; Get the variable ID for the image:
image = NCDF_VARID(id, 'image')
; Get the full image:
NCDF_VARGET, id, image, fullimage
; Extract the sub-sampled image:
NCDF_VARGET, id, image, subimage, $
    COUNT=count, STRIDE=stride, OFFSET=offset
; Close the NetCDF file:
NCDF_CLOSE, id

```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_VARGET1](#), [NCDF\\_VARID](#), [NCDF\\_VARINQ](#), [NCDF\\_VARPUP](#)

# NCDF\_VARGET1

The NCDF\_VARGET1 procedure retrieves one element from a netCDF variable. The netCDF file must be in *data* mode to use this procedure.

## Syntax

```
NCDF_VARGET1, Cdfid, Varid, Value [, OFFSET=vector]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable.

### Value

A named variable in which the value of the variable is returned. NCDF\_VARGET1 sets *Value*'s size and data type as appropriate.

## Keywords

### OFFSET

A vector containing the starting position of the read. The default starting position is [0, 0, ...].

## Examples

Suppose that the file `dave.nc` contains an image saved with the netCDF variable name “dave”. The following commands extract the value of a single pixel from the image:

```
; The location of the single element (pixel) whose value we will
; retrieve:
offset = [180,190]
; Open the netCDF file:
id = NCDF_OPEN('dave.nc')
```

```
; Get the variable ID for variable "dave":  
varid = NCDF_VARID(id, 'dave')  
; Extract the element and return the value in the variable  
; single_pixel:  
NCDF_VARGET1, id, varid, single_pixel, OFFSET=offset  
; Close the netCDF file:  
NCDF_CLOSE, id
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_VARGET](#), [NCDF\\_VARID](#), [NCDF\\_VARINQ](#), [NCDF\\_VARPUT](#)

# NCDF\_VARID

The NCDF\_VARID function returns the ID of a netCDF variable.

## Syntax

*Result* = NCDF\_VARID(*Cdfid*, *Name*)

## Return Value

This function returns the variable ID or returns -1 if the variable does not exist.

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Name

A scalar string containing the variable name.

## Keywords

None

## Examples

See [NCDF\\_VARDEF](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_VARINQ

The NCDF\_VARINQ function returns a structure that contains information about a netCDF variable, given its ID. This structure has the form:

```
{ NAME:" ", DATATYPE:" ", NDIMS:0L, NATTS:0L, DIM:LONARR(NDIMS) }
```

This structure is described below.

## Syntax

*Result* = NCDF\_VARINQ(*Cdfid*, *Varid*)

## Return Value

The returned structure contains the following tags:

Tag	Description
Name	The name of the variable.
DataType	A string describing the data type of the variable. The string will be one of the following: 'BYTE', 'CHAR', 'INT', 'LONG', 'FLOAT', or 'DOUBLE'.
Ndims	The number of dimensions.
Natts	The number of attributes assigned to this variable.
Dim	A vector of the dimension IDs for the variable dimensions.

Table 6-4: NCDF\_VARINQ Structure Tags

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable.

## Examples

See [NCDF\\_VARDEF](#).

## Version History

Pre 4.0	Introduced
---------	------------

# NCDF\_VARPUT

The NCDF\_VARPUT procedure writes a hyperslab of values to a netCDF variable. The netCDF file must be in *data* mode to use this procedure.

## Syntax

```
NCDF_VARPUT, Cdfid, Varid, Value [, COUNT=vector] [, OFFSET=vector]
[, STRIDE=vector]
```

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable.

### Value

Data values to be written to the netCDF file. If the data type of *Value* does not match that of the netCDF variable, it is converted to the correct data type before writing. *Value* must have a dimensionality less than or equal to that of the variable being written.

## Keywords

### COUNT

An optional vector containing the counts to be used in writing *Value*. COUNT is a 1-based vector with an element for each dimension of the data to be written. Note that counts do not have to match the dimensions of *Value*. The default count vector is the dimensionality of *Value*.

### OFFSET

An optional vector containing the starting position to write. The default start position is [0, 0, ...].



## STRIDE

An optional vector containing the strides, or writing intervals, between written values of the netCDF variable. The default stride vector is that for a contiguous write, [1, 1, ...].

## Examples

Suppose that you wish to create a 100x100 byte (0 & 1) checker board:

```

; Create offsets for even and odd rows:
offset_even = [0,0] & offset_odd = [1,1]
; Create count and stride values:
count = [50,50] & stride = [2,2]
; Make the "black" spaces of the checker board:
black = BYTARR(50,50) > 1B
; Create the netCDF file:
id = NCDF_CREATE('checker.nc', /CLOBBER)
; Fill the file with BYTE zeros:
NCDF_CONTROL, id, /FILL
; Define the X dimension:
xid = NCDF_DIMDEF(id, 'x', 100)
; Define the Y dimension:
yid = NCDF_DIMDEF(id, 'y', 100)
; Define the Z dimension, UNLIMITED:
zid = NCDF_DIMDEF(id, 'yy', /UNLIMITED)
; Define a variable with the name "board":
vid = NCDF_VARDEF(id, 'board', [yid, xid], /BYTE)
; Rename 'yy' to 'z' as the zid dimension name:
NCDF_DIMRENAME, id, zid, 'z'
; Put the file into data mode:
NCDF_CONTROL, id, /ENDEF
; Use NCDF_DIMID and NCDF_DIMINQ to verify the name and size
; of the zid dimension:
check_id = NCDF_DIMID(id, 'z')
NCDF_DIMINQ, id, check_id, dim_name, dim_size
HELP, check_id, dim_name, dim_size

```

IDL prints:

```

CHECK_ID      LONG          =    2
DIM_NAME      STRING       = 'z'
DIM_SIZE      LONG          =    0

```

Note that the DIM\_SIZE is 0 because no records have been written yet for this dimension.

```

NCDF_VARPUT, id, vid, black, $
    COUNT=count, STRIDE=stride, OFFSET=offset_even
NCDF_VARPUT, id, vid, black, $
    COUNT=count, STRIDE=stride, OFFSET=offset_odd
; Get the full image:
NCDF_VARGET, id, vid, output
; Create a window for displaying the image:
WINDOW, XSIZE=100, YSIZE=100
; Display the image:
TVSCL, output
; Make stride larger than possible:
stride = [2,3]
; As an experiment, attempt to write to an array larger than
; the one we previously allocated with NCDF_VARDEF:
NCDF_VARPUT, id, vid, black, $
    COUNT=count, STRIDE=stride, OFFSET=offset_odd

```

IDL prints:

```
% NCDF_VARPUT: Requested write is larger than the available data
area.
```

You will need to change the OFFSET/COUNT/STRIDE, or redefine the variable dimensions. You attempted to access 150 elements in a 100 array.

```
NCDF_CLOSE, id ; Close the netCDF file.
```

## Version History

Pre 4.0	Introduced
---------	------------

## See Also

[NCDF\\_VARGET](#), [NCDF\\_VARGET1](#), [NCDF\\_VARID](#), [NCDF\\_VARINQ](#)

# NCDF\_VARRENAME

The NCDF\_VARRENAME procedure renames a netCDF variable.

## Syntax

NCDF\_VARRENAME, *Cdfid*, *Varid*, *Name*

## Arguments

### Cdfid

The netCDF ID, returned from a previous call to NCDF\_OPEN or NCDF\_CREATE.

### Varid

The netCDF variable ID, returned from a previous call to NCDF\_VARDEF or NCDF\_VARID, or the name of the variable.

### Name

A scalar string containing the new name for the variable.

## Keywords

None

## Examples

See [NCDF\\_VARDEF](#).

## Version History

Pre 4.0	Introduced
---------	------------





# Index

## A

### annotating

- HDF file, [370](#)
- HDF reference numbers, [382](#)
- reading next HDF, [376](#)

### attributes

- copying NCDF, [830](#)
- netCDF, [26](#), [822](#)

## C

### CDF files

#### attributes

- creating, [32](#)
- deleting, [34](#)
- getting information, [40](#)
- obtaining numbers, [42](#)

reading, [38](#)

renaming, [46](#)

retrieving information, [53](#)

setting parameters, [53](#)

writing, [43](#)

CDFvarHyperPut C routine, [113](#)

CDFvarPut C routine, [113](#)

closing, [47](#)

computing epochs, [75](#)

creating

    CDF\_CREATE function, [60](#)

    overview, [28](#)

deleting, [67](#)

determining if library exists, [83](#)

global information about, [84](#)

obtaining explanations of status codes, [82](#)

obtaining information about, [68](#)

opening, [89](#)

## reading

- CDF\_OPEN function, 89

- overview, 28

## retrieving information, 53

- setting parameters, 53

## variables

- creating, 96

- obtaining information, 109

- reading multiple values, 103

- reading one value, 107

- renaming, 115

- retrieving information, 53

- returning numbers, 111

- setting parameters, 53

- writing values to, 113

## CDF, overview, 19

- CDF\_ATTCREATE function, 32

- CDF\_ATTDELETE procedure, 34

- CDF\_ATT EXISTS function, 36

- CDF\_ATTGET procedure, 38

- CDF\_ATTINQ procedure, 40

- CDF\_ATTNUM function, 42

- CDF\_ATTPUT procedure, 43

- CDF\_ATTRENAME procedure, 46

- CDF\_CLOSE procedure, 47, 47

- CDF\_COMPRESSION procedure, 48

- CDF\_CONTROL procedure, 53

- CDF\_CREATE function, 60

- CDF\_DELETE procedure, 67

- CDF\_DOC procedure, 68

- CDF\_ENCODE\_EPOCH function, 70

- CDF\_ENCODE\_EPOCH16 function, 73

- CDF\_EPOCH procedure, 75

- CDF\_EPOCH16 procedure, 78

- CDF\_ERROR function, 82

- CDF\_EXISTS function, 83

- CDF\_INQUIRE function, 84

- CDF\_LIB\_INFO procedure, 87

- CDF\_OPEN function, 89

- CDF\_PARSE\_EPOCH function, 90

- CDF\_PARSE\_EPOCH16 function, 92

- CDF\_SET\_CDF27\_BACKWARD\_COMPATIBLE procedure, 94

- CDF\_VARCREATE function, 96

- CDF\_VARDELETE procedure, 100

- CDF\_VARGET procedure, 103

- CDF\_VARGET1 procedure, 107

- CDF\_VARINQ function, 109

- CDF\_VARNUM function, 111

- CDF\_VARPUT procedure, 113

- CDF\_VARRENAME procedure, 115

## closing

- CDF files, 47

- HDF files, 356

- netCDF files, 846

- Common Data Format *see* CDF files

## D

## data modes

- about netCDF, 821

- setting for netCDF, 847

- data types, HDF, 317

- DATATYPE structure tag, 109

- define mode, 847

- defining, netCDF define mode, 848

- DIM structure tag, 110

- dimensions, netCDF, 822

- DIMVAR structure tag, 110

## E

- EOS\_EH\_CONVANG function, 585

- EOS\_EH\_GETVERSION function, 587

- EOS\_EH\_IDINFO function, 589

- EOS\_EXISTS function, 590

- EOS\_GD\_ATTACH function, 591

- EOS\_GD\_ATTRINFO function, 593

- EOS\_GD\_BLKSOFFSET function, 595

- EOS\_GD\_CLOSE function, 596

- EOS\_GD\_COMPINFO function, 597

EOS\_GD\_CREATE function, 599  
 EOS\_GD\_DEFBOXREGION function, 602  
 EOS\_GD\_DEFCOMP function, 604  
 EOS\_GD\_DEFDIM function, 606  
 EOS\_GD\_DEFFIELD function, 608  
 EOS\_GD\_DEFORIGIN function, 610  
 EOS\_GD\_DEFPIXREG function, 612  
 EOS\_GD\_DEFPROJ function, 613  
 EOS\_GD\_DEFTILE function, 615  
 EOS\_GD\_DEFVRTREGION function, 617  
 EOS\_GD\_DETACH function, 620  
 EOS\_GD\_DIMINFO function, 621  
 EOS\_GD\_DUPREGION function, 622  
 EOS\_GD\_EXTRACTREGION function, 624  
 EOS\_GD\_FIELDINFO function, 626  
 EOS\_GD\_GETFILLVALUE function, 628  
 EOS\_GD\_GETPIXELS function, 629  
 EOS\_GD\_GETPIXVALUES function, 631  
 EOS\_GD\_GRIDINFO function, 633  
 EOS\_GD\_INQATTRS function, 635  
 EOS\_GD\_INQDIMS function, 637  
 EOS\_GD\_INQFIELDS function, 639  
 EOS\_GD\_INQGRID function, 641  
 EOS\_GD\_INTERPOLATE function, 643  
 EOS\_GD\_NENTRIES function, 645  
 EOS\_GD\_OPEN function, 647  
 EOS\_GD\_ORIGININFO function, 649  
 EOS\_GD\_PIXREGINFO function, 650  
 EOS\_GD\_PROJINFO function, 651  
 EOS\_GD\_READATTR function, 655  
 EOS\_GD\_READFIELD function, 656  
 EOS\_GD\_READTILE function, 658  
 EOS\_GD\_REGIONINFO function, 660  
 EOS\_GD\_SETFILLVALUE function, 662  
 EOS\_GD SETTILECACHE function, 664  
 EOS\_GD\_TILEINFO function, 666  
 EOS\_GD\_WRITEATTR function, 668  
 EOS\_GD\_WRITEFIELD function, 670  
 EOS\_GD\_WRITEFIELDMETA function, 672  
 EOS\_GD\_WRITETILE function, 674  
 EOS\_PT\_ATTACH function, 676  
 EOS\_PT\_ATTRINFO function, 678  
 EOS\_PT\_BCKLINKINFO function, 680  
 EOS\_PT\_CLOSE function, 682  
 EOS\_PT\_CREATE function, 683  
 EOS\_PT\_DEFBOXREGION function, 684  
 EOS\_PT\_DEFLEVEL function, 686  
 EOS\_PT\_DEFLINKAGE function, 689  
 EOS\_PT\_DEFTIMEPERIOD function, 691  
 EOS\_PT\_DEFVRTREGION function, 693  
 EOS\_PT\_DETACH function, 695  
 EOS\_PT\_EXTRACTPERIOD function, 696  
 EOS\_PT\_EXTRACTREGION function, 698  
 EOS\_PT\_FWDLINKINFO function, 700  
 EOS\_PT\_GETLEVELNAME function, 702  
 EOS\_PT\_GETRECNUMS function, 704  
 EOS\_PT\_INQATTRS function, 706  
 EOS\_PT\_INQPOINT function, 708  
 EOS\_PT\_LEVELINDX function, 710  
 EOS\_PT\_LEVELINFO function, 711  
 EOS\_PT\_NFIELDS function, 713  
 EOS\_PT\_NLEVELS function, 714  
 EOS\_PT\_NRECS function, 715  
 EOS\_PT\_OPEN function, 716  
 EOS\_PT\_PERIODINFO function, 718  
 EOS\_PT\_PERIODRECS function, 720  
 EOS\_PT\_READATTR function, 724  
 EOS\_PT\_READLEVEL function, 725  
 EOS\_PT\_REGIONINFO function, 727  
 EOS\_PT\_REGIONRECS function, 729  
 EOS\_PT\_SIZEOF function, 731  
 EOS\_PT\_UPDATELEVEL function, 732  
 EOS\_PT\_WRITEATTR function, 734  
 EOS\_PT\_WRITELEVEL function, 736  
 EOS\_QUERY function, 738  
 EOS\_SW\_ATTACH function, 740  
 EOS\_SW\_ATTRINFO function, 742  
 EOS\_SW\_CLOSE function, 744  
 EOS\_SW\_COMPINFO function, 745  
 EOS\_SW\_CREATE function, 747  
 EOS\_SW\_DEFBOXREGION function, 748  
 EOS\_SW\_DEFCOMP function, 750

EOS\_SW\_DEFDATAFIELD function, 752  
 EOS\_SW\_DEFDIM function, 754  
 EOS\_SW\_DEFDIMMAP function, 756  
 EOS\_SW\_DEFGEOFIELD function, 758  
 EOS\_SW\_DEFIDXMAP function, 760  
 EOS\_SW\_DEFTIMEPERIOD function, 762  
 EOS\_SW\_DEFVRTREGION function, 764  
 EOS\_SW\_DETACH function, 767  
 EOS\_SW\_DIMINFO function, 768  
 EOS\_SW\_DUPREGION function, 769  
 EOS\_SW\_EXTRACTPERIOD function, 771  
 EOS\_SW\_EXTRACTREGION function, 773  
 EOS\_SW\_FIELDINFO function, 775  
 EOS\_SW\_GETFILLVALUE function, 777  
 EOS\_SW\_IDXMAPINFO function, 778  
 EOS\_SW\_INQATTRS function, 780  
 EOS\_SW\_INQDATAFIELDS function, 782  
 EOS\_SW\_INQDIMS function, 784  
 EOS\_SW\_INQGEOFIELDS function, 786  
 EOS\_SW\_INQIDXMAPS function, 788  
 EOS\_SW\_INQMAPS function, 790  
 EOS\_SW\_INQSWATH function, 792  
 EOS\_SW\_MAPINFO function, 794  
 EOS\_SW\_NENTRIES function, 796  
 EOS\_SW\_OPEN function, 798  
 EOS\_SW\_PERIODINFO function, 800  
 EOS\_SW\_READATTR function, 804  
 EOS\_SW\_READFIELD function, 805  
 EOS\_SW\_REGIONINFO function, 807  
 EOS\_SW\_SETFILLVALUE function, 809  
 EOS\_SW\_WRITEATTR function, 811  
 EOS\_SW\_WRITEDATAMETA function, 813  
 EOS\_SW\_WRITEFIELD function, 815  
 EOS\_SW\_WRITEGEOMETA function, 817  
 error messages, displaying, netCDF, 849  
 examples  
   SDF  
     hdf\_info.pro, 316, 362, 400  
     hdf\_rdwr.pro, 316  
     ncdf\_cat.pro, 824  
     ncdf\_rdwr.pro, 824

## H

H5\_CLOSE procedure, 143  
 H5\_CREATE procedure, 144  
 H5\_GET\_LIBVERSION function, 149  
 H5\_OPEN procedure, 150  
 H5\_PARSE function, 151  
 H5A\_CLOSE procedure, 157  
 H5A\_CREATE function, 158  
 H5A\_DELETE procedure, 160  
 H5A\_GET\_NAME function, 161  
 H5A\_GET\_NUM\_ATTRS function, 162  
 H5A\_GET\_SPACE function, 163  
 H5A\_GET\_TYPE function, 164  
 H5A\_OPEN\_IDX function, 165  
 H5A\_OPEN\_NAME function, 166  
 H5A\_READ function, 167  
 H5A\_WRITE procedure, 168  
 H5D\_CLOSE procedure, 170  
 H5D\_CREATE function, 171  
 H5D\_EXTEND function, 174  
 H5D\_GET\_SPACE function, 176  
 H5D\_GET\_STORAGE\_SIZE function, 177  
 H5D\_GET\_TYPE function, 178  
 H5D\_OPEN function, 179  
 H5D\_READ function, 180  
 H5D\_WRITE procedure, 184  
 H5F\_CLOSE procedure, 186  
 H5F\_CREATE function, 187  
 H5F\_IS\_HDF5 function, 191  
 H5F\_OPEN function, 192  
 H5G\_CLOSE procedure, 193  
 H5G\_CREATE function, 194  
 H5G\_GET\_COMMENT function, 195  
 H5G\_GET\_LINKVAL function, 196  
 H5G\_GET\_MEMBER\_NAME function, 197  
 H5G\_GET\_NMEMBERS function, 199  
 H5G\_GET\_NUM\_OBJS function, 200  
 H5G\_GET\_OBJ\_NAME\_BY\_IDX function,  
   201  
 H5G\_GET\_OBJINFO function, 202  
 H5G\_LINK procedure, 204



- H5G\_MOVE procedure, 206
- H5G\_OPEN function, 207
- H5G\_SET\_COMMENT procedure, 208
- H5G\_UNLINK procedure, 209
- H5I\_GET\_FILE\_ID function, 210
- H5I\_GET\_TYPE function, 211
- H5R\_CREATE function, 212
- H5R\_DEREFERENCE function, 214
- H5R\_GET\_OBJECT\_TYPE function, 215
- H5R\_GET\_REGION function, 217
- H5S\_CLOSE procedure, 219
- H5S\_COPY function, 220
- H5S\_CREATE\_SCALAR function, 221
- H5S\_CREATE\_SIMPLE function, 222
- H5S\_GET\_SELECT\_BOUNDS function, 224
- H5S\_GET\_SELECT\_ELEM\_NPOINTS function, 225
- H5S\_GET\_SELECT\_ELEM\_POINTLIST function, 226
- H5S\_GET\_SELECT\_HYPER\_BLOCKLIST function, 228
- H5S\_GET\_SELECT\_HYPER\_NBLOCKS function, 230
- H5S\_GET\_SELECT\_NPOINTS function, 231
- H5S\_GET\_SIMPLE\_EXTENT\_DIMS function, 232
- H5S\_GET\_SIMPLE\_EXTENT\_NDIMS function, 233
- H5S\_GET\_SIMPLE\_EXTENT\_NPOINTS function, 234
- H5S\_GET\_SIMPLE\_EXTENT\_TYPE function, 235
- H5S\_IS\_SIMPLE function, 236
- H5S\_OFFSET\_SIMPLE procedure, 237
- H5S\_SELECT\_ALL procedure, 238
- H5S\_SELECT\_ELEMENTS procedure, 239
- H5S\_SELECT\_HYPERSLAB procedure, 241
- H5S\_SELECT\_NONE procedure, 243
- H5S\_SELECT\_VALID function, 244
- H5S\_SET\_EXTENT\_NONE function, 245
- H5S\_SET\_EXTENT\_SIMPLE procedure, 246
- H5T\_ARRAY\_CREATE function, 248
- H5T\_CLOSE procedure, 250
- H5T\_COMMIT procedure, 251
- H5T\_COMMITTED function, 253
- H5T\_COMPOUND\_CREATE function, 254
- H5T\_COPY function, 256
- H5T\_ENUM\_CREATE function, 257
- H5T\_ENUM\_GET\_DATA function, 259
- H5T\_ENUM\_INSERT procedure, 260
- H5T\_ENUM\_NAMEOF function, 261
- H5T\_ENUM\_SET\_DATA procedure, 262
- H5T\_ENUM\_VALUEOF function, 264
- H5T\_ENUM\_VALUES\_TO\_NAMES function, 265
- H5T\_EQUAL function, 267
- H5T\_GET\_ARRAY\_DIMS function, 268
- H5T\_GET\_ARRAY\_NDIMS function, 269
- H5T\_GET\_CLASS function, 270
- H5T\_GET\_CSET function, 272
- H5T\_GET\_EBIAS function, 273
- H5T\_GET\_FIELDS function, 274
- H5T\_GET\_INPAD function, 276
- H5T\_GET\_MEMBER\_CLASS function, 277
- H5T\_GET\_MEMBER\_INDEX function, 279
- H5T\_GET\_MEMBER\_NAME function, 280
- H5T\_GET\_MEMBER\_OFFSET function, 281
- H5T\_GET\_MEMBER\_TYPE function, 282
- H5T\_GET\_MEMBER\_VALUE function, 283
- H5T\_GET\_NMEMBERS function, 284
- H5T\_GET\_NORM function, 285
- H5T\_GET\_OFFSET function, 286
- H5T\_GET\_ORDER function, 287
- H5T\_GET\_PAD function, 288
- H5T\_GET\_PRECISION function, 289
- H5T\_GET\_SIGN function, 290
- H5T\_GET\_SIZE function, 291
- H5T\_GET\_STRPAD function, 292
- H5T\_GET\_SUPER function, 293
- H5T\_GET\_TAG function, 294
- H5T\_IDL\_CREATE function, 295
- H5T\_IDLTYPE function, 298

- H5T\_INSERT procedure, [300](#)
- H5T\_MEMTYPE function, [301](#)
- H5T\_OPEN function, [303](#)
- H5T\_REFERENCE\_CREATE function, [304](#)
- H5T\_SET\_TAG procedure, [305](#)
- H5T\_STR\_TO\_VLEN function, [306](#)
- H5T\_VLEN\_CREATE function, [307](#)
- H5T\_VLEN\_TO\_STR function, [309](#)
- HDF files
  - about, [312](#)
  - annotations
    - adding, [370](#)
    - HDF\_DFAN\_GETFID procedure, [376](#)
    - retrieving reference numbers, [382](#)
  - closing, [356](#)
  - creating files, [315](#)
  - data types, [317](#)
  - descriptions, adding, [369](#)
  - determining if HDF file, [454](#)
  - determining if library exists, [412](#)
  - examples, [316](#)
  - images
    - appending, [395](#)
    - number of, [403](#)
    - reading, [398](#)
    - reading 24-bit, [360](#)
    - reading first 24-bit, [368](#)
    - reading first in file, [409](#)
    - retrieving reference numbers, [401](#)
    - setting reference number
      - HDF\_DF24\_READREF, [367](#)
      - HDF\_DFR8\_READREF, [408](#)
    - writing
      - 24-bit, [358](#)
      - 8-bit, [405](#)
  - interfaces, [313](#)
  - labels, writing, [385](#)
  - models, [313](#)
  - opening, [459](#)
  - overview, [20](#)
  - palettes
    - appending, [390](#)
    - default, [410](#)
    - number of, [389](#)
    - reading, [387](#)
    - reading first in file, [393](#)
    - retrieving reference numbers, [388](#)
    - setting reference number, [394](#)
    - specifying next read, [392](#)
  - palettes, adding, [386](#)
  - references
    - creating, [411](#)
    - returning next, [457](#)
  - scientific dataset ID numbers, [317](#)
  - tag numbers, [319](#)
  - tags
    - deleting, [357](#)
    - number of, [458](#)
    - reading descriptions, [372](#)
    - reading labels, [377](#)
    - retrieving reference numbers and labels, [379](#)
    - writing descriptions, [383](#)
- VData
  - attaching, [519](#)
  - checking object, [543](#)
  - checking result, [568](#)
  - detaching, [531](#)
  - field specifications, [532](#)
  - fields, [534](#)
  - lone, [545](#)
  - moving read pointer, [550](#)
  - reading, [548](#)
  - retrieving
    - field information, [539](#)
    - general information, [536](#)
    - next reference number, [538](#)
    - reference number, [535](#)
    - specifying general information, [551](#)
    - writing, [553](#)
- VGroups
  - adding data to, [567](#)
  - adding tags, [556](#)
  - adding to VGroup, [541](#)

- attaching, [557](#)
- checking object, [544](#)
- checking result, [569](#)
- closing, [559](#)
- detaching, [559](#)
- lone, [570](#)
- number of objects, [571](#)
- opening, [557](#)
- retrieving IDs, [560](#)
- retrieving information about, [561](#)
- retrieving reference numbers, [563](#)
- returning specified tags, [564](#)
- returning tags, [565](#)
- tags, [566](#)
- HDF Library, determining version, [455](#)
- HDF\_AN\_ANNLEN function, [328](#)
- HDF\_AN\_ANNLIST function, [329](#)
- HDF\_AN\_ATYPE2TAG function, [331](#)
- HDF\_AN\_CREATE function, [333](#)
- HDF\_AN\_CREATEF function, [335](#)
- HDF\_AN\_END procedure, [336](#)
- HDF\_AN\_ENDACCESS procedure, [337](#)
- HDF\_AN\_FILEINFO function, [338](#)
- HDF\_AN\_GET\_TAGREF function, [340](#)
- HDF\_AN\_ID2TAGREF function, [342](#)
- HDF\_AN\_NUMANN function, [344](#)
- HDF\_AN\_READANN function, [346](#)
- HDF\_AN\_SELECT function, [347](#)
- HDF\_AN\_START function, [349](#)
- HDF\_AN\_TAG2ATYPE function, [350](#)
- HDF\_AN\_TAGREF2ID function, [352](#)
- HDF\_AN\_WRITEANN function, [354](#)
- HDF\_CLOSE procedure, [356](#)
- HDF\_DELDD procedure, [357](#)
- HDF\_DF24\_ADDIMAGE procedure, [358](#)
- HDF\_DF24\_GETIMAGE procedure, [360](#)
- HDF\_DF24\_GETINFO procedure, [361](#)
- HDF\_DF24\_LASTREF function, [363](#)
- HDF\_DF24\_NIMAGES function, [365](#)
- HDF\_DF24\_READREF procedure, [367](#)
- HDF\_DF24\_RESTART procedure, [368](#)
- HDF\_DFAN\_ADDFDS procedure, [369](#)
- HDF\_DFAN\_ADDFID procedure, [370](#)
- HDF\_DFAN\_GETDESC procedure, [372](#)
- HDF\_DFAN\_GETFDS procedure, [374](#)
- HDF\_DFAN\_GETFID procedure, [376](#)
- HDF\_DFAN\_GETLABEL procedure, [377](#)
- HDF\_DFAN\_LABLIST function, [379](#)
- HDF\_DFAN\_LASTREF function, [382](#)
- HDF\_DFAN\_PUTDESC procedure, [383](#)
- HDF\_DFAN\_PUTLABEL procedure, [385](#)
- HDF\_DFP\_ADDPAL procedure, [386](#)
- HDF\_DFP\_GETPAL procedure, [387](#)
- HDF\_DFP\_LASTREF function, [388](#)
- HDF\_DFP\_NPALS function, [389](#)
- HDF\_DFP\_PUTPAL procedure, [390](#)
- HDF\_DFP\_READREF procedure, [392](#)
- HDF\_DFP\_RESTART procedure, [393](#)
- HDF\_DFP\_WRITEREF procedure, [394](#)
- HDF\_DFR8\_ADDIMAGE procedure, [395](#)
- HDF\_DFR8\_GETIMAGE procedure, [398](#)
- HDF\_DFR8\_GETINFO procedure, [399](#)
- HDF\_DFR8\_LASTREF function, [401](#)
- HDF\_DFR8\_NIMAGES function, [403](#)
- HDF\_DFR8\_PUTIMAGE procedure, [405](#)
- HDF\_DFR8\_READREF procedure, [408](#)
- HDF\_DFR8\_RESTART procedure, [409](#)
- HDF\_DFR8\_SETPALETTE procedure, [410](#)
- HDF\_DUPDD procedure, [411](#)
- HDF\_EXISTS function, [412](#)
- HDF\_GR\_ATTRINFO function, [413](#)
- HDF\_GR\_CREATE function, [415](#)
- HDF\_GR\_END procedure, [417](#)
- HDF\_GR\_ENDACCESS procedure, [418](#)
- HDF\_GR\_FILEINFO function, [419](#)
- HDF\_GR\_FINDATTR function, [421](#)
- HDF\_GR\_GETATTR function, [422](#)
- HDF\_GR\_GETCHUNKINFO function, [424](#)
- HDF\_GR\_GETMININFO function, [426](#)
- HDF\_GR\_GETLUTID function, [428](#)
- HDF\_GR\_GETLUTINFO function, [429](#)
- HDF\_GR\_IDTOREF function, [431](#)

- HDF\_GR\_LUTTOREF function, 432
- HDF\_GR\_NAMETOINDEX function, 433
- HDF\_GR\_READIMAGE function, 434
- HDF\_GR\_READLUT function, 436
- HDF\_GR\_REFTOINDEX function, 437
- HDF\_GR\_SELECT function, 438
- HDF\_GR\_SETATTR function, 439
- HDF\_GR\_SETCHUNK function, 441
- HDF\_GR\_SETCHUNKCACHE function, 443
- HDF\_GR\_SETCOMPRESS function, 444
- HDF\_GR\_SETEXTTERNALFILE function, 446
- HDF\_GR\_START function, 448
- HDF\_GR\_WRITEIMAGE function, 449
- HDF\_GR\_WRITELUT function, 451
- HDF\_HDF2IDLTYPE function, 452
- HDF\_IDL2HDFTYPE function, 453
- hdf\_info.pro, 316, 362, 400
- HDF\_ISHDF function, 454
- HDF\_LIB\_INFO procedure, 455
- HDF\_NEWREF function, 457
- HDF\_NUMBER function, 458
- HDF\_OPEN function, 459
- HDF\_PACKDATA function, 461
- hdf\_rdwr.pro, 316
- HDF\_SD\_ADDDATA procedure, 464
- HDF\_SD\_ATTRFIND function, 467
- HDF\_SD\_ATTRINFO procedure, 469
- HDF\_SD\_ATTRSET procedure, 472
- HDF\_SD\_CREATE function, 476
- HDF\_SD\_DIMGET procedure, 480
- HDF\_SD\_DIMGETID function, 482
- HDF\_SD\_DIMSET function, 484
- HDF\_SD\_END function, 487
- HDF\_SD\_ENDACCESS function, 489
- HDF\_SD\_FILEINFO procedure, 491
- HDF\_SD\_GETDATA procedure, 493
- HDF\_SD\_GETINFO procedure, 495
- HDF\_SD\_IDTOREF function, 498
- HDF\_SD\_ISCOORDVAR function, 500
- HDF\_SD\_NAMETOINDEX function, 501
- HDF\_SD\_REFTOINDEX function, 503
- HDF\_SD\_SELECT function, 505
- HDF\_SD\_SETCOMPRESS procedure, 507
- HDF\_SD\_SETEXTFILE procedure, 509
- HDF\_SD\_SETINFO procedure, 511
- HDF\_SD\_START function, 515
- HDF\_UNPACKDATA procedure, 517
- HDF\_VD\_ATTACH function, 519
- HDF\_VD\_ATTRFIND function, 521
- HDF\_VD\_ATTRINFO procedure, 523
- HDF\_VD\_ATTRSET procedure, 525
- HDF\_VD\_DETACH procedure, 531
- HDF\_VD\_FDEFINE procedure, 532
- HDF\_VD\_FEXIST function, 534
- HDF\_VD\_FIND function, 535
- HDF\_VD\_GET procedure, 536
- HDF\_VD\_GETID function, 538
- HDF\_VD\_GETINFO procedure, 539
- HDF\_VD\_INSERT procedure, 541
- HDF\_VD\_ISATTR function, 542
- HDF\_VD\_ISVD function, 543
- HDF\_VD\_ISVG function, 544
- HDF\_VD\_LONE function, 545
- HDF\_VD\_NATTRS function, 546
- HDF\_VD\_READ function, 548
- HDF\_VD\_SEEK procedure, 550
- HDF\_VD\_SETINFO procedure, 551
- HDF\_VD\_WRITE procedure, 553
- HDF\_VG\_ADDTR procedure, 556
- HDF\_VG\_ATTACH procedure, 557
- HDF\_VG\_DETACH procedure, 559
- HDF\_VG\_GETID function, 560
- HDF\_VG\_GETINFO procedure, 561
- HDF\_VG\_GETNEXT function, 563
- HDF\_VG\_GETTR procedure, 564
- HDF\_VG\_GETTRS procedure, 565
- HDF\_VG\_INQTR function, 566
- HDF\_VG\_INSERT procedure, 567
- HDF\_VG\_ISVD function, 568
- HDF\_VG\_ISVG function, 569
- HDF\_VG\_LONE function, 570

HDF\_VG\_NUMBER function, 571  
 HDF\_VG\_SETINFO procedure, 572  
 HDF5 files, *See also* H5\* files.  
 HDF-EOS, overview, 20, 576  
 Hierarchical Data Format *see* HDF  
 hyperslab, retrieving (netCDF files), 865

## I

ID numbers, scientific datasets, 317  
 images, number of, 403  
 input/output  
   HDF, 312  
   netCDF, 21, 820  
 IS\_ZVAR structure tag, 109

## N

NAME structure tag, 109  
 NCDF\_ATTCOPY function, 830  
 NCDF\_ATTDEL procedure, 832  
 NCDF\_ATTGET procedure, 834  
 NCDF\_ATTINQ function, 836  
 NCDF\_ATTNAME function, 839  
 NCDF\_ATTPUT procedure, 841  
 NCDF\_ATTRENAME procedure, 844  
 ncd\_f\_cat.pro, 824  
 NCDF\_CLOSE procedure, 846  
 NCDF\_CONTROL procedure, 847  
 NCDF\_CREATE function, 850  
 NCDF\_DIMDEF function, 852  
 NCDF\_DIMID function, 854  
 NCDF\_DIMINQ procedure, 855  
 NCDF\_DIMRENAME procedure, 857  
 NCDF\_EXISTS function, 858  
 NCDF\_INQUIRE function, 859  
 NCDF\_OPEN function, 861  
 ncd\_f\_rdwr.pro, 824  
 NCDF\_VARDEF function, 862  
 NCDF\_VARGET procedure, 865

NCDF\_VARGET1 procedure, 867  
 NCDF\_VARID function, 869  
 NCDF\_VARINQ function, 870  
 NCDF\_VARPUT procedure, 872  
 NCDF\_VARENAM procedure, 875  
 netCDF files  
   about, 820  
   attributes  
     about, 26, 822  
     creating, 841  
     creating global, 831  
     deleting, 832  
     obtaining names, 839  
     reading, 834  
     reading global, 831  
     renaming, 844  
     specifying, 827  
   closing, 846  
   creating, 823, 850  
   data modes, 821  
   determining if library exists, 858  
   dimensions  
     about, 822  
     defining, 852  
     obtaining ID, 854  
     obtaining name, 855  
     obtaining size, 855  
     renaming, 857  
   getting information about, 859  
   miscellaneous operations, 847  
   opening, 823, 861  
   reading, 823  
   specifying attributes/variables, 827  
   type conversion, 826  
   updating, 849  
   variables  
     about, 25, 822  
     adding, 862  
     getting ID, 869  
     getting information, 870  
     renaming, 875

- retrieving data from, [865](#)
- retrieving one element, [867](#)
- specifying, [827](#)
- writing values to, [872](#)

Network Common Data Format *see* netCDF

NUMELEM structure tag, [109](#)

## R

RECVAR structure tag, [109](#)

reference numbers (HDF)

- adding to a VGroup, [556](#)

- creating new, [411](#)

- deleting, [357](#)

- returning all from a VGroup, [565](#)

- returning number of, [458](#)

- returning specified from a VGroup, [564](#)

- writing descriptions, [383](#)

## S

scientific data format, overview, [19](#)

strings, in netCDF files, [828](#)

## T

tag numbers, HDF, [319](#)

## V

variable names, [111](#)

variables, netCDF, [25](#)